Norm (mathematics)

From Wikipedia, the free encyclopedia

In linear algebra, functional analysis, and related areas of mathematics, a norm is a function that assigns a strictly positive *length* or *size* to each vector in a vector space—save for the zero vector, which is assigned a length of zero. A seminorm, on the other hand, is allowed to assign zero length to some non-zero vectors (in addition to the zero vector).

A norm must also satisfy certain properties pertaining to scalability and additivity which are given in the formal definition below.

A simple example is the 2-dimensional Euclidean space R² equipped with the Euclidean norm. Elements in this vector space (e.g., (3, 7)) are usually drawn as arrows in a 2-dimensional cartesian coordinate system starting at the origin (0, 0). The Euclidean norm assigns to each vector the length of its arrow. Because of this, the Euclidean norm is often known as the magnitude.

A vector space on which a norm is defined is called a normed vector space. Similarly, a vector space with a seminorm is called a seminormed vector space. It is often possible to supply a norm for a given vector space in more than one way.

Contents

- 1 Definition
- 2 Notation
- 3 Examples
 - 3.1 Absolute-value norm
 - 3.2 Euclidean norm
 - 3.2.1 Euclidean norm of a complex number
 - 3.3 Taxicab norm or Manhattan norm
 - 3.4 *p*-norm
 - 3.5 Maximum norm (special case of: infinity norm, uniform norm, or supremum norm)
 - 3.6 Zero norm
 - 3.6.1 Hamming distance of a vector from zero
 - 3.7 Other norms
 - 3.8 Infinite-dimensional case
- 4 Properties
- 5 Classification of seminorms: absolutely convex absorbing sets
- 6 Generalizations
- 7 See also

第1页 共12页 2016年09月12日 22:14

- 8 Notes
- 9 References

Definition

Given a vector space V over a subfield F of the complex numbers, a norm on V is a function $p: V \to \mathbb{R}$ with the following properties:^[1]

For all $a \in F$ and all $u, v \in V$,

- 1. p(av) = |a| p(v), (absolute homogeneity or absolute scalability).
- 2. $p(u + v) \le p(u) + p(v)$ (triangle inequality or subadditivity).
- 3. If p(v) = 0 then v is the zero vector (separates points).

By the first axiom, absolute homogeneity, we have p(0) = 0 and p(-v) = p(v), so that by the triangle inequality

$$p(v) \ge 0$$
 (non-negativity).

A seminorm on V is a function $p: V \to \mathbb{R}$ with the properties 1. and 2. above.

Every vector space V with seminorm p induces a normed space WW, called the quotient space, where W is the subspace of V consisting of all vectors v in V with p(v) = 0. The induced norm on WW is clearly well-defined and is given by:

$$p(W + v) = p(v)$$
.

Two norms (or seminorms) p and q on a vector space V are equivalent if there exist two real constants c and C, with c > 0 such that

for every vector v in V, one has that: $c g(v) \le p(v) \le C g(v)$.

A topological vector space is called normable (seminormable) if the topology of the space can be induced by a norm (seminorm).

Notation

If a norm $p: V \to \mathbb{R}$ is given on a vector space V then the norm of a vector $v \in V$ is usually denoted by enclosing it within double vertical lines: ||v|| = p(v). Such notation is also sometimes used if p is only a seminorm.

For the length of a vector in Euclidean space (which is an example of a norm, as explained below), the notation | v | with single vertical lines is also widespread.

In Unicode, the codepoint of the "double vertical line" character \parallel is U+2016. The double vertical line should not be confused with the "parallel to" symbol, Unicode U+2225 (\parallel).

第2页 共12页 2016年09月12日 22:14

This is usually not a problem because the former is used in parenthesis-like fashion, whereas the latter is used as an infix operator. The double vertical line used here should also not be confused with the symbol used to denote lateral clicks, Unicode U+01C1 (\parallel). The single vertical line \parallel is called "vertical line" in Unicode and its codepoint is U+007C.

Examples

- All norms are seminorms.
- The *trivial seminorm* has p(x) = 0 for all x in V.
- Every linear form f on a vector space defines a seminorm by $x \to |f(x)|$.

Absolute-value norm

The absolute value

$$||x|| = |x|$$

is a norm on the one-dimensional vector spaces formed by the real or complex numbers.

Euclidean norm

On an *n*-dimensional Euclidean space \mathbb{R}^n , the intuitive notion of length of the vector $x = (x_1, x_2, ..., x_n)$ is captured by the formula

$$\|oldsymbol{x}\|:=\sqrt{x_1^2+\cdots+x_n^2}.$$

This gives the ordinary distance from the origin to the point x, a consequence of the Pythagorean theorem. The Euclidean norm is by far the most commonly used norm on \mathbb{R}^n , but there are other norms on this vector space as will be shown below. However all these norms are equivalent in the sense that they all define the same topology.

On an n-dimensional complex space C^n the most common norm is

$$\|oldsymbol{z}\|:=\sqrt{\left|z_1
ight|^2+\cdots+\left|z_n
ight|^2}=\sqrt{z_1ar{z}_1+\cdots+z_nar{z}_n}.$$

In both cases we can also express the norm as the square root of the inner product of the vector and itself:

$$\|oldsymbol{x}\| := \sqrt{oldsymbol{x}^* \, oldsymbol{x}},$$

where x is represented as a column vector ([x_1 ; x_2 ; ...; x_n]), and x^* denotes its conjugate transpose.

This formula is valid for any inner product space, including Euclidean and complex spaces. For Euclidean spaces, the inner product is equivalent to the dot product. Hence, in this

specific case the formula can be also written with the following notation:

$$\|oldsymbol{x}\| := \sqrt{oldsymbol{x} \cdot oldsymbol{x}}.$$

The Euclidean norm is also called the Euclidean length, L^2 distance, ℓ^2 distance, L^2 norm, or ℓ^2 norm; see L^p space.

The set of vectors in \mathbb{R}^{n+1} whose Euclidean norm is a given positive constant forms an n-sphere.

Euclidean norm of a complex number

The Euclidean norm of a complex number is the absolute value (also called the modulus) of it, if the complex plane is identified with the Euclidean plane R^2 . This identification of the complex number x + iy as a vector in the Euclidean plane, makes the quantity

 $\sqrt{x^2+y^2}$ (as first suggested by Euler) the Euclidean norm associated with the complex number.

Taxicab norm or Manhattan norm

$$\left\|oldsymbol{x}
ight\|_1:=\sum_{i=1}^n\left|x_i
ight|.$$

The name relates to the distance a taxi has to drive in a rectangular street grid to get from the origin to the point *x*.

The set of vectors whose 1-norm is a given constant forms the surface of a cross polytope of dimension equivalent to that of the norm minus 1. The Taxicab norm is also called the ℓ_1 norm. The distance derived from this norm is called the Manhattan distance or ℓ_1 distance.

The 1-norm is simply the sum of the absolute values of the columns.

In contrast,

$$\sum_{i=1}^n x_i$$

is not a norm because it may yield negative results.

p-norm

Let $p \ge 1$ be a real number.

$$\left\|\mathbf{x}
ight\|_p := \left(\sum_{i=1}^n \left|x_i
ight|^p
ight)^{1/p}.$$

For p = 1 we get the taxicab norm, for p = 2 we get the Euclidean norm, and as p approaches ∞ the p-norm approaches the infinity norm or maximum norm. The p-norm is related to the generalized mean or power mean.

This definition is still of some interest for $0 , but the resulting function does not define a norm,^[2] because it violates the triangle inequality. What is true for this case of <math>0 , even in the measurable analog, is that the corresponding <math>L^p$ class is a vector space, and it is also true that the function

$$\int_X |f(x)-g(x)|^p \;\mathrm{d}\mu$$

(without pth root) defines a distance that makes $L^p(X)$ into a complete metric topological vector space. These spaces are of great interest in functional analysis, probability theory, and harmonic analysis. However, outside trivial cases, this topological vector space is not locally convex and has no continuous nonzero linear forms. Thus the topological dual space contains only the zero functional.

The partial derivative of the p-norm is given by

$$\left\|rac{\partial}{\partial x_k} {\left\|\mathbf{x}
ight\|}_p = rac{x_k {\left|x_k
ight|}^{p-2}}{\left\|\mathbf{x}
ight\|}_p^{p-1}.$$

The derivative with respect to x, therefore, is

$$rac{\partial \|\mathbf{x}\|_p}{\partial \mathbf{x}} = rac{\mathbf{x} \circ \left|\mathbf{x}
ight|^{p-2}}{\|\mathbf{x}\|_p^{p-1}}.$$

where o denotes Hadamard product and $|\cdot|$ is used for absolute value of each component of the vector.

For the special case of p = 2, this becomes

$$rac{\partial}{\partial x_k} \|\mathbf{x}\|_2 = rac{x_k}{\|\mathbf{x}\|_2},$$

or

$$rac{\partial}{\partial \mathbf{x}} \|\mathbf{x}\|_2 = rac{\mathbf{x}}{\|\mathbf{x}\|_2}.$$

Maximum norm (special case of: infinity norm, uniform norm, or supremum norm)

If ${f x}$ is some vector such that ${f x}=(x_1,x_2,\ldots,x_n)$, then:

$$\left\|\mathbf{x}
ight\|_{\infty}:=\max\left(\left|x_{1}
ight|,\ldots,\left|x_{n}
ight|
ight).$$

The set of vectors whose infinity norm is a given constant, *c*, forms the surface of a hypercube with edge length 2*c*.

$\|x\|_{\infty} = 1$

Zero norm

In probability and functional analysis, the zero norm induces a complete metric topology for the space of measurable functions

and for the F-space of sequences with F–norm $(x_n)\mapsto \sum_n 2^{-n}x_n/(1+x_n)$, which is

discussed by Stefan Rolewicz in *Metric Linear Spaces*.^[3] Here we mean by *F-norm* some real-valued function $\|\cdot\|$ on an F-space with distance d, such that $\|x\|=d(x,0)$. One should note that the *F-norm* described above is not a norm in the usual sense because it lacks the required homogeneity property.

Hamming distance of a vector from zero

In metric geometry, the discrete metric takes the value one for distinct points and zero otherwise. When applied coordinate-wise to the elements of a vector space, the discrete distance defines the *Hamming distance*, which is important in coding and information theory. In the field of real or complex numbers, the distance of the discrete metric from zero is not homogeneous in the non-zero point; indeed, the distance from zero remains one as its non-zero argument approaches zero. However, the discrete distance of a number from zero does satisfy the other properties of a norm, namely the triangle inequality and positive definiteness. When applied component-wise to vectors, the discrete distance from zero behaves like a non-homogeneous "norm", which counts the number of non-zero components in its vector argument; again, this non-homogeneous "norm" is discontinuous.

In signal processing and statistics, David Donoho referred to the *zero* "norm" with quotation marks. Following Donoho's notation, the zero "norm" of x is simply the number of non-zero coordinates of x, or the Hamming distance of the vector from zero. When this "norm" is localized to a bounded set, it is the limit of p-norms as p approaches 0. Of course, the zero "norm" is not truly a norm, because it is not positive homogeneous. Indeed, it is not even an F-norm in the sense described above, since it is discontinuous, jointly and severally, with respect to the scalar argument in scalar-vector multiplication and with respect to its vector argument. Abusing terminology, some engineers omit Donoho's quotation marks and inappropriately call the number-of-nonzeros function the L^0 norm, echoing the notation for the Lebesgue space of measurable functions.

Other norms

Other norms on \mathbb{R}^n can be constructed by combining the above; for example

$$\left\Vert x
ight\Vert :=2\leftert x_{1}
ightert +\sqrt{3\leftert x_{2}
ightert ^{2}+\max (\leftert x_{3}
ightert ,2\leftert x_{4}
ightert)^{2}}$$

is a norm on R⁴.

For any norm and any injective linear transformation A we can define a new norm of x, equal to

$$||Ax||$$
.

In 2D, with A a rotation by 45° and a suitable scaling, this changes the taxicab norm into the maximum norm. In 2D, each A applied to the taxicab norm, up to inversion and interchanging of axes, gives a different unit ball: a parallelogram of a particular shape, size and orientation. In 3D this is similar but different for the 1-norm (octahedrons) and the maximum norm (prisms with parallelogram base).

All the above formulas also yield norms on C^n without modification.

Infinite-dimensional case

The generalization of the above norms to an infinite number of components leads to the L^p spaces, with norms

$$\left\|x
ight\|_{p}=\left(\sum_{i\in\mathbb{N}}\left|x_{i}
ight|^{p}
ight)^{1/p} ext{resp.}\left\|f
ight\|_{p,X}=\left(\int_{X}\left|f(x)
ight|^{p}\,\mathrm{d}x
ight)^{1/p}$$

(for complex-valued sequences x resp. functions f defined on $X \subset \mathbb{R}$), which can be further generalized (see Haar measure).

Any inner product induces in a natural way the norm $\|x\| := \sqrt{\langle x, x
angle}$.

Other examples of infinite dimensional normed vector spaces can be found in the Banach space article.

Properties

The concept of unit circle (the set of all vectors of norm 1) is different in different norms: for the 1-norm the unit circle in \mathbb{R}^2 is a square, for the 2-norm (Euclidean norm) it is the well-known unit circle, while for the infinity norm it is a different square. For any p-norm it is a superellipse (with congruent axes). See the accompanying illustration. Due to the definition of the norm, the unit circle must be convex and centrally symmetric (therefore,

第7页 共12页 2016年09月12日 22:14

for example, the unit ball may be a rectangle but cannot be a triangle, and p > 1 for a p-norm).

In terms of the vector space, the seminorm defines a topology on the space, and this is a Hausdorff topology precisely when the seminorm can distinguish between distinct vectors, which is again equivalent to the seminorm being a norm. The topology thus defined (by either a norm or a seminorm) can be understood either in terms of sequences or open sets. A sequence of vectors $\{v_n\}$ is said to converge in norm to v if $\|v_n-v\| o 0$ as $n \to \infty$. Equivalently, the topology consists of all sets that can be represented as a union of open balls.

Two norms $\| \bullet \|_{\alpha}$ and $\| \bullet \|_{\beta}$ on a vector space V are called equivalent if there exist positive real numbers C and D such that for all x in V

$$C||x||_{\alpha} \leq ||x||_{\beta} \leq D||x||_{\alpha}.$$

For instance, on \mathbb{C}^n , if p > r > 0, then


$$||x||_p \le ||x||_r \le n^{(1/r-1/p)} ||x||_p.$$

In particular,

$$\begin{split} \|x\|_2 & \leq \|x\|_1 \leq \sqrt{n} \|x\|_2 \\ \|x\|_\infty & \leq \|x\|_2 \leq \sqrt{n} \|x\|_\infty \\ \|x\|_\infty & \leq \|x\|_1 \leq n \|x\|_\infty, \end{split}$$

i.e.,


$$||x||_{\infty} \le ||x||_{2} \le ||x||_{1} \le \sqrt{n} ||x||_{2} \le n ||x||_{\infty}$$
.



Equivalent norms define the same notions of continuity and convergence and for many purposes do not need to be distinguished. To be more precise the uniform structure defined by equivalent norms on the vector space is uniformly isomorphic.

Every (semi)-norm is a sublinear function, which implies that every norm is a convex function. As a result, finding a global optimum of a norm-based objective function is often tractable.

Given a finite family of seminorms p_i on a vector space the sum



norms.

$$p(x) := \sum_{i=0}^n p_i(x)$$

is again a seminorm.

For any norm p on a vector space V, we have that for all u and $v \in V$:

$$p(u \pm v) \ge |p(u) - p(v)|$$
.

Proof: Applying the triangular inequality to both p(u-0) and p(v-0):

$$p(u-0) \leq p(u-v) + p(v-0) \Rightarrow p(u-v) \geq p(u) - p(v) \ p(u-0) \leq p(u+v) + p(0-v) \Rightarrow p(u+v) \geq p(u) - p(v) \ p(v-0) \leq p(u-v) + p(u-0) \Rightarrow p(u-v) \geq p(v) - p(u) \ p(v-0) \leq p(u+v) + p(0-u) \Rightarrow p(u+v) \geq p(v) - p(u)$$

Thus, $p(u \pm v) \ge |p(u) - p(v)|$.

If X and Y are normed spaces and $u:X\to Y$ is a continuous linear map, then the norm of u and the norm of the transpose of u are equal. [4]

For the I^p norms, we have Hölder's inequality^[5]

$$\left|x^{\mathsf{T}}y\right| \leq \left\|x\right\|_{p} \left\|y\right\|_{q} \qquad rac{1}{p} + rac{1}{q} = 1.$$

A special case of this is the Cauchy–Schwarz inequality:^[5]

$$\left|x^{\mathsf{T}}y\right| \leq \left\|x\right\|_{2} \left\|y\right\|_{2}.$$

Classification of seminorms: absolutely convex absorbing sets

All seminorms on a vector space V can be classified in terms of absolutely convex absorbing sets in V. To each such set, A, corresponds a seminorm p_A called the gauge of A, defined as

$$p_A(x) := \inf\{\alpha : \alpha > 0, x \in \alpha A\}$$

with the property that

$${x: p_A(x) < 1} \subseteq A \subseteq {x: p_A(x) \le 1}.$$

Conversely:

Any locally convex topological vector space has a local basis consisting of absolutely convex sets. A common method to construct such a basis is to use a family (p) of seminorms p that separates points: the collection of all finite intersections of sets {p < 1/n} turns the space into a locally convex topological vector space so that every p is continuous.

Such a method is used to design weak and weak* topologies.

norm case:

Suppose now that (p) contains a single p: since (p) is separating, p is a norm, and $A = \{p < 1\}$ is its open unit ball. Then A is an absolutely convex bounded neighbourhood of 0, and $p = p_A$ is continuous.

The converse is due to Kolmogorov: any locally convex and locally bounded topological vector space is normable. Precisely:

If V is an absolutely convex bounded neighbourhood of 0, the gauge g_V (so that $V = \{g_V < 1\}$) is a norm.

Generalizations

There are several generalizations of norms and semi-norms. If p is absolute homogeneity but in place of subadditivity we require that

2', there is a
$$b \geq 1$$
 such that $p(u+v) \leq b(p(u)+p(v))$ for all $u,v \in V$

then p satisfies the triangle inequality but is called a quasi-seminorm and the smallest value of p for which this holds is called the multiplier of p; if in addition p separates points then it is called a quasi-norm.

On the other hand, if p satisfies the triangle inequality but in place of absolute homogeneity we require that

there exists a
$$k$$
 such that $0 < k \leq 1$ and for all $v \in V$ and scalars λ : $p(\lambda v) = |\lambda|^k p(v)$

then *p* is called a *k*-seminorm.

We have the following relationship between quasi-seminorms and k-seminorms:

Suppose that q is a quasi-seminorm on a vector space X with multiplier b. If $0 < k < \log_2^2 b$ then there exists k-seminorm p on X equivalent to q.

The concept of norm in composition algebras does *not* share the usual properties of a norm. A composition algebra (*A*, *, *N*) consists of an algebra over a field *A*, an involution *, and a quadratic form *N*, which is called the "norm". In several cases *N* is an isotropic

第10页 共12页 2016年09月12日 22:14

quadratic form so that A has at least one null vector, contrary to the separation of points required for the usual norm discussed in this article.

See also

- Normed vector space
- Asymmetric norm
- Matrix norm
- Gowers norm
- Mahalanobis distance
- Manhattan distance
- Relation of norms and metrics

Notes

- 1. Prugovečki 1981, page 20 (http://books.google.com/books?id=GxmQxn2PF3IC&pg=PA20)
- 2. Except in R¹, where it coincides with the Euclidean norm, and R⁰, where it is trivial.
- 3. Rolewicz, Stefan (1987), *Functional analysis and control theory: Linear systems*, Mathematics and its Applications (East European Series), 29 (Translated from the Polish by Ewa Bednarczuk ed.), Dordrecht; Warsaw: D. Reidel Publishing Co.; PWN—Polish Scientific Publishers, pp. xvi,524, ISBN 90-277-2186-6, MR 920371, OCLC 13064804
- 4. Treves pp. 242-243
- 5. Golub, Gene; Van Loan, Charles F. (1996). *Matrix Computations* (Third ed.). Baltimore: The Johns Hopkins University Press. p. 53. ISBN 0-8018-5413-X.

References

- Bourbaki, Nicolas (1987). "Chapters 1–5". *Topological vector spaces*. Springer. ISBN 3-540-13627-4.
- Prugovečki, Eduard (1981). *Quantum mechanics in Hilbert space* (2nd ed.). Academic Press. p. 20. ISBN 0-12-566060-X.
- Trèves, François (1995). *Topological Vector Spaces, Distributions and Kernels*. Academic Press, Inc. pp. 136–149, 195–201, 240–252, 335–390, 420–433. ISBN 0-486-45352-9.
- Khaleelulla, S. M. (1982). *Counterexamples in Topological Vector Spaces*. Lecture Notes in Mathematics. 936. Springer-Verlag. pp. 3–5. ISBN 978-3-540-11565-6. Zbl 0482.46002.

Retrieved from "https://en.wikipedia.org/w/index.php?title=Norm_(mathematics)& oldid=736305607"

Categories: Norms (mathematics) | Linear algebra

第11页 共12页 2016年09月12日 22:14

- This page was last modified on 26 August 2016, at 15:39.
- Text is available under the Creative Commons Attribution-ShareAlike License; additional terms may apply. By using this site, you agree to the Terms of Use and Privacy Policy. Wikipedia® is a registered trademark of the Wikimedia Foundation, Inc., a non-profit organization.

第12页 共12页 2016年09月12日 22:14