AMD Version 1.0 User Guide

Patrick R. Amestoy* Timothy A. Davis[†] Iain S. Duff[‡]
April 30, 2003

Abstract

AMD is a set of routines for permuting sparse matrices prior to factorization, using the approximate minimum degree ordering algorithm. It is written in both C and Fortran, with a MATLAB interface.

Technical report TR-03-011, CISE Department, University of Florida, Gainesville, FL, 2003. AMD Version 1.0 (Apr. 30, 2003), Copyright©2003 by Timothy A. Davis, Patrick R. Amestoy, and Iain S. Duff. All Rights Reserved.

AMD License: Your use or distribution of AMD or any modified version of AMD implies that you agree to this License.

THIS MATERIAL IS PROVIDED AS IS, WITH ABSOLUTELY NO WARRANTY EXPRESSED OR IMPLIED. ANY USE IS AT YOUR OWN RISK.

Permission is hereby granted to use or copy this program, provided that the Copyright, this License, and the Availability of the original version is retained on all copies. User documentation of any code that uses AMD or any modified version of AMD code must cite the Copyright, this License, the Availability note, and "Used by permission." Permission to modify the code and to distribute modified code is granted, provided the Copyright, this License, and the Availability note are retained, and a notice that the code was modified is included. This software was developed with support from the National Science Foundation, and is provided to you free of charge.

Availability: http://www.cise.ufl.edu/research/sparse/amd

Acknowledgments:

This work was supported by the National Science Foundation, under grants ASC-9111263 and DMS-9223088 and DMS-0203270. The conversion to C, the addition of the elimination tree post-ordering, and the handling of dense rows and columns were done while Davis was on sabbatical at Stanford University and Lawrence Berkeley National Laboratory.

^{*}ENSEEIHT-IRIT, 2 rue Camichel 31017 Toulouse, France. email: amestoy@enseeiht.fr. http://www.enseeiht.fr/ \sim amestoy.

[†]Dept. of Computer and Information Science and Engineering, Univ. of Florida, Gainesville, FL, USA. email: davis@cise.ufl.edu. http://www.cise.ufl.edu/~davis. This work was supported by the National Science Foundation, under grants ASC-9111263, DMS-9223088, and DMS-0203270. Portions of the work were done while on sabbatical at Stanford University and Lawrence Berkeley National Laboratory.

[‡]Rutherford Appleton Laboratory, Chilton, Didcot, Oxon OX11 0QX, England. email: i.s.duff@rl.ac.uk. http://www.numerical.rl.ac.uk/people/isd/isd.html. This work was supported by the the EPSRC under grant GR/R46441.

1 Overview

AMD is a set of routines for pre-ordering a sparse matrix prior to numeric factorization. It uses the approximate minimum degree ordering algorithm to find a permutation matrix \mathbf{P} such that the Cholesky factorization $\mathbf{P}\mathbf{A}\mathbf{P}^\mathsf{T} = \mathbf{L}\mathbf{L}^\mathsf{T}$ has low fill-in (fill-in refers to nonzeros in \mathbf{L} that did not appear in \mathbf{A}). If given an unsymmetric matrix, it operates on the symmetric nonzero pattern of $\mathbf{A} + \mathbf{A}^\mathsf{T}$.

The algorithm starts with an undirected graph representation of a symmetric sparse matrix **A**. Node i in the graph corresponds to row and column i of the matrix, and there is an edge (i, j) in the graph if a_{ij} is nonzero. The degree of a node starts out as the number of off-diagonal nonzeros in row i, which is the size of the set of nodes adjacent to i in the graph.

The selection of a pivot a_{ii} from the diagonal of **A** and the first step of Gaussian elimination corresponds to one step of graph elimination. Numerical fill-in results in new nonzero entries in the matrix. Node i is eliminated and edges are added to its neighbors so that they form a clique (or *element*). To reduce fill-in, node i is selected as the node of least degree in the graph. This process repeats until the graph is eliminated. The reduce fill-in, node i is selected as the node of least degree.

The clique is represented implicitly. Rather than listing all the new edges in the graph, a single list of nodes is kept which represents the clique. This list corresponds to the nonzero pattern of the first column of \mathbf{L} . As the elimination proceeds, some of these cliques become subsets of subsequent cliques, and are removed. This graph can be stored in place, using the same amount of memory as the original graph.

The most costly part of the minimum degree algorithm is the recomputation of the degrees of nodes adjacent to the current pivot element. Rather than keep track of the exact degree, the approximate minimum degree algorithm finds an upper bound on the degree that is easier to compute. For nodes of least degree, this bound tends to be tight. Using the approximate degree instead of the exact degree leads to a substantial savings in run time, particularly for very irregularly structured matrices. It has no effect on the quality of the ordering.

In the C version of AMD, the elimination phase is followed by an elimination tree post-ordering. This has no effect on fill-in, but reorganizes the ordering so that the subsequent numeric factorization is more efficient. It also includes a pre-processing phase in which nodes of very high degree are removed (without causing fill-in), and placed last in the permutation **P**. This reduces the run time substantially if the matrix has a few rows with many nonzero entries, and has little effect on the quality of the ordering.

Details of the algorithm are discussed in [1]. For a discussion of the long history of the minimum degree algorithm, see [2].

2 Availability

In addition to appearing as a Collected Algorithm of the ACM, AMD Version 1.0 is available at http://www.cise.ufl.edu/research/sparse. The Fortran version is available as the routine MC47 in HSL (formerly the Harwell Subroutine Library) [3].

3 Using AMD in MATLAB

The easiest way to use AMD is within MATLAB. To compile the AMD mexFunction, just type make in the Unix system shell, while in the AMD directory. You can also type amd_make in MATLAB,

if you are in the AMD/MATLAB directory, or if that directory is in your MATLAB path. This works on any system with MATLAB, including Windows. See Section 8 for more details on how to install AMD.

The MATLAB statement p = amd (A) finds a permutation vector p such that the Cholesky factorization chol (A (p,p)) is typically sparser than chol (A). If A is not symmetric positive definite, but has substantial diagonal entries and a mostly symmetric nonzero pattern, then this ordering is also suitable for LU factorization. A partial pivoting threshold may be required to prevent pivots from being selected off the diagonal, such as the statement [L,U,P] = lu (A (p,p), 0.1). Type help lu for more details. The statement [L,U,P,Q] = lu (A (p,p)) in MATLAB 6.5 is not suitable, however, because it uses UMFPACK Version 4.0 and thus does not attempt to select pivots from the diagonal. UMFPACK Version 4.1 uses several strategies, including a symmetric pivoting strategy, and will give you better results if you want to factorize an unsymmetric matrix of this type. Refer to the UMFPACK User Guide for more details, at http://www.cise.ufl.edu/research/sparse/umfpack.

An optional input argument can be used to modify the control parameters for AMD, and an optional output argument provides statistics on the ordering, including an analysis of the fill-in and floating-point operation count of a subsequent factorization. AMD will print these statistics if you turn on the sparse matrix monitor flag with spparms ('spumoni',1). Type help amd for more information.

4 Using AMD in a C program

The C-callable AMD library consists of four user-callable routines and one include file. Each of the routines come in two versions, with int and long integers. The routines with prefix amd_l_ use long integer arguments; the others use int integer arguments. If you compile AMD in the standard ILP32 mode (32-bit int's, long's, and pointers) then the versions are essentially identical. You will be able to solve problems using up to 2GB of memory. If you compile AMD in the standard LP64 mode, the size of an int remains 32-bits, but the size of a long and a pointer both get promoted to 64-bits.

The following routines are fully described in Section 9:

amd_order (long version: amd_l_order)

Computes the approximate minimum degree ordering of an n-by-n matrix \mathbf{A} . Returns a permutation vector \mathbf{P} of size \mathbf{n} , where \mathbf{P} [k] = \mathbf{i} if row and column \mathbf{i} are the kth row and column in the permuted matrix. This routine allocates its own memory, and requires $O(|\mathbf{A}|)$ space, where $|\mathbf{A}|$ is the number of nonzero entries in the matrix. It computes statistics about the matrix \mathbf{A} , such the symmetry of its nonzero pattern, the number of nonzeros in \mathbf{L} , and the floating-point operations required for Cholesky and LU factorizations. The user's input matrix is not modified.

• amd_defaults (long version: amd_l_defaults)

Sets the default control parameters in the Control array. These can then be modified as desired before passing the array to the other AMD routines.

• amd_control (long version: amd_l_control)

Prints the control parameters.

• amd_info (long version: amd_l_info)

Prints the statistics computed by AMD.

The nonzero pattern of the matrix **A** is represented in compressed column form, which is identical to the sparse matrix representation used by MATLAB. It consists of two arrays, where the matrix is **n**-by-**n**, with **nz** entries. For the **int** version of AMD:

```
int Ap [n+1];
int Ai [nz];

For the long version of AMD:
long Ap [n+1];
long Ai [nz];
```

The row indices of entries in column j are stored in Ai[Ap[j] ... Ap[j+1]-1].

No duplicate row indices may be present, and the row indices in any given column must be sorted in ascending order. The first entry Ap[0] must be zero. The total number of entries in the matrix is thus nz = Ap[n]. The matrix must be square, but it does not need to be symmetric. If it is unsymmetric, AMD computes the ordering of $A + A^T$. The diagonal entries may be present, but are ignored. AMD checks the input matrix and returns a negative value if it is invalid.

For a more flexible method for providing an input matrix to AMD, refer to the discussion of the "triplet" data structure in the UMFPACK User Guide.

Here is a simple main program, amd_demo.c, that illustrates the basic usage of AMD. See Section 5 for a short description of each calling sequence.

```
#include <stdio.h>
#include "amd.h"

int n = 5;
int Ap [] = { 0, 2, 6, 10, 12, 14};
int Ai [] = { 0,1, 0,1,2,4, 1,2,3,4, 2,3, 1,4 };
int P [5];

int main (void)
{
   int k;
   (void) amd_order (n, Ap, Ai, P, (double *) NULL, (double *) NULL);
   for (k = 0; k < n; k++) printf ("P [%d] = %d\n", k, P [k]);
   return (0);
}</pre>
```

The Ap and Ai arrays represent the binary matrix

$$\mathbf{A} = \left[\begin{array}{ccccc} 1 & 1 & 0 & 0 & 0 \\ 1 & 1 & 1 & 0 & 1 \\ 0 & 1 & 1 & 1 & 0 \\ 0 & 0 & 1 & 1 & 0 \\ 0 & 1 & 1 & 0 & 1 \end{array} \right].$$

The diagonal entries are ignored. AMD constructs the pattern of $\mathbf{A} + \mathbf{A}^{\mathsf{T}}$, and returns a permutation vector of (0, 3, 2, 4, 1). Since the matrix is unsymmetric but with a mostly symmetric nonzero pattern, this would be a suitable permutation for an LU factorization of a matrix with this nonzero

Table 1: AMD Control parameters

MATLAB	ANSI C	default	description
Control(1)	Control[AMD_DENSE]	10	dense row/column parameter
Control(2)	Control[AMD_AGGRESSIVE]	1 (yes)	aggressive absorption

pattern and whose diagonal entries are not too small. The program uses default control settings and does not return any statistics about the ordering, factorization, or solution (Control and Info are both (double *) NULL). It also ignores the status value returned by amd_order.

The amd_demo.c program provides a more detailed demo of AMD. Another example is the AMD mexFunction, amd_mex.c.

4.1 A note about zero-sized arrays

AMD uses several user-provided arrays of size n or nz. Either n or nz can be zero. If you attempt to malloc an array of size zero, however, malloc will return a null pointer which AMD will report as invalid. If you malloc an array of size n or nz to pass to AMD, make sure that you handle the n=0 and nz=0 cases correctly.

4.2 Control parameters

AMD uses an optional double array of size 5, Control, to modify its control parameters. If you pass (double *) NULL instead of a Control array, then defaults are used. NOTE: the size of this array may increase in future versions. Follow good programming practices and define your Control array to be of size AMD_CONTROL, which is currently defined as 5.

The contents of this array may be modified by the user (see amd_defaults or amd_l_defaults). Table 1 summarizes the contents of the Control array. Note that ANSI C uses 0-based indexing, while MATLAB uses 1-based indexing. Thus, Control(1) in MATLAB is the same as Control[0] or Control[AMD_DENSE] in ANSI C.

Let α =Control [AMD_DENSE]. A row or column of $\mathbf{A} + \mathbf{A}^\mathsf{T}$ is considered "dense" if it has more than $\max(16, \alpha \sqrt{n})$ entries. These rows/columns are placed last in AMD's output ordering. If Control [AMD_AGGRESSIVE] is nonzero, then AMD performs aggressive absorption. See [1] for details.

5 Synopsis of C-callable routines

The matrix **A** is n-by-n with nz entries.

```
#include "amd.h"
int n, status, Ap [n+1], Ai [nz], P [n];
double Control [AMD_CONTROL], Info [AMD_INFO];
amd_defaults (Control);
status = amd_order (n, Ap, Ai, P, Control, Info);
amd_control (Control);
amd_info (Info);
```

The amd_l_* routines are identical, except that all int arguments become long:

```
#include "amd.h"
long n, status, Ap [n+1], Ai [nz], P [n] ;
```

```
double Control [AMD_CONTROL], Info [AMD_INFO] ;
amd_l_defaults (Control) ;
status = amd_l_order (n, Ap, Ai, P, Control, Info) ;
amd_l_control (Control) ;
amd_l_info (Info) ;
```

6 Using AMD in a Fortran program

Two Fortran versions of AMD are provided. The AMD routine computes the approximate minimum degree ordering, using aggressive absorption. The AMDBAR routine is identical, except that it does not perform aggressive absorption. The AMD routine is essentially identical to the HSL routine MC47B/BD.

The Fortran versions differ from the C routines. The AMD algorithms were originally coded in Fortran and so are identical to the routines used in the experimental results in [1]. The internal routines require a symmetric nonzero pattern, with no diagonal entries present although the MC47A/AD wrapper allows duplicates, ignores out-of-range entries, and only uses entries from the upper triangular part of the matrix. Although we have an experimental Fortran code for treating "dense" rows, the Fortran codes in this release do not treat "dense" rows and columns of A differently, and thus their run time can be high if there are a few dense rows and columns in the matrix. They do not perform a post-ordering of the elimination tree, compute statistics on the ordering, or check the validity of their input arguments. These functions are provided by the HSL routines MA57L/LD and MC47A/AD, which are not part of this release. However, details on an assembly tree that respects the AMD ordering are returned from the calls to the Fortran codes. Only one integer version of each routine is provided. Both Fortran versions overwrite the user's input matrix, in contrast to the C version. The two Fortran versions have the same calling sequence, and only differ in the name of the routine.

The input matrix is provided to AMD and AMDBAR in three arrays, PE, of size N, LEN, of size N, and IW, of size IWLEN. The size of IW must be at least NZ+N. The recommended size is 1.2*NZ + N. On input, the indices of nonzero entries in row I are stored in IW. PE (I) is the index in IW of the start of row I. LEN (I) is the number of entries in row I. Row I is contained in IW (PE (I) ... PE (I) + LEN (I) - 1). The diagonal entries must not be present. The indices within each row must not contain any duplicates, but they need not be sorted. The rows themselves need not be in any particular order, and there may be empty space between the rows. If LEN (I) is zero, then there are no off-diagonal entries in row I, and PE (I) is ignored. The integer PFREE defines what part of IW contains the user's input matrix. The input matrix is in IW (1 ... PFREE-1). The contents of IW and LEN are undefined on output, and PE is modified to contain information about the ordering.

As the algorithm proceeds, it modifies the IW array, placing the pattern of the partially eliminated matrix in IW (PFREE ... IWLEN). If this space is exhausted, the space is compacted. The number of compactions performed on the IW array is returned in the scalar NCMPA. The value of PFREE on output is the size IW required for no compactions to occur.

The output permutation is returned in the array LAST, of size N. If I = LAST (K), then I is the Kth row in the permuted matrix. The inverse permutation is returned in the array ELEN, where K = ELEN (I) if I is the Kth row in the permuted matrix.

On output, the PE and NV arrays hold the assembly tree, a supernodal elimination tree that represents the relationship between columns of the Cholesky factor L. If NV (I) > 0, then I is a node in the assembly tree, and the parent of I is -PE (I). If I is a root of the tree, then PE (I) is zero. The value of NV (I) is the number of entries in the corresponding column of L, including the

diagonal. If NV (I) is zero, then I is a non-principal node that is not in the assembly tree. Node -PE (I) is the parent of node I in a subtree, the root of which is a node in the assembly tree. All nodes in one subtree belong to the same supernode in the assembly tree.

The other size N arrays (DEGREE, HEAD, NEXT, and W) are used as workspace, and are not defined on input or output.

If you want to use a simpler user-interface and compute the elimination tree post-ordering, you should be able to call the C routines amd_order or amd_l_order from a Fortran program. Just be sure to take into account the 0-based indexing in the P, Ap, and Ai arguments to amd_order and amd_l_order. A sample interface is provided in the files AMD/Demo/amd_f77cross.f and AMD/Demo/amd_f77wrapper.c. To compile the amd_f77cross program, type make cross in the AMD/Demo directory. The Fortran-to-C calling conventions are highly non-portable, so this example is not guaranteed to work with your compiler C and Fortran compilers. The output of amd_f77cross is in amd_f77cross.out.

7 Synopsis of Fortran-callable routines

8 Installation

The following discussion assumes you have the make program, either in Unix, or in Windows with Cygwin.

System-dependent configurations are in the AMD/Make directory. You can edit the Make.include file in that directory to customize the compilation. The default settings will work on most systems. Sample configuration files are provided for Linux, Sun Solaris, SGI IRIX, IBM AIX, and the DEC/Compaq Alpha.

To compile and install the C-callable AMD library, go to the AMD directory and type make. The library will be placed in AMD/Lib/libamd.a. Two demo programs of the AMD ordering routine will be compiled and tested in the AMD/Demo directory. The outputs of these demo programs will then be compared with output files in the distribution. The AMD mexFunction for use in MATLAB will also be compiled. If you do not have MATLAB type make lib instead.

To compile and install the Fortran-callable AMD library, go to the AMD directory and type make fortran. The library will be placed in AMD/Lib/libamdf77.a. A demo program will be compiled and tested in the AMD/Demo directory. The output will be compared with an output file in the distribution.

If you compile AMD and then later change the Make.include file or your system-specific configuration file such as Make.linux, then you should type make purge and then make to recompile.

Here are the various parameters that you can control in your Make.include file:

- CC = your C compiler, such as cc.
- RANLIB = your system's ranlib program, if needed.

- CFLAGS = optimization flags, such as -0.
- LIB = your libraries, such as -lm or -lblas.
- \bullet RM = the command to delete a file.
- \bullet MV = the command to rename a file.
- MEX = the command to compile a MATLAB mexFunction.
- F77 = the command to compile a Fortran program (optional).
- F77FLAGS = the Fortran compiler flags (optional).
- F77LIB = the Fortran libraries (optional).

When you compile your program that uses the C-callable AMD library, you need to add the AMD/Lib/libamd.a library and you need to tell your compiler to look in the AMD/Include directory for include files. To compile a Fortran program that calls the Fortran AMD library, you need to add the AMD/Lib/libamdf77.a library. See AMD/Demo/Makefile for an example.

If all you want to use is the AMD mexFunction in MATLAB, you can skip the use of the make command entirely. Simply type amd_make in MATLAB while in the AMD/MATLAB directory.

9 The AMD routines

The file AMD/Include/amd.h listed below describes each user-callable routine in the C version of AMD, and gives details on their use.

```
/* =========== */
/* === AMD: approximate minimum degree ordering ============ */
/* ========== */
/* AMD Version 1.0 (Apr. 30, 2003), Copyright (c) 2003 by Timothy A. Davis, */
/* Patrick R. Amestoy, and Iain S. Duff. See ../README for License.
                           CISE Department, Univ. of Florida.
/* email: davis@cise.ufl.edu
                                                                        */
/* web: http://www.cise.ufl.edu/research/sparse/amd
                                                                        */
/* ------ */
/* AMD finds a symmetric ordering P of a matrix A so that the Cholesky
* factorization of P*A*P' has fewer nonzeros and takes less work than the
* Cholesky factorization of A. If A is not symmetric, then it performs its
st ordering on the matrix A+A'. Two sets of user-callable routines are
* provided, one for "int" integers and the other for "long" integers.
* The method is based on the approximate minimum degree algorithm, discussed in
* Amestoy, Davis, and Duff, "An approximate degree ordering algorithm", SIAM
 * Journal of Matrix Analysis and Applications, vol. 17, no. 4, pp. 886-905,
* 1996. This package can perform both the AMD ordering (with aggressive
* absorption), and the AMDBAR ordering (without aggressive absorption)
* discussed in the above paper. This package differs from the Fortran codes
* discussed in the paper:
       (1) it can ignore "dense" rows and columns, leading to faster run times,
       (2) it computes the ordering of A+A' if A is not symmetric,
       (3) it is followed by a depth-first post-ordering of the assembly tree
           (or supernodal elimination tree)
 * For historical reasons, the Fortran versions, amd.f and amdbar.f, have
 * been left unchanged. They compute the identical ordering as described in
 * the above paper.
*/
#ifndef AMD_H
#define AMD H
int amd_order (
                         /* returns 0 if OK, negative value if error */
                         /* A is n-by-n. n must be >= 0. */
   int n,
   const int Ap [],
                         /* column pointers for A, of size n+1 */
   const int Ai [],
                         /* row indices of A, of size nz = Ap [n] */
   int P [ ],
                         /* output permutation, of size n */
                       /* input Control settings, of size AMD_CONTROL */
/* output Info statistics, of size AMD_INFO */
   double Control [],
   double Info [ ]
);
                        /* see above for description of arguments */
long amd_l_order (
   long n,
   const long Ap [],
   const long Ai [],
   long P [],
   double Control [],
   double Info [ ]
```

```
);
/* Input arguments (not modified):
        n: the matrix A is n-by-n.
        Ap: an int/long array of size n+1, containing the column pointers of A.
        Ai: an int/long array of size nz, containing the row indices of A,
            where nz = Ap [n].
        Control: a double array of size AMD_CONTROL, containing control
           parameters. Defaults are used if Control is NULL.
 * Output arguments (not defined on input):
        P: an int/long array of size n, containing the output permutation. If
           row i is the kth pivot row, then P[k] = i. In MATLAB notation,
            the reordered matrix is A (P,P).
        Info: a double array of size AMD_INFO, containing statistical
            information. Ignored if Info is NULL.
 * On input, the matrix A is stored in column-oriented form. The row indices
 * of nonzero entries in column j are stored in Ai [Ap [j] ... Ap [j+1]-1].
 * The row indices must appear in ascending order in each column, and there
 * must not be any duplicate entries. Row indices must be in the range 0 to
 * n-1. Ap [0] must be zero, and thus nz = Ap [n] is the number of nonzeros
 * in A. The array Ap is of size n+1, and the array Ai is of size nz = Ap [n].
 * The matrix does not need to be symmetric, and the diagonal does not need to
 * be present (if diagonal entries are present, they are ignored except for
 * the output statistic Info [AMD_NZDIAG]). The arrays Ai and Ap are not
 * modified. This form of the Ap and Ai arrays to represent the nonzero
 * pattern of the matrix A is the same as that used internally by MATLAB.
 * If you wish to use a more flexible input structure, please see the
 * umfpack_*_triplet_to_col routines in the UMFPACK package, at
 * http://www.cise.ufl.edu/research/sparse/umfpack.
 * Restrictions: n \ge 0. Ap [0] = 0. Ap [j] \le Ap [j+1] for all j in the
        range 0 to n-1. nz = Ap [n] >= 0. For all j in the range 0 to n-1,
        and for all p in the range Ap [j] to Ap [j+1]-2, Ai [p] < Ai [p+1] must
        hold. Ai [0..nz-1] must be in the range 0 to n-1. To avoid integer
        overflow, (2.4*nz + 8*n) < INT_MAX / size of (int) for must hold for the
        "int" version. (2.4*nz + 8*n) < LONG_MAX / sizeof (long) must hold
        for the "long" version. Finally, Ai, Ap, and P must not be NULL. If
        any of these restrictions are not met, AMD returns AMD_INVALID.
  AMD returns:
        AMD_OK if the matrix is valid and sufficient memory can be allocated to
           perform the ordering.
        AMD_OUT_OF_MEMORY if not enough memory can be allocated.
        AMD_INVALID if the input arguments n, Ap, Ai are invalid, or if P is
            NULL.
 * The AMD routine first forms the pattern of the matrix A+A, and then computes
 * a fill-reducing ordering, P. If P [k] = i, then row/column i of the original
 st is the kth pivotal row. In MATLAB notation, the permuted matrix is A (P,P),
 * except that O-based indexing is used instead of the 1-based indexing in
 * MATLAB.
```

```
* pointer is passed, default values are used. The Control array is not
* modified.
       Control [AMD_DENSE]: controls the threshold for "dense" rows/columns.
           A dense row/column in A+A' can cause AMD to spend a lot of time in
           ordering the matrix. If Control [AMD_DENSE] >= 0, rows/columns with
          more than Control [AMD_DENSE] * sqrt (n) entries are ignored during
           the ordering, and placed last in the output order. The default
           value of Control [AMD_DENSE] is 10. If negative, no rows/columns
           are treated as "dense". Rows/columns with 16 or fewer off-diagonal
           entries are never considered "dense".
       {\tt Control\ [AMD\_AGGRESSIVE]:\ controls\ whether\ or\ not\ to\ use\ aggressive}
           absorption, in which a prior element is absorbed into the current
           element if is a subset of the current element, even if it is not
           adjacent to the current pivot element (refer to Amestoy, Davis,
           \ensuremath{\&} Duff, 1996, for more details). The default value is nonzero,
           which means to perform aggressive absorption. This nearly always
           leads to a better ordering (because the approximate degrees are more
           accurate) and a lower execution time. There are cases where it can
           lead to a slightly worse ordering, however. To turn it off, set
           Control [AMD_AGGRESSIVE] to 0.
       Control [2..4] are not used in the current version, but may be used in
          future versions.
* The Info array provides statistics about the ordering on output. If it is
* not present, the statistics are not returned. This is not an error
* condition.
       Info [AMD_STATUS]: the return value of AMD, either AMD_OK,
           AMD_OUT_OF_MEMORY, or AMD_INVALID.
       Info [AMD_N]: n, the size of the input matrix
       Info [AMD_NZ]: the number of nonzeros in A, nz = Ap [n]
       Info [AMD_SYMMETRY]: the symmetry of the matrix A. It is the number
           of "matched" off-diagonal entries divided by the total number of
           off-diagonal entries. An entry A(i,j) is matched if A(j,i) is also
           an entry, for any pair (i,j) for which i != j. In MATLAB notation,
               S = spones (A);
               B = tril (S, -1) + triu (S, 1);
               symmetry = nnz (B & B') / nnz (B);
       Info [AMD_NZDIAG]: the number of entries on the diagonal of A.
       Info [AMD_NZ_A_PLUS_AT]: the number of nonzeros in A+A', excluding the
           diagonal. If A is perfectly symmetric (Info [AMD_SYMMETRY] = 1)
           with a fully nonzero diagonal, then Info [AMD_NZ_A_PLUS_AT] = nz-n
           (the smallest possible value). If A is perfectly unsymmetric
           (Info [AMD_SYMMETRY] = 0, for an upper triangular matrix, for
           example) with no diagonal, then Info [AMD_NZ_A_PLUS_AT] = 2*nz
           (the largest possible value).
       Info [AMD_NDENSE]: the number of "dense" rows/columns of A+A' that were
          removed from A prior to ordering. These are placed last in the
           output order P.
```

* The Control array is used to set various parameters for AMD. If a NULL

```
Info [AMD_MEMORY]: the amount of memory used by AMD, in bytes. In the
            current version, this is 1.2 * Info [AMD_NZ_A_PLUS_AT] + 9*n
           times the size of an integer. This is at most 2.4nz + 9n. This
            excludes the size of the input arguments Ai, Ap, and P, which have
           a total size of nz + 2*n + 1 integers.
       Info [AMD_NCMPA]: the number of garbage collections performed.
       Info [AMD_LNZ]: the number of nonzeros in L (excluding the diagonal).
           This is a slight upper bound because mass elimination is combined
           with the approximate degree update. It is a rough upper bound if
           there are many "dense" rows/columns. The rest of the statistics,
           below, are also slight or rough upper bounds, for the same reasons.
           The post-ordering of the assembly tree might also not exactly
           correspond to a true elimination tree postordering.
       Info [AMD_NDIV]: the number of divide operations for a subsequent LDL'
            or LU factorization of the permuted matrix A (P,P).
       Info [AMD_NMULTSUBS_LDL]: the number of multiply-subtract pairs for a
            subsequent LDL' factorization of A (P,P).
       Info [AMD_NMULTSUBS_LU]: the number of multiply-subtract pairs for a
            subsequent LU factorization of A (P,P), assuming that no numerical
           pivoting is required.
       Info [AMD_DMAX]: the maximum number of nonzeros in any column of L,
            including the diagonal.
       Info [14..19] are not used in the current version, but may be used in
           future versions.
/* AMD Control and Info arrays */
/* amd_defaults: sets the default control settings */
void amd_defaults (double Control []);
void amd_l_defaults (double Control [ ]) ;
/* amd_control: prints the control settings */
void amd_control (double Control []);
void amd_l_control (double Control [ ]) ;
/* amd_info: prints the statistics */
void amd_info (double Info [ ]);
void amd_l_info
                  (double Info [ ]) ;
#define AMD_CONTROL 5
                           /* size of Control array */
#define AMD_INFO 20
                           /* size of Info array */
/* contents of Control */
#define AMD_DENSE 0
                           /* "dense" if degree > Control [0] * sqrt (n) */
#define AMD_AGGRESSIVE 1 /* do aggressive absorption if Control [1] != 0 */
/* default Control settings */
#define AMD_DEFAULT_DENSE 10.0
                                   /* default "dense" degree 10*sqrt(n) */
```

```
#define AMD_DEFAULT_AGGRESSIVE 1 /* do aggressive absorption by default */
/* contents of Info */
#define AMD_STATUS 0
                    /* return value of amd_order and amd_l_order */
#define AMD_N 1
                     /* A is n-by-n */
#define AMD_NZ 2
                    /* number of nonzeros in A */
#define AMD_NZ_A_PLUS_AT 5 /* nz in A+A' */
#define AMD_NDENSE 6  /* number of "dense" rows/columns in A */
#define AMD_MEMORY 7
                    /* amount of memory used by AMD */
#define AMD_NCMPA 8
                    /* number of garbage collections in AMD */
#define AMD_LNZ 9
                    /* approx. nz in L, excluding the diagonal */
#define AMD_NDIV 10
                    /* number of fl. point divides for LU and LDL' */
#define AMD_NMULTSUBS_LDL 11 /* number of fl. point (*,-) pairs for LDL' */
#define AMD_DMAX 13
                    /* max nz. in any column of L, incl. diagonal */
/* return values of AMD */
/* ------ */
#define AMD_OK 0
                        /* success */
#define AMD_OUT_OF_MEMORY -1 /* malloc failed, or 2.4*nz+9*n is too large */
                       /* input arguments are not valid */
#define AMD_INVALID -2
#endif
```

References

- [1] P. R. Amestoy, T. A. Davis, and I. S. Duff. An approximate minimum degree ordering algorithm. SIAM J. Matrix Anal. Applic., 17(4):886–905, 1996.
- [2] A. George and J. W. H. Liu. The evolution of the minimum degree ordering algorithm. *SIAM Review*, 31(1):1–19, 1989.
- [3] HSL. HSL 2002: A collection of Fortran codes for large scale scientific computation, 2002. www.cse.clrc.ac.uk/nag/hsl.