AA25 invalid account nonce

Thenonce of the user operation is invalid.

Possible solutions

- · Verify that you are using the correctnonce
- for the user operation. Thenonce
- should be the current nonce of the smart account for the selectedkey
- . Consider leveraging functions likegetAccountNonce
- .* Make sure that you are not reusing a nonce that has already been used.
 - Make sure that you are not using a nonce that is too far in the future (more than 10 higher than the current nonce).
- · Verify that the nonce is formatted correctly.

Instead of sequential nonce the EntryPoint implements a nonce mechanism that uses a singleuint256 nonce value in the user operation, but treats it as two values:

- 192-bitkey
- 64-bitsequence

For eachkey thesequence is validated and incremented sequentially and monotonically by the EntryPoint for each user operation, however a newkey can be introduced with an arbitrary value at any point.