## **ACLManager**

## **ACLManager**

Access Control List Manager is the main registry of system roles and permissions.

ACLManager allows aRole Admin to manage roles. Role Admin is itself a role that is managed by the DEFAULT\_ADMIN\_ROLE.

DEFAULT ADMIN ROLE is held by the ACLAdmin, which is initialised in Pool Addresses Provider.

 ${f i}$  On Ethereum chainPoolAddressesProvider , is owned by Aave Governance. In networks other than Ethereum, either theCrosschain Governance Bridges orCommunity Multisigs are used to manage thePoolAddressesProvider .

## Roles

Below we outline the powers/responsibilities of the roles and the specific methods that are only accessible to the holders of these roles.

Role Responsibilities / Powers Methods Accessible FLASH\_BORROWER Flash loan premium is waived for the holders of this role.

Does not include flashLoanSimple flashLoan BRIDGE Can leverage the Portal feature mintUnbacked backUnbacked ASSET\_LISTING\_ADMIN Can update

- · asset oracle sources
- · fallback oracle
- add new assets to the Aave market \*
- setAssetSources
- setFallbackOracle
- initReserves \* RISK\_ADMIN Can update
- · grace period of Oracle Sentinels
- · reserve params
- · unbacked mint cap
- · liquidation protocol fee
- existing eMode categories and create new. (not category 0)
- add/remove asset in silo mode \*
- setGracePeriod
- setReserveBorrowing
- configureReserveAsCollateral
- setReserveStableRateBorrowing
- setReserveFreeze
- setBorrowableInIsolation
- setReserveFactor
- · setDebtCeiling
- setBorrowCap
- setSupplyCap
- setLiquidationProtocolFee
- setEModeCategory
- setAssetEModeCategory
- setUnbackedMintCap
- setReserveInterestRateStrategyAddress
- setSiloedBorrowing \* ACL\_ADMIN Manage the role admins in the ACLManager
- setRoleAdmin
- addPoolAdmin
- removePoolAdmin
- addEmergencyAdmin
- · removeEmergencyAdmin
- addRiskAdmin
- · removeRiskAdmin
- addFlashBorrower
- removeFlashBorrower
- addBridge
- removeBridge
- · addAssetListingAdmin
- removeAssetListingAdmin \* EMERGENCY ADMIN Can pause/unpause the pool or individual reserve setPoolPause

## POOL\_ADMIN Can

- · update token implementations
- · drop reserves
- pause/unpause reserves
- activate/deactivate reserves
- · update premiums
- do all the things available to RISK\_ADMIN & ASSET\_LISTING\_ADMIN \*
- · all methods available toRISK\_ADMIN
- all methods available to ASSET\_LISTING\_ADMIN
- dropReserve
- updateAToken
- updateStableDebtToken
- updateVariableDebtToken
- setReserveActive
- updateBridgeProtocolFee
- updateFlashloanPremiumTotal
- updateFlashloanPremiumToProtocol \*

View Methods

isPoolAdmin

function isPoolAdmin(address admin)

Returnstrue if the address has POOL ADMIN role.

isEmergencyAdmin

function isEmergencyAdmin(address admin)

Returnstrue if the address has EMERGENCY ADMIN role.

isRiskAdmin

function isRiskAdmin(address admin)

Returnstrue if the address hasRISK ADMIN role.

isFlashBorrower

function isFlashBorrower(address borrower)

Returnstrue if the address hasFLASH\_BORROWER role.

isBridge

function isBridge(address bridge)

Returnstrue if the address has BRIDGE role.

isAssetListingAdmin

function is Asset Listing Admin (address admin)

Returnstrue if the address has ASSET\_LISTING\_ADMIN role.

Write Methods

setRoleAdmin

setRoleAdmin(bytes32 role, bytes32 adminRole)

Setup admin to manage Roles.

This method can only be called by address with DEFAULT ADMIN ROLE. Call Params

Name Type Description role bytes32 keccak256 hash of one of the following:

POOL ADMIN

- EMERGENCY ADMIN
- RISK ADMIN
- FLASH BORROWER
- BRIDGE
- ASSET\_LISTING\_ADMIN \* adminRole bytes32 adminRole responsible for role. 0x00 is reserved for DEFAULT ADMIN ROLE

addPoolAdmin

addPoolAdmin(address admin)

Add address to the list of members in POOL\_ADMIN role. Holders of this role can update token implementations, drop, (un)pause and (de)activate reserves, update premiums and do everything the ASSET\_LISTING\_ADMIN and RISK\_ADMIN can do.

Can be called only byRole Admin , specified byAave Governance , responsible for managingPOOL\_ADMIN role. Call Params

Name Type Description admin address address which will be granted POOL ADMIN role.

removePoolAdmin

removePoolAdmin(address admin)

Remove given address from the list of members in POOL ADMIN role.

Can be called only byRole Admin , specified byAave Governance , responsible for managingPOOL\_ADMIN role. Call Params

Name Type Description admin address address for which POOL ADMIN role permissions must be revoked.

addEmergencyAdmin

addEmergencyAdmin(address admin)

Add address to the list of members in EMERGENCY\_ADMIN role. Holders of this role can pause and unpause the pool or an individual reserve.

Can be called only byRole Admin, specified byAave Governance, responsible for managingEMERGENCY\_ADMIN role. Name Type Description admin address address which will be granted EMERGENCY\_ADMIN role.

removeEmergencyAdmin

function removeEmergencyAdmin(address admin)

Remove given address from the list of members in EMERGENCY ADMIN role.

Can be called only byRole Admin, specified byAave Governance, responsible for managingEMERGENCY\_ADMIN role. Name Type Description admin address address for which EMERGENCY ADMIN role permissions must be revoked.

addRiskAdmin

function addRiskAdmin(address admin)

Add address to the list of members in RISK\_ADMIN role. Holders of this role can update grace period of Oracle Sentinels, reserve params, unbacked mint cap, liquidation fee and eMode categories.

Name Type Description admin address address which will be granted RISK ADMIN role.

removeRiskAdmin

Remove given address from the list of members in RISK\_ADMIN role.

Name Type Description admin address address for which RISK ADMIN role permissions must be revoked.

addFlashBorrower

function addFlashBorrower(address borrower)

Add address to the list of members in FLASH\_BORROWER role. Holders of this role do not pay premium for flash loan (Does not apply to flash Lona Simple .

removeFlashBorrower

function removeFlashBorrower(address borrower)

Remove given address from the list of members in FLASH\_BORROWER role.

Name Type Description admin address address for which FLASH BORROWER role permissions must be revoked.

addBridge

addBridge(address bridge)

Add contract address to the list ofbridges . Holders of this role can leverage the Portal feature to seamlessly move supplied assets across Aave V3 markets on different networks.

i Can be called only byRole Admin , specified byAave Governance , responsible for managingBRIDGE role. Name Type Description bridge address address which will be granted BRIDGE role.

removeBridge

removeBridge(address bridge)

Remove contract address from the list ofbridges .

i Can be called only byRole Admin, specified byAave Governance, responsible for managingBRIDGE role. Name Type Description bridge address address for which BRIDGE role permissions must be revoked.

addAssetListingAdmin

function addAssetListingAdmin(address admin)

Add address to the list of member in ASSET\_LISTING\_ADMIN role. Holder of this role can update oracles & add new asset to the Aave market.

Name Type Description admin address address which will be granted ASSET\_LISTING\_ADMIN role.

removeAssetListingAdmin

function removeAssetListingAdmin(address admin)

Remove address from the list of members in ASSET\_LISTING\_ADMIN role.

Name Type Description admin address address for which ASSET\_LISTING\_ADMIN role permissions must be revoked.

ABI

ACLManager ABI ```

```
Copy [ { "inputs": [ { "internalType": "contract IPoolAddressesProvider", "name": "provider", "type": "address" } ],
 "stateMutability": "nonpayable", "type": "constructor" }, { "anonymous": false, "inputs": [ { "indexed": true, "internalType":
"bytes32", "name": "role", "type": "bytes32" }, { "indexed": true, "internalType": "bytes32", "name": "previousAdminRole",
"type": "bytes32" }, { "indexed": true, "internalType": "bytes32", "name": "newAdminRole", "type": "bytes32" } ], "name":
"RoleAdminChanged", "type": "event" }, { "anonymous": false, "inputs": [ { "indexed": true, "internalType": "bytes32", "name":
"role", "type": "bytes32" }, { "indexed": true, "internalType": "address", "name": "account", "type": "address" }, { "indexed": true, "internalType": "address" } ], "name": "RoleGranted", "type": "event" }, { "anonymous": false, "inputs": [ { "indexed": true, "internalType": "bytes32", "name": "role", "type": "bytes32" }, { "indexed": true, "internalType": "bytes32", "name": "role", "type": "bytes32" }, { "indexed": true, "internalType": "bytes32", "name": "role", "type": "bytes32" }, { "indexed": true, "internalType": "bytes32", "name": "role", "type": "bytes32" }, { "indexed": true, "internalType": "bytes32", "name": "role", "type": "bytes32" }, { "indexed": true, "internalType": "bytes32", "name": "role", "type": "bytes32" }, { "indexed": true, "internalType": "bytes32", "name": "role", "type": "bytes32" }, { "indexed": true, "internalType": "bytes32", "name": "role", "type": "bytes32" }, { "indexed": true, "internalType": "bytes32", "name": "role", "type": "bytes32", "type": "bytes3
"internalType": "address", "name": "account", "type": "address" }, { "indexed": true, "internalType": "address", "name":
"sender", "type": "address" } ], "name": "RoleRevoked", "type": "event" }, { "inputs": [], "name": "ADDRESSES_PROVIDER", "outputs": [ { "internalType": "contract IPoolAddressesProvider", "name": "", "type": "address" } ], "stateMutability": "vew",
"type": "function" }, { "inputs": [], "name": "ASSET_LISTING_ADMIN_ROLE", "outputs": [ { "internalType": "bytes32", "name": "", "type": "bytes32" } ], "stateMutability": "view", "type": "function" }, { "inputs": [], "name": "BRIDGE_ROLE", "outputs": [ {
"internalType": "bytes32", "name": "", "type": "bytes32" } ], "stateMutability": "view", "type": "function" }, { "inputs": [], "name":
"DEFAULT_ADMIN_ROLE", "outputs": [ { "internalType": "bytes32", "name": "", "type": "bytes32" } ], "stateMutability": "view", "type": "function" }, { "inputs": [], "name": "EMERGENCY_ADMIN_ROLE", "outputs": [ { "internalType": "bytes32", "name": "",
"type": "bytes32" } ], "stateMutability": "view", "type": "function" }, { "inputs": [], "name": "FLASH_BORROWER_ROLE", "outputs": [ { "internalType": "bytes32", "name": "", "type": "bytes32" } ], "stateMutability": "view", "type": "function" }, { "inputs": [], "name": "POOL_ADMIN_ROLE", "outputs": [ { "internalType": "bytes32", "name": "", "type": "bytes32" } ], "stateMutability":
 "view", "type": "function" }, { "inputs": [], "name": "RISK_ADMIN_ROLE", "outputs": [ { "internalType": "bytes32", "name": "",
"type": "bytes32" } ], "stateMutability": "view", "type": "function" }, { "inputs": [ { "internalType": "address", "name": "admin",
 "type": "address" } ], "name": "addAssetListingAdmin", "outputs": [], "stateMutability": "nonpayable", "type": "function" }, {
 "inputs": [ { "internalType": "address", "name": "bridge", "type": "address" } ], "name": "addBridge", "outputs": [],
```

```
"stateMutability": "nonpayable", "type": "function" }, { "inputs": [ { "internalType": "address", "name": "admin", "type":
"address" } ], "name": "addEmergencyAdmin", "outputs": [], "stateMutability": "nonpayable", "type": "function" }, { "inputs": [ {
    "internalType": "address", "name": "borrower", "type": "address" } ], "name": "addFlashBorrower", "outputs": [],
    "stateMutability": "nonpayable", "type": "function" }, { "inputs": [ { "internalType": "address", "name": "admin", "type":
    "address" } ], "name": "addPoolAdmin", "outputs": [], "stateMutability": "nonpayable", "type": "function" }, { "inputs": [ {
    "internalType": "address", "pame": "address", "name": "ad
"type": "address" } ], "name": "hasRole", "outputs": [ { "internalType": "bool", "name": "", "type": "bool" } ], "stateMutability":
 "view", "type": "function" }, { "inputs": [ { "internalType": "address", "name": "admin", "type": "address" } ], "name":
"isAssetListingAdmin", "outputs": [ { "internalType": "bool", "name": "", "type": "bool" } ], "stateMutability": "view", "type":
"function" }, { "inputs": [ { "internalType": "address", "name": "bridge", "type": "address" } ], "name": "isBridge", "outputs": [ {
"internalType": "bool", "name": "", "type": "bool" } ], "stateMutability": "view", "type": "function" }, { "inputs": [ { "internalType":
"address", "name": "admin", "type": "address" } ], "name": "isEmergencyAdmin", "outputs": [ { "internalType": "bool", "name":
"", "type": "bool" } ], "stateMutability": "view", "type": "function" }, { "inputs": [ { "internalType": "address", "name": "borrower",
"type": "address" } ], "name": "isFlashBorrower", "outputs": [ { "internalType": "bool", "name": "", "type": "bool" } ],
"stateMutability": "view", "type": "function" }, { "inputs": [ { "internalType": "address", "name": "admin", "type": "address" } ],
"name": "isPoolAdmin", "outputs": [ { "internalType": "bool", "name": "", "type": "bool" } ], "stateMutability": "view", "type":
"function" }, { "inputs": [ { "internalType": "address", "name": "admin", "type": "address" } ], "name": "isRiskAdmin", "outputs": [
{ "internalType": "bool", "name": "", "type": "bool" } ], "stateMutability": "view", "type": "function" }, { "inputs": [ { "internalType":
 "address", "name": "admin", "type": "address" } ], "name": "removeAssetListingAdmin", "outputs": [], "stateMutability":
 "nonpayable", "type": "function" }, { "inputs": [ { "internalType": "address", "name": "bridge", "type": "address" } ], "name":
 "removeBridge", "outputs": [], "stateMutability": "nonpayable", "type": "function" }, { "inputs": [ { "internalType": "address",
 "name": "admin", "type": "address" } ], "name": "removeEmergencyAdmin", "outputs": [], "stateMutability": "nonpayable",
 "type": "function" }, { "inputs": [ { "internalType": "address", "name": "borrower", "type": "address" } ], "name":
 "removeFlashBorrower", "outputs": [], "stateMutability": "nonpayable", "type": "function" }, { "inputs": [ { "internalType":
 "address", "name": "admin", "type": "address" } ], "name": "removePoolAdmin", "outputs": [], "stateMutability": "nonpayable",
 "type": "function" }, { "inputs": [ { "internalType": "address", "name": "admin", "type": "address" } ], "name":
"removeRiskAdmin", "outputs": [], "stateMutability": "nonpayable", "type": "function" }, { "inputs": [ { "internalType": "bytes32", "name": "role", "type": "bytes32" }, { "internalType": "address", "name": "account", "type": "address" } ], "name": "renounceRole", "outputs": [], "stateMutability": "nonpayable", "type": "function" }, { "inputs": [ { "internalType": "bytes32", "name": "role", "type": "address" } ], "name": "revokeRole", "outputs": [], "stateMutability": "nonpayable", "type": "function" }, { "inputs": [ { "internalType": "bytes32", "name": "role", "type": "bytes32", "name": "setRoleAdmin", "outputs": [], "stateMutability": "nonpayable", "type": "bytes32" } ], "name": "setRoleAdmin", "outputs": [], "stateMutability": "nonpayable", "type": "bytes32" } ], "name": "setRoleAdmin", "outputs": [], "stateMutability": "nonpayable", "type": "function" } [ { "inputs": [ { "internalType": "bytes32" } ], "name": "setRoleAdmin", "outputs": [], "stateMutability": "nonpayable", "type": "function" } [ { "inputs": [], "inputs": "listerfood!", "type": "bytes32", "name": "inputs": "function" } [ { "inputs": "function", "type": "bytes32", "name": "inputs
"stateMutability": "nonpayable", "type": "function" }, { "inputs": [ { "internalType": "bytes4", "name": "interfaceId", "type": "bytes4" } ], "name": "supportsInterface", "outputs": [ { "internalType": "bool", "name": "", "type": "bool" } ], "stateMutability":
"view", "type": "function" } ]
```

Previous Rates Guide Next AaveProtocolDataProvider Last updated1 year ago On this page \*ACLManager \* Roles \* View Methods \* isPoolAdmin \* isEmergencyAdmin \* isRiskAdmin \* isFlashBorrower \* isBridge \* isAssetListingAdmin \* Write Methods \* setRoleAdmin \* addPoolAdmin \* removePoolAdmin \* addEmergencyAdmin \* removeEmergencyAdmin \* addFlashBorrower \* removeFlashBorrower \* addBridge \* removeBridge \* addAssetListingAdmin \* removeAssetListingAdmin \* ABI

Was this helpful?