title: ERC-4626 Tokenized Vault Standard description: A standard for yield bearing vaults. lang: en

Introduction {#introduction}

ERC-4626 is a standard to optimize and unify the technical parameters of yield-bearing vaults. It provides a standard API for tokenized yield-bearing vaults that represent shares of a single underlying ERC-20 token. ERC-4626 also outlines an optional extension for tokenized vaults utilizing ERC-20, offering basic functionality for depositing, withdrawing tokens and reading balances.

The role of ERC-4626 in yield-bearing vaults

Lending markets, aggregators, and intrinsically interest-bearing tokens help users find the best yield on their crypto tokens by executing different strategies. These strategies are done with slight variation, which might be error-prone or waste development resources.

ERC-4626 in yield-bearing vaults will lower the integration effort and unlock access to yield in various applications with little specialized effort from developers by creating more consistent and robust implementation patterns.

The ERC-4626 token is described fully in EIP-4626.

Prerequisites {#prerequisites}

To better understand this page, we recommend you first read abouttoken standards and ERC-20.

ERC-4626 Functions and Features: {#body}

Methods {#methods}

asset {#asset}

solidity function asset() public view returns (address)

This function returns the address of the underlying token used for the vault for accounting, depositing, withdrawing.

totalAssets {#totalassets}

```
solidity function totalAssets() public view returns (uint256)
```

This function returns the total amount of underlying assets held by the vault.

convertToShares {#convertoshares}

```
solidity function convertToShares(uint256 assets) public view returns (uint256 shares)
```

This function returns the amount of shares that would be exchanged by the vault for the amount of assets provided.

convertToAssets {#convertoassets}

```
solidity function convertToAssets(uint256 shares) public view returns (uint256 assets)
```

This function returns the amount of assets that would be exchanged by the vault for the amount of shares provided.

maxDeposit {#maxdeposit}

```
solidity function maxDeposit(address receiver) public view returns (uint256)
```

This function returns the maximum amount of underlying assets that can be deposited in a singledeposit call by the receiver.

previewDeposit {#previewdeposit}

solidity function previewDeposit(uint256 assets) public view returns (uint256)

This function allows users to simulate the effects of their deposit at the current block.

deposit {#deposit}

solidity function deposit(uint256 assets, address receiver) public returns (uint256 shares)

This function deposits assets of underlying tokens into the vault and grants ownership of shares to receiver.

maxMint {#maxmint}

solidity function maxMint(address receiver) public view returns (uint256)

This function returns the maximum amount of shares that can be minted in a singlement call by the receiver.

previewMint {#previewmint}

solidity function previewMint(uint256 shares) public view returns (uint256)

This function allows users to simulate the effects of their mint at the current block.

mint {#mint}

solidity function mint(uint256 shares, address receiver) public returns (uint256 assets)

This function mints exactly shares vault shares to receiver by depositing assets of underlying tokens.

maxWithdraw {#maxwithdraw}

solidity function maxWithdraw(address owner) public view returns (uint256)

This function returns the maximum amount of underlying assets that can be withdrawn from theware balance with a single withdraw call.

previewWithdraw {#previewwithdraw}

solidity function previewWithdraw(uint256 assets) public view returns (uint256)

This function allows users to simulate the effects of their withdrawal at the current block.

withdraw {#withdraw}

solidity function withdraw(uint256 assets, address receiver, address owner) public returns (uint256 shares)

This function burns shares from owner and send exactly assets token from the vault to receiver.

maxRedeem {#maxredeem}

solidity function maxRedeem(address owner) public view returns (uint256)

This function returns the maximum amount of shares that can be redeemed from theowner balance through a redeem call.

previewRedeem {#previewredeem}

solidity function previewRedeem(uint256 shares) public view returns (uint256)

This function allows users to simulate the effects of their redemption at the current block.

redeem {#redeem}

solidity function redeem(uint256 shares, address receiver, address owner) public returns (uint256 assets)

This function redeems a specific number of shares from owner and sends assets of underlying token from the vault to receiver.

totalSupply {#totalsupply}

solidity function totalSupply() public view returns (uint256)

Returns the total number of unredeemed vault shares in circulation.

balanceOf {#balanceof}

solidity function balanceOf(address owner) public view returns (uint256)

Returns the total amount of vault shares theowner currently has.

Events {#events}

Deposit Event

MUST be emitted when tokens are deposited into the vault via themint and deposit methods

solidity event Deposit(address indexed sender, address indexed owner, uint256 assets, uint256 shares)

Where sender is the user who exchanged assets for shares, and transferred those shares to owner.

Withdraw Event

MUST be emitted when shares are withdrawn from the vault by a depositor in the redeem or withdraw methods.

solidity event Withdraw(address indexed sender, address indexed receiver, address indexed owner, uint256 assets, uint256 share)

Where sender is the user who triggered the withdrawal and exchanged shares, owned by owner, for assets. receiver is the user who received the withdrawn assets.

Further reading {#further-reading}

- EIP-4626: Tokenized vault Standard
- ERC-4626: GitHub Repo