## Initializing Core Kit SFA Web SDK

After Installation, the next step to use Web3Auth Single Factor Auth Web SDK is to Initialize the SDK.

However, the Initialization is a two-step process, ie.

- Instantiation of Web3Auth
- Initialization of Web3Auth

### Instantiating Web3Authâ

#### Import theWeb3Auth

```
class from@web3auth/single-factor-auth package.â
import
{
Web3Auth
}
from
"@web3auth/single-factor-auth";

Assign theWeb3Auth
class to a variableâ
const web3auth =
```

Web3Auth ( Web3AuthOptions ); This Web3Auth constructor takes an object withWeb3AuthOptions as input.

#### **Arguments**â

#### Web3AuthOptions

â

new

- Table
- Interface

Parameter Type Description Mandatory clientId string Web3Auth Client ID. Obtain yourclientId from the Web3Auth Developer Dashboard. Yes web3AuthNetwork? TORUS\_LEGACY\_NETWORK\_TYPE Web3Auth Network to use for login. @defaultValue mainnet No enableLogging? boolean Setting it to true will enable logs. No usePnPKey? boolean Setting this to true returns the same key as PnP Web SDK, By default, this SDK returns CoreKitKey. Use this flag if you require the key returned by PnP SDK. Ideal for migrating from PnP Products to SFA No sessionTime? number Determine the session length in seconds. By default the value is set at 86400 seconds, ie. 1 day. No storageKey? "session" or "local" Select the session key storage across local storage or session storage. Setting to "local" will persist social login session accross browser tabs. @defaultValue "local" No storageServerUrl? string Specify a custom metadata storage server url. For general usecases, you don't need to change this value. @defaultValuehttps://broadcast-server.tor.us No export

interface

Web3AuthOptions

{ /\* \* Client id for web3auth. \* You can obtain your client id from the web3auth developer dashboard. \* You can set any random string for this on localhost. / clientId :

```
string; /* * Web3Auth Network to use for login * @defaultValue mainnet/ web3AuthNetwork ?:
```

```
TORUS_LEGACY_NETWORK_TYPE;
```

/\* \* setting to true will enable logs \* \* @defaultValue false enableLogging ? :

```
boolean;
/* * setting this to true returns the same key as web sdk (i.e., plug n play key) * By default, this sdk returns CoreKitKely
usePnPKey?:
boolean;
/* * How long should a login session last at a minimum in seconds * * @defaultValue 86400 seconds * @remarks Max value
of sessionTime can be 7 * 86400 (7 days) / sessionTime ?:
number;
/* * setting to "local" will persist social login session accross browser tabs. * * @defaultValue "local" storageKey ? :
"session"
"local";
/* * Specify a custom storage server url * @defaultValue https://broadcast-server.tor.us/ storageServerUrl ? :
string; }
Usageâ
const web3auth =
new
Web3Auth ( { clientId :
"WEB3AUTH_CLIENT_ID",
// Get your Client ID from the Web3Auth Dashboard web3AuthNetwork :
"sapphire_mainnet", usePnPKey:
false,
// By default, this sdk returns CoreKitKey } );
```

## Instantiating Providerâ

For getting the appropriate key for your selected chain, you need to instantiate a provider. This provider is used to make calls to the selected blockchain. Currently, Web3Auth exposes the following provider packages to be integrated within the SDKs:

- EthereumPrivateKeyProvider
- : For Ethereum and EVM compatible chains (secp256k1 private key)
- SolanaPrivateKeyProvider
- : For Solana Blockchain (ed25519 private key)
- XRPLPrivateKeyProvider
- · : For XRP Ledger
- CommonPrivateKeyProvider
- : For other blockchains (secp256k1 private key)

Using these providers, you can export the private keys for the respective curves of the selected blockchain. You can use these keys to even create manual providers for other blockchains supporting the curves/ have conversion packages for their blockchain curves.

- ETH
- Solana
- XRPL
- · Other Chains

```
Usage import
```

EthereumPrivateKeyProvider

```
}
from
"@web3auth/ethereum-provider"; import
CHAIN_NAMESPACES
from
"@web3auth/base";
const privateKeyProvider =
new
EthereumPrivateKeyProvider ( { config :
{ / pass the chain config that you want to connect with. all chainConfig fields are required/ chainConfig :
{ chainNamespace :
CHAIN_NAMESPACES . EIP155 , chainId :
"0x1", rpcTarget:
"https://rpc.ankr.com/eth", displayName:
"Ethereum Mainnet", blockExplorer:
"https://etherscan.io", ticker:
"ETH", tickerName:
"Ethereum", }, }, }); Usage import
SolanaPrivateKeyProvider
}
from
"@web3auth/solana-provider"; import
CHAIN_NAMESPACES
}
from
"@web3auth/base";
const privateKeyProvider =
new
SolanaPrivateKeyProvider ( { config :
{ / pass the chain config that you want to connect with. all chainConfig fields are required/ chainConfig :
{ chainNamespace :
CHAIN_NAMESPACES . SOLANA , chainId :
"0x1", rpcTarget:
```

```
"https://rpc.ankr.com/solana", displayName:
"Solana Mainnet", blockExplorer:
"https://explorer.solana.com/", ticker:
"SOL", tickerName:
"Solana", }, }, }); Usage import
{
XrplPrivateKeyProvider
}
from
"@web3auth/xrpl-provider"; import
CHAIN_NAMESPACES
}
from
"@web3auth/base";
const privateKeyProvider =
new
XrplPrivateKeyProvider ( { config :
{ / pass the chain config that you want to connect with. all chainConfig fields are required/ chainConfig:
{ chainNamespace :
CHAIN_NAMESPACES . OTHER , chainId :
"0x1", rpcTarget:
"https://s.altnet.rippletest.net:51234", displayName:
"XRPL", blockExplorer:
"https://testnet.xrpl.org", ticker:
"XRP", tickerName:
"XRP", }, }, }); Usage import
CommonPrivateKeyProvider
}
from
"@web3auth/base-provider"; import
CHAIN_NAMESPACES
}
from
"@web3auth/base";
```

```
const privateKeyProvider =
new
CommonPrivateKeyProvider ( { config :
{ / pass the chain config that you want to connect with. all chainConfig fields are required/ chainConfig :
{ chainNamespace :
CHAIN_NAMESPACES . OTHER , chainId :
"0x1", rpcTarget:
https://rpc.target.url , displayName :
"Display Name", blockExplorer:
"https://chain.explorer.link", ticker:
"TKR", tickerName:
"Ticker Name", }, }, });
Initializing Web3Authâ
init()
â
To complete the initialization process, we need to initialize the Web3Auth instance, which we namedweb3auth . This is
achieved by calling theinit() function of the previously createdweb3auth instance, using aprivate key provider .
web3auth . init ( privateKeyProvider ) ;
```

# **Example**<sup>â</sup>

```
import
Web3Auth
}
from
"@web3auth/single-factor-auth"; import
EthereumPrivateKeyProvider
}
from
"@web3auth/ethereum-provider"; import
CHAIN_NAMESPACES
}
from
"@web3auth/base";
// Swap with a different provider if you want to use a different blockchain const privateKeyProvider =
new
```

```
EthereumPrivateKeyProvider ( { config :
{ chainConfig :
{ chainNamespace :
CHAIN_NAMESPACES . EIP155 , chainId :
"0x1", rpcTarget:
"https://rpc.ankr.com/eth", displayName:
"Ethereum Mainnet", blockExplorer:
"https://etherscan.io", ticker:
"ETH", tickerName:
"Ethereum", }, }, });
const web3auth =
new
Web3Auth ( { clientId :
"WEB3AUTH_CLIENT_ID",
// Get your Client ID from the Web3Auth Dashboard web3AuthNetwork :
"sapphire_mainnet", usePnPKey:
false,
// By default, this SDK returns CoreKitKey by default. } );
web3auth . init ( privateKeyProvider ) ;Edit this page Previous Install Next Authentication
```