(C) INRIA

CADP MANUAL PAGES FSP.OPEN (LOCAL)

NAME

fsp.open - OPEN/CAESAR connection for the FSP language

SYNOPSIS

fsp.open [-root root-process] [-silent | -verbose] [-version] [exp_options] filename[.lts] [cc_options] prog[.a|.c|.o] [prog_options]

DESCRIPTION

Taking as input *filename*.lts (which describes a process in the FSP language of Magee & Kramer, Imperial College, London) and an OPEN/CAESAR program *prog*[.al.cl.o], fsp.open operates as follows:

- First, it translates *filename*.lts into an EXP.OPEN network of automata *filename*.exp, using fsp2lotos(LOCAL) and svl(LOCAL). See fsp2lotos(LOCAL) for more information.
- Second, it calls "**exp.open** filename.**exp** [cc_options] prog[.a|.c|.o] [prog_options]", passing to **exp.open** appropriate options that depend on the options passed to **fsp.open** (see below). See **exp.open**(LOCAL) for more information.

However, if *prog* is the "-" string (instead of the name of an OPEN/CAESAR application program), **fsp.open** will execute only the first step (translation into an EXP.OPEN network of automata) and then stop without invoking **exp.open**. In such case, the files generated during the first step are not removed, thus allowing the generated EXP.OPEN network of automata to be used for other purpose than OPEN/CAESAR.

OPTIONS

-root root-process

Use the process root-process as the main process. This option is passed to **fsp2lotos**(LOCAL). See **fsp2lotos**(LOCAL) for more information.

-silent Execute silently. This option is passed to exp.open(LOCAL) and svl(LOCAL). See exp.open(LOCAL) and svl(LOCAL) for more information.

-verbose

Report activities and progress, including errors and messages emitted by auxiliary tools, to the user's screen. This option is passed to exp.open(LOCAL) and svl(LOCAL). See exp.open(LOCAL) and svl(LOCAL) for more information.

-version

Display the version number of **fsp2lotos**(LOCAL) and stop.

OPERANDS

filename.lts	FSP specification (input)
prog.a	exploration module (archive, input)
prog.c	exploration module (source, input)
prog.o	exploration module (object code, input)
prog	executable program (output)

CADP MANUAL PAGES FSP.OPEN (LOCAL)

FILES

\$CADP_TMP/fsp.* temporary files \$CADP/lib/FSP_V1.lib

FSP predefined library (LOTOS code)

\$CADP/incl/FSP_V1.h FSP predefined library (C code)

EXIT STATUS

When the source is erroneous, error messages are issued. Exit status is 0 if everything is alright, 1 otherwise.

AUTHORS

Remi Herilier and Frederic Lang (INRIA Rhone-Alpes).

SEE ALSO

exp(LOCAL), exp.open(LOCAL), fsp2lotos(LOCAL), lotos(LOCAL), svl(LOCAL), svl-lang(LOCAL)

Additional information is available from the CADP Web page located at http://cadp.inria.fr Directives for installation are given in files **\$CADP/INSTALLATION_***.

Recent changes and improvements to this software are reported and commented in file \$CADP/HISTORY.

BUGS

Please report any bug to cadp@inria.fr

(C) INRIA Last change: 2019/01/13 2