PHY293 Waves and Modern Physics

Michael Boyadjian

December 27, 2019

Contents

Ι	Waves	3
1	Simple Harmonic Oscillators	3
	1.1 Equations of Motion	. 3
	1.2 General Solutions	. 3
	1.3 Energy	. 3
2	Damped Harmonic Oscillators	4
	2.1 Equations of Motion	. 4
	2.2 General Solutions	. 4
	2.3 Conditions of Damping	. 4
	2.3.1 Light Damping	. 4
	2.3.2 Critical Damping	. 5
	2.3.3 Heavy Damping	. 5
	2.4 Energy	. 5
	2.5 Quality Factor (Q)	. 5
3	Forced Harmonic Oscillators and Resonance	7
	3.1 Forced Undamped Oscillator	. 7
	3.2 Forced Damped Oscillator	. 8
	3.3 Varying the Forcing Frequency	. 8
	3.4 Power Absorbed by Damping During Forced Oscillations	. 8
4	Coupled Harmonic Oscillators and Eigenmodes	9
	4.1 Coupled Pendulums	. 9
	4.2 General Solution Method	. 9
5	Wave Equation and Standing Waves	11
	5.1 Wave Equation	. 11
	5.2 Standing Waves	. 11
	5.3 Energy	. 11
6	Travelling Waves	12
	6.1 Solutions to the Wave Equation	. 12
	6.2 Reflection and Transmission	
7	Wave Packets and Dispersion	13

Part I

Waves

1 Simple Harmonic Oscillators

1.1 Equations of Motion

If we look at a mass attached to a spring, we can model its motion using Hooke's Law:

$$F = -kx_0$$

The negative indicates that this is a restoring force that brings it back to the origin. The constant k shows that the force is proportional to the distance from the rest state.

Now if the spring is released, it must obey Newton's second law. Therefore the motion can be modelled as

$$m\ddot{x} = -kx$$

a second-order ordinary differential equation.

1.2 General Solutions

To consider the solution to this equation, let's define $\omega^2 = \frac{k}{m}$, ($\omega = \frac{2\pi}{T}$ as well), which is called the angular frequency. This allows us to represent this differential equation as

$$\ddot{x} + \omega^2 x = 0$$

Thus, the solution to this problem would be

$$x(t) = A\cos(\omega t + \phi)$$
 or $x(t) = A_1\cos(\omega t) + A_2\sin(\omega t)$

where A is the amplitude and ϕ is the phase shift, which can be determined by given initial values. Using what is given and our known equation, we can then solve for whatever unknown variables. It may also be important to remember that the velocity (first-derivative of position) is

$$\dot{x}(t) = v(t) = -A\omega \sin(\omega t + \phi)$$

1.3 Energy

Energy is an important tool to solve problems, simple harmonic oscillators being no exception. Without their dissipation, their mechanical energy stay the same forever. The total energy of a simple harmonic oscillator is simply the sum of its kinetic energy (KE) and potential energy (PE).

$$E = KE + PE = \frac{1}{2}mv^2 + \frac{1}{2}kx^2 = \frac{1}{2}kA^2$$

which is a constant. The above equation shows us that the energy is proportional to the square of the amplitude.

2 Damped Harmonic Oscillators

2.1 Equations of Motion

Realistically, we have to consider friction in the motion of a spring-mass system. This friction force is proportional to its velocity:

$$F_d = -b\dot{x}$$

With this we can now define a new equation of motion:

$$m\ddot{x} + kx + b\dot{x} = \ddot{x} + \gamma\dot{x} + \omega_0^2 x = 0$$

where $\gamma = \frac{b}{m}$ is called the damping factor and ω_0^2 is now the natural frequency of the oscillator - frequency if there was no damping. This tells us there could be multiple natural frequencies.

2.2 General Solutions

If we look at our equation from above, it's a second-order differential equation. The solution to it gives two roots, meaning that any solution can be a linear combination of both. This most general solution exists as

$$x(t) = a_p e^{r_p t} + a_m e^{r_m t}$$

where r_p and r_m are the roots of the equation:

$$r_p = -\frac{\gamma}{2} + \sqrt{\frac{\gamma^2}{4} - \omega_0^2}$$
 $r_m = -\frac{\gamma}{2} - \sqrt{\frac{\gamma^2}{4} - \omega_0^2}$

Note that this will not work if $\omega^2 = \frac{\gamma^2}{4}$, as we will see in conditions of damping.

2.3 Conditions of Damping

There are 3 cases of damping we can consider, which we can characterize as light damping $(\frac{\gamma^2}{4} < \omega_0^2)$, critical damping $(\frac{\gamma^2}{4} = \omega_0^2)$, and heavy damping $(\frac{\gamma^2}{4} > \omega_0^2)$.

2.3.1 Light Damping

For light damping to occur, we consider the case where $\frac{\gamma^2}{4} < \omega_0^2$. When this happens, the general solution becomes

$$x(t) = Ae^{\frac{\gamma t}{2}}cos(\omega t + \phi)$$
 \rightarrow $\omega = \sqrt{\omega_0^2 - \frac{\gamma^2}{4}}$

A graph of the lightly damped model shows the decaying amplitude. We see that there is actually a factor by which this occurs

$$ln\left(\frac{A_n}{A_{n+1}}\right) = e^{\frac{\gamma T}{2}}$$

which is known as the **logarithmic decrement**

2.3.2 Critical Damping

This is an interesting case. Since $\omega_o^2 - \frac{\gamma^2}{4} = 0$, then $r_p = r_m = -\frac{\gamma}{2}$. Therefore, our general solution becomes

$$x(t) = (a_p + a_m)e^{-\frac{\gamma t}{2}}$$

But this would not work as it could easily become an over constrained problem. So, the general solution actually becomes:

$$x(t) = (A + Bt)e^{-\frac{\gamma t}{2}}$$

2.3.3 Heavy Damping

Heavy damping occurs when a system returns to its equilibrium without any oscillations. This is when $\frac{\gamma^2}{4} > \omega_0^2$. The general solution for this case is

$$x(t) = e^{\frac{-\gamma t}{2}} (Ae^{\alpha t} + Be^{-\alpha t})$$

2.4 Energy

The energy of a damped oscillator eventually dissipates over time. We can find the rate at which this occurs by looking at the change in the total energy, which is given by:

$$E = KE + PE = \frac{1}{2}mv^2 + \frac{1}{2}kx^2$$

We find that the energy can be modelled by the equation:

$$E(t) = E_0 e^{-\gamma t}$$

where E_0 is the initial energy at t=0 and $\frac{1}{\gamma}$ tells us the time it takes for the energy to decay by a factor of e. We can define $\tau=\frac{1}{\gamma}$ and show this equation as

$$E(t) = E_0 e^{\frac{-t}{\tau}}$$

where τ is called the **decay time** or **time constant** of the system

2.5 Quality Factor (Q)

For energy saving purposes, we want a system to do as little driving as possible, meaning the less damping the better. To measure this, we define the Quality Factor (Q), measured by the ratio

$$Q = \frac{\text{tendency to oscillate}}{\text{tendency to damp}}$$

In our lightly damped system, oscillations last longer when $\gamma \ll 2\omega_0$, so a 'high quality' is achieved when

$$Q = \frac{\omega_0}{\gamma}$$

We can now write the pseudo angular frequency as

$$\omega_d^2 = \omega_0^2 (1 - \frac{1}{4Q^2})$$

This can also be thought of as the number of oscillations an oscillator will achieve in a lifetime. If we define $\tau = \frac{1}{\gamma}$ and $n = \frac{\tau}{T_0}$, then the quality factor will be

$$Q=2\pi n$$

3 Forced Harmonic Oscillators and Resonance

Remember the following for this chapter:

- If an oscillator is driven at frequency ω , then it will oscillate at ω , regardless of the values of ω_0 and γ
- If an oscillator is driven at $\omega \approx \omega_0$, then it will resonate
- At resonance, the amplitude is approximately $A \approx QA_f$
- The resonance frequency is exactly ω_0 because it is where the peak in velocity response and power absorption are both located.

3.1 Forced Undamped Oscillator

Consider the SHO we discussed earlier, but this time with an engine attached to the system. If the oscillator is being driven at a frequency ω and applying a force with amplitude, F_0 , its equation of motion could be modelled as

$$\ddot{x} + \omega_0^2 x = \frac{F_0}{m} \cos(\omega t)$$

This is a non-homogeneous ODE. We don't consider the complimentary solution in this case, since this was covered in the unforced case. A particular solution to this problem is

$$x(t) = A(\omega)\cos(\omega t - \delta(\omega))$$

There are several cases to consider here:

• If $\delta = 0$, then $\cos \delta = 1$, so:

$$A(\omega) = \frac{\omega_0^2}{\omega_0^2 - \omega^2} A_f \qquad \omega_0 > \omega$$

• If $\delta = \pi$, then $\cos \delta = -1$, so:

$$A(\omega) = -\frac{\omega_0^2}{\omega_0^2 - \omega^2} A_f \qquad \omega_0 < \omega$$

In the case where $\omega_0 = \omega$, the general solution from above cannot be applied. Instead, the solution is the following

$$x(t) = \frac{1}{2} A_f \omega_0 t \cos\left(\omega_0 t - \frac{\pi}{2}\right)$$

3.2 Forced Damped Oscillator

If we add damping to the forced oscillator system, we obtain the following equation of motion

$$\ddot{x} + \gamma \dot{x} + \omega_0^2 x = A_f \omega_0^2 \cos(\omega t)$$

We can consider the same general solution as the undamped case

$$x(t) = A(\omega)\cos(\omega t - \delta(\omega))$$

where $A(\omega)$ and $\delta(\omega)$ are as follows

$$A(\omega) = \frac{\omega_0^2}{\sqrt{\gamma^2 \omega^2 + (\omega_0^2 - \omega^2)^2}} A_f \qquad \delta(\omega) = \arctan\left(\frac{\gamma \omega}{\omega_0^2 - \omega^2}\right)$$

3.3 Varying the Forcing Frequency

It appears that resonance occurs when $\omega = \omega_0$, but this is in fact not the case.

$$\omega_{max}^2 = \omega_0^2 - \frac{\gamma^2}{2} = \omega_0^2 \left[1 - \frac{1}{2Q^2} \right]$$

The maximum amplitude is found when $\omega = \omega_{max}$

$$A_{max} = A(\omega_{max}) = \frac{Q}{\sqrt{1 - \frac{1}{4Q^2}}} A_f$$

For practical purposes however, $\omega_{max} \approx \omega_0$ and $A_{max} \approx QA_f = \frac{F_0Q}{k}$

3.4 Power Absorbed by Damping During Forced Oscillations

The rate of energy loss due to damping is given as

$$-\dot{E}(\omega, t) = P(\omega, t) = bv^2 = bV^2(\omega)\sin^2(\omega t - \delta)$$

where $V(\omega)$ is the velocity response

$$V(\omega) = \frac{\omega_0 \omega}{\sqrt{\gamma^2 \omega^2 + (\omega_0^2 - \omega^2)^2}} A_f$$

The average power as a function of only ω is given as

$$\bar{P}(\omega) = \frac{F_0^2}{2m} \frac{\gamma}{\gamma^2 + (\frac{\omega_0^2}{\omega} - \omega)^2}$$

Friction absorbs the most energy when $\omega = \omega_0$. At this frequency, the average power becomes

$$\bar{P}_{max} = \frac{F_0^2}{2\gamma m} = \frac{F_0^2}{2b}$$

For this reason we call the natural frequency, ω_0 the resonant frequency.

4 Coupled Harmonic Oscillators and Eigenmodes

4.1 Coupled Pendulums

Consider two identical pendulums of length L with a mass m hanging from each. The masses are connected with a spring of stiffness k. There are two natural modes of motion to consider in this situation

• Antisymmetric Normal Mode: Both pendulums oscillate in perfect sync , with the same amplitude and phase

$$x_A(t) = x_B(t) = A\cos(\omega_1 t)$$

The spring is neither stretched or compressed and thus does not play any role in the motion. All elements of the system oscillate at the same frequency $\omega_1 = \omega_p$

• Symmetric Normal Mode: The pendulums will oscillate 180 degrees out of phase and with a single angular frequency ω_2

$$x_A(t) = A\cos(\omega_2 t)$$
 $x_B(t) = A\cos(\omega_2 t + \pi)$

This is considered a normal mode because both pendulums oscillate at the same frequency.

4.2 General Solution Method

Consider three masses coupled together with springs of spring constant k with two fixed ends:

1. Define the equations of motion

$$m\ddot{x}_A = -kx_A - k(x_A - x_B)$$

$$m\ddot{x}_B = -k(x_B - x_A) - k(x_B - x_C)$$

$$m\ddot{x}_C = -k(x_C - x_B) - kx_C$$

2. Substitute $x(t) = A\cos(\omega t)$ and $\ddot{x}(t) = -A\omega^2\cos(\omega t)$ to simplify equations of motion

$$-A\omega^2 m = -2kA + kB$$
$$-B\omega^2 m = -kB + kA + kC$$
$$-C\omega^2 m = -2kC + kB$$

3. Generate the matrix system of equations

$$\begin{bmatrix} 2k - \omega^2 m & -k & 0 \\ -k & 2k - \omega^2 m & -k \\ 0 & -k & 2k - \omega^2 m \end{bmatrix} \begin{bmatrix} A \\ B \\ C \end{bmatrix} = \vec{0}$$

4. Take the determinant and find the eigenvalues

$$\det M = (2k - \omega^2 m)(2k - \omega^2 m - k^2)(2k - \omega^2 m + k^2)$$

$$\omega_1 = \sqrt{\frac{2k}{m}} \qquad \omega_2 = \pm \sqrt{\frac{(2 - \sqrt{2})k}{m}}$$

5. Compose general solution and solve for the constants using the initial conditions

$$x(t) = C\cos(\omega_1 t) + D\cos(\omega_2 t)$$

5 Wave Equation and Standing Waves

5.1 Wave Equation

The wave equation is given as the following

$$\frac{\partial^2 y}{\partial t^2} = \nu^2 \frac{\partial^2 y}{\partial x^2}$$

5.2 Standing Waves

The general equation for standing waves can be given as such that the variables are separable

$$y(x,t) = f(x)h(t)$$

Therefore, the general solution for a standing waves on a string is

$$y_n(x,t) = A_n \sin\left(\frac{n\pi x}{L}\right) \cos(\omega_n t)$$

where n is known as the harmonic number.

Some important things to note about standing waves:

- A **node** is a position where there is zero displacement (the string doesn't move)
- An antinode is the position where the largest displacement or amplitude occurs
- The mode with no nodes is known as the **fundamental** mode or **first harmonic**
- The n^{th} harmonic has n-1 nodes and n antinodes
- The wavelength of the n^{th} mode is $\lambda_n = \frac{2L}{n}$ and each has a corresponding wave number, $k_n = \frac{2\pi}{\lambda_n} = \frac{n\pi}{L}$

5.3 Energy

The energy per unit length of a string is given as

$$E = \frac{1}{2}\mu \int_0^L \left[\left(\frac{\partial y}{\partial t} \right)^2 + \nu^2 \left(\frac{\partial y}{\partial t} \right)^2 \right] dx$$

For a single mode, the energy equation is simplified to

$$E_n = \frac{1}{4}\mu L\omega_n^2 A_n^2$$

And the total energy is just the sum of the energies of each mode

$$E = \sum_{n=1}^{\infty} E_n = \frac{1}{4} \mu L \sum_{n=1}^{\infty} \omega_n^2 A_n^2$$

6 Travelling Waves

The main travelling wave function that will be encountered is the following

$$y(x,t) = A\sin(kx \pm \omega t)$$

The relationship $v = \frac{\omega}{k} = \lambda \nu$ may also be useful

6.1 Solutions to the Wave Equation

The most general solution to the wave equation is

$$y(x,t) = f(x - vt) + g(x - vt)$$

6.2 Reflection and Transmission

When a wave hits discontinuity part of it is transmitted and part of it is reflected. This discontinuity occurs in the phase speed. If the mass density, μ or the tension, t changes suddenly, the phase speed will as well. Therefore, there are two phase speeds

$$v_1 = \sqrt{\frac{T}{\mu_1}}$$
 $x < 0$ $v_2 = \sqrt{\frac{T}{\mu_2}}$ $x > 0$

We find that the amplitude of the transmitted wave is equal to the sum of the amplitudes of the incident and reflected waves in the following relation

$$A_I + A_R = A_T$$

From this we can derive the transmission and reflection coefficients, τ_{12} and ρ_{12}

$$\tau_{12} = \frac{2k_1}{k_1 + k_2} = \frac{2\sqrt{\mu_1}}{\sqrt{\mu_1} + \sqrt{\mu_2}}$$

$$\rho_{12} = \frac{k_1 - k_2}{k_1 + k_2} = \frac{\sqrt{\mu_1} - \sqrt{\mu_2}}{\sqrt{\mu_1} + \sqrt{\mu_2}}$$

7 Wave Packets and Dispersion

If the phase speed depends on the wavenumber or frequency of the wave, this is said to be in a dispersive medium. In this case,

$$\frac{\omega}{k} = v(\omega)$$

The important part in this chapter is being able to find the group velocity, which is the following

$$v_g = \frac{d\omega}{dk}$$