## Exhibit I

## D&B Worldbase 1784 Layout w Lat/Long

Positions	Leng	*	**	Field Name	Field Description
Start-End	th				
0001-0002	002	N	Z	Filler	Reserved for future use
0003-0011	009	N	Z	D-U-N-S <sup>®</sup> Number	A randomly generated nine-digit number assigned by D&B to
					identify unique business establishments.
0012-0101	090	Α	С	Business Name	The Primary or Registered name of the business.
0102-0191	090	Α	С	Tradestyle Name	The Secondary Name of the business, if used.
0192-0192	001	Α	С	Registered Address Indicator	When set to Y this denotes that the Address available is also
					the Registered Address. This is common on global records
					where address details are registered with local and/or public
					registries. In some cases the registered address can be the
		_	_		office of the solicitor registering the business name.
0193-0256	064	Α	С	Street Address	The physical street location of the business. Generally in local
	064	_			language.
0257-0320	064	Α	С	Street Address 2	The physical address line 2 of the business. Generally in local
0224 0250	020		_	City Name	language.
0321-0350	030	Α	С	City Name	Name of the city where the business is located. Generally in
0251 0200	020	^		State / Dues din se Nome	local language.
0351-0380	030	Α	С	State/Province Name	Name of the state/province where the business is located.
0381-0400	020	^	_	Country Name	Generally in local language.
	020	Α	С	Country Name	Name of the country in English where the business is located.
0401-0406	006	Α	С	D&B City Code	D&B proprietary geographical code which indicates the city
					where the business is located. For US records, the code is
					unique within COUNTY, for non-US records, the code is unique within COUNTRY. Geographical codes provide one
					unique code value for various languages and/or spellings of
					the geographical data. For example, Brussels, Bruxelles, and
					Brussel – all are accurate and the same city but presented in
					English, French, and Dutch. The city geo code will be the
					same D&B city code for all presentations which allows
					searches in any language to return back all versions of the
					city. Only validated city names carry a city code, otherwise
					the code is blank.
0407-0409	003	N	Z	D&B County Code	D&B geographical code which indicates the county where the
				,	business is located. Populated in US & Canada only; unique
					within state/province. Zeroes if not available.
0410-0412	003	Α	С	D&B State/Province Code	D&B geographical code which indicates the state/province
					(aka primary subdivision) where the business is located. Only
					validated state/province names carry a state/province code.
					Zeroes if not available.
0413-0416	004	Α	С	State/Province Abbreviation	Abbreviations for the physical state/province name where the
					business is located.
0417-0419	003	Ν	Z	D&B Country Code	D&B three-digit code which indicates the country where the
					business is located. Assigned by D&B for WorldBase and
					other global products.
0420-0428	009	Α	С	Postal Code	Postal or zip code for the physical address location of the
					business.

0429-0429	001	A	С	D&B Region/Continent Code	D&B code which indicates the region where the business is located.  1 = Africa 2 = Australia/Asia 3 = Europe 4 = Middle East 5 = South & Central America 6 = North America	
0430-0461	032	Α	С	Mailing Address	Mailing location of the business (i.e. post office box)	
0462-0491	030	A	С	Mailing City Name	City name used for mailing address. Generally in local language.	
0492-0521	030	Α	С	Mailing County Name	Name of the county (aka secondary subdivision) where the business is located for mailing address.	
0522-0551	030	Α	С	Mailing State/Province Name	Name of state/province (aka primary subdivision) used for mailing address. Generally in local language.	
0552-0571	020	А	С	Mailing Country Name	Name of the country name in English where the business is located for the mailing address.	
0572-0577	006	Α	С	D&B Mailing City Code	D&B geographical code which indicates the city where the business is located for mailing address. For US records, the code is unique within COUNTY, for non-US records, the code is unique within COUNTRY. Geographical codes provide one unique code value for various languages and/or spellings of the geographical data. Only validated city names carry a city code, otherwise the code is blank.	
0578-0580	003	N	Z	D&B Mailing County Code	D&B geographical code which indicates the county where the business is located for mailing address. Populated in US and Canada only; unique within state/province. Zeros if not available.	
0581-0583	003	Α	С	D&B Mailing State/Province Code	D&B geographical code which indicates the state/province where the business is located for mailing address. Only validated state/province names carry a state/province code. Zeros if not available.	
0584-0587	004	Α	С	Mailing State/Province Abbreviation	Abbreviations for the state/province name where the business mailing address is located.	
0588-0590	003	N	Z	D&B Mailing Country Code	D&B three-digit country code which indicates the country where the mailing address of the business is located.  Assigned by D&B for WorldBase and other global products.	
0591-0599	009	Α	С	Mailing Postal Code	Postal or zip code for the mailing location of the business.	
0600-0600	001	A	С	D&B Mailing Region/Continent Code	D&B code which indicates the region of the mailing address of the business.  1 = Africa	
0601-0616	016	A	С	National Identification Number	Business identification number used in some countries for business registration and tax collection. Examples include VAT Numbers, CRO numbers (UK), Siren numbers (France). FEIN Number (US) is not included in WorldBase. Note: The National ID field in legacy products such as the WB1784 Record is 16 bytes. A 20-byte National ID field is available in the WorldBase Business Side File and GDMI File.	
0617-0621	005	А	С	National Identification Type Code	Code that identifies the type of National ID number provided; i.e. '12' = CRO, '14' = Siren. A table listing of all acceptable code values is available.	
0622-0625	004	А	С	Country Access Code	The international dialing code used to access the country phone system from outside the country. Can be 1 to 4 digits.	

0626-0641	016	A	С	Telephone Number	Telephone number for the business with no formatting or punctuation. Lengths of telephone numbers are country specific and may vary in length within country. The international dialing code is not included in the telephone number.
0642-0657	016	Α	С	Filler	Filler. Internal Use Only. Previously Cable Telex Number.
0658-0673	016	A	С	Facsimile Number	The fax number of the business. Provided as entered in the local database with no formatting or punctuation. Note: US does NOT supply fax number to WorldBase.
0674-0733	060	А	С	Chief Executive Officer Name	The principal with the highest ranking authority of the business at this location.
0734-0793	060	Α	С	Chief Executive Officer Title	The title (in English) of the principal with the highest authority at this location. May be abbreviated.
0794-0834	041	А	С	Line of Business	Narrative description in English of the operations or activities of the business. Relates to the primary four-digit 1987 US SIC.
0835-0838	004	A	С	US 1987 SIC 1	The US 1987 standard industrial classification (SIC) code system categorizes business establishments based upon the type of activity done by that business at that location. A business can have up to six SIC codes. The first-listed SIC code represents the primary operations of the business. Then, SIC codes are assigned in descending order according to the percentage of the revenue contributed by each function of the business. If countries collect other industry classifications ( <i>Primary Local Activity Code</i> -position 859-866), local classifications are converted to the standard 1987 US SIC Code. The SIC code of a parent/ultimate may include the activities of its subsidiaries.
0839-0842	004	Α	С	US 1987 SIC 2	The secondary SIC code of the business.
0843-0846	004	Α	С	US 1987 SIC 3	The third SIC code of the business.
0847-0850	004	Α	С	US 1987 SIC 4	The fourth SIC code of the business.
0851-0854	004	Α	С	US 1987 SIC 5	The fifth SIC code of the business.
0855-0858	004	Α	С	US 1987 SIC 6	The sixth SIC code of the business.
0859-0866	008	A	С	Primary Local Activity Code	The local industry classification code if different from the 1987 US SIC. Examples include 1972 US SIC, SBA, APE, and NACE. See Appendix for examples on use of Primary Local Activity Code.
0867-0869	003	A	С	Local Activity Type Code (Activity Indicator)	If <i>Primary Local Activity Code</i> is available, this indicator identifies which activity code type is provided. A table listing of all acceptable code values is available. For example, '60' = 1972 US SIC. See Appendix for examples on use of Local Activity Type Code.
0870-0873	004	N	Z	Year Started	A four-digit numeric field representing the year that the current ownership of the business has taken control or the year established if no control change has taken place. Not available on branch records.
0874-0891	018	N	Z	Sales Volume (local currency)	Sales value for the business in local currency. See <i>Currency Code-position 908-911</i> to determine currency provided for Sales figure. Sales figure can be a consolidated figure to include Sales for the business and all subsidiary and branch locations OR a non-consolidated figure. Consolidated Sales is preferred and provided if available. Signed decimal field.

					Note: All local Sales volumes in the global environment are converted to US Dollar based on the DATE when the financial information was collected. All business records in the global environment have a financial date which is the date when the financial figures were filed or collected; that date could be this month, last year, or 5 years ago. Based on the date of the financial figures, we use the currency exchange rate from that month/year to convert from local currency to US Dollar. The global data environment keeps exchange tables back 10+ years to calculate accurate exchange rates based on the date of the financial information.
0892-0892	001	A	С	Sales Volume (local currency) Reliability Code	<ul> <li>0 - actual</li> <li>1 - low end of the range</li> <li>2 - estimated (all records) or not available when sales is greater than zero (all records) or modeled (US records)</li> <li>3 - modeled (non US records)</li> <li>blank - Not Available when Sales equal 0.</li> </ul>
0893-0907	015	N	Z	Sales Volume (US Dollars)	Sales value for the business in US dollars. If Sales value is collected in different local currency, local values are converted to US dollars. Signed decimal field.  Note: Data is converted to US dollars based on the date of the financial figures/statement of the record. If the Sales figure is from Jun-2006, the conversion rate is as of Jun-2006. All financial figures will have a financial date in global products.
0908-0911	004	A	С	Currency Code	Code indicating which currency the financial figures data (Sales, Net Worth, Profit/Loss) is represented. A table listing of all acceptable code values is available. For example, '280' = Japanese Yen.
0912-0918	007	N	Z	Employees Here	The number of employees at this location.
0919-0919	001	A	С	Employees Here Reliability Code	Code value indicating the source reliability of the Employee Here figure: 0 - actual 1 - low end of the range 2 - estimated (all records) or not available when Employees Here is greater than zero (all records) or modeled (US records) 3 - modeled (non US records) blank - Not Available when Employees Here equal 0.
0920-0926	007	N	Z	Employees Total	The total number of employees in the business organization. The employee figure can be a consolidated figure to include Employee counts for the business and all subsidiary and branch locations OR a non-consolidated figure. Consolidated Employee is preferred and provided if available.
0927-0927	001	A	С	Employees Total Reliability Code	Code value indicating the source reliability of the Employee Total figure: 0 - actual 1 - low end of the range 2 - estimated (all records) or not available when Employees Total is greater than zero (all records) or modeled (US records) 3 - modeled (non US records) blank - Not Available when Employees Total equal 0.

0928-0928	001	А	С	Principals Included Indicator	Indicates that the principals are included in the employee total figure. ('Y' = included) Primarily available on non-US records.	
0929-0929	001	A	С	Import/Export/Agent Code	D&B-collected information which indicates that the busin either imports materials for re-manufacture or sale, expo products to other countries, or both.  Values include:  A Import/Export/Agent  B Imports & Exports  C Imports  D Imports & Agent  E Exports & Agent  F Agent - keeps no inventory and does not take title good of None or Not Available  H Exports  Blank Not available	
0930-0932	003	N	Z	Legal Status Code	D&B code that identifies the legal status/structure of the business:  Possible codes are: blank or 0 = Not Available 3 = Corporation 8 = Joint Venture 12 = Partnership 13 = Proprietorship 120 = Foreign Company A table listing of all acceptable code values is available.	
0933-0933	001	N	Z	Filler	Field is currently not used, formerly Control Indicator.	
0934-0934	001	N	Z	Status Code  Subsidiary Indicator	D&B code that provides business data of the record:  0 = Single Location - no other entities report to the business  1 = Headquarter/Parent - branches and/or subsidiaries report  to the business  2 = Branch - secondary location to a headquarter location  4 = Division - a separate operating unit of a corporation. A division may have its own name and officers, but it does not have stock and is not incorporated.  Note: The Status Code adds insight with the Subsidiary Code, position 935. It is possible to have a Single Location status and Subsidiary code or a Headquarter status and Subsidiary code. Blank when not available.	
0935-0935	001	N	Z	Subsidiary Indicator	D&B code which indicates whether the business is a subsidiary.  0 = Not a subsidiary  3 = Is a subsidiary  Populated on linked records only; otherwise blank.	
0936-0937	002	N	Z	Filler	Reserved for future use.	
0938-0946	009	N	Z	Previous D-U-N-S® Number	The D-U-N-S number that was previously assigned to this business.	
0947-0954	008	A	С	Full Report Date	The date when a complete review of all Business Information Report data was updated about the business. The format of the field is YYYYMMDD. Data collection methods have changed and updates are more frequent to sections of the	

					business report. Report Date does not reflect the age of the business data of the report.	
0955-0956	002	N	Z	Filler	Reserved for future use.	
0957-0965	009	N	Z	Headquarter/Parent D-U-N-S® Number	D-U-N-S number of the Parent/Headquarter organization. Blank if not linked.	
0966-1055	090	Α	С	Headquarter/Parent Business Name	The primary name of the Parent/Headquarter company. Blank if not linked.	
1056-1119	064	Α	С	Headquarter/Parent Street Address	Physical street address of the Parent/Headquarter company. Blank if not linked.	
1120-1149	030	Α	С	Headquarter/Parent City	City where the Parent/Headquarter is located. Blank if not linked.	
1150-1179	030	Α	С	Headquarter/Parent State/Province	State/province where the Parent/Headquarter is located. Blank if not linked.	
1180-1199	020	Α	С	Headquarter/Parent Country Name	Name of country in English where the Parent/Headquarter is located. Blank if not linked.	
1200-1205	006	А	С	Headquarter/Parent D&B City Code	Code of the city where the Parent/Headquarter is located. Blank if not linked.	
1206-1208	003	N	Z	Headquarter/Parent D&B County Code	Code of the county where the Parent/Headquarter is located. Present when Parent/Headquarter is located in US or Canada. Blank if not linked.	
1209-1212	004	Α	С	Headquarter/Parent State/Province Abbreviation	Abbreviated state name where Parent/Headquarter is located. Blank if not linked.	
1213-1215	003	N	Z	Headquarter/Parent D&B Country Code	D&B three-digit code for the country where the Parent/Headquarter is located. Blank if not linked.	
1216-1224	009	Α	С	Headquarter/Parent Postal Code	Postal or zip code where the Parent/Headquarter is located. Blank if not linked.	
1225-1225	001	Α	С	Headquarter/Parent D&B Region/Continent Code	D&B code for the region where the Parent/Headquarter is located. Blank if not linked.	
1226-1227	002	N	Z	Filler	Reserved for future use.	
1228-1236	009	N	Z	Domestic Ultimate D-U-N-S® Number	D-U-N-S Number for the domestic ultimate, which is the highest family member in the same country as case business record as you walk up this 'branch' of the tree. A case may be its own domestic ultimate.	
1237-1326	090	Α	С	Domestic Ultimate Business Name	The primary name of the domestic ultimate business. Blank if not linked.	
1327-1390	064	Α	С	Domestic Ultimate Street Address	Physical street address of the domestic ultimate company. Blank if not linked.	
1391-1420	030	Α	С	Domestic Ultimate City Name	Name of the city where the domestic ultimate is located. Blank if not linked.	
1421-1450	030	Α	С	Domestic Ultimate State/Province Name	Name of the state or province in which the domestic ultimate is located. Blank if not linked.	
1451-1456	006	Α	С	Domestic Ultimate D&B City Code	Code for the city where the domestic ultimate is located. Blank if not linked.	
1457-1459	003	N	Z	Domestic Ultimate D&B Country Code	Code for the country where the domestic ultimate is located. Blank if not linked.	
1460-1463	004	Α	С	Domestic Ultimate State Abbreviation	Abbreviated name of the state or province in which the domestic is located. Blank if not linked.	
1464-1472	009	Α	С	Domestic Ultimate Postal Code Postal code for the city in which the domestic ultimate located. Blank if not linked.		
1473-1473	001	Α	С	Global Ultimate Indicator	If 'Y', this case is the global ultimate, otherwise 'N'. Blank if not linked.	
1474-1475	002	N	Z	Filler	Reserved for future use.	

1787-1787	001			Transactional Indicator	A = ADD C = Change D = Delete		
1771-1786	016	Α	С	Longitude	The angular distance east or west from the prime meridian measured through 180 degrees		
1761-1770	010	Α	С	Latitude	The angular distance north or south from the earth's equator measured through 90 degrees		
4704 (770	040				1 3 15 Subsidiary of Sub13 (Sub14) Blank if not linked.		
					2 0 02 Branch of Sub1 1 3 03 Subsidiary of Sub1 (Sub 2)		
					1 0 01 Global Ultimate 1 3 02 Headquarters (Sub1)		
					hierarchy code. Hierarchy code examples: <u>Status Subsidiary Hierarchy Description</u>		
					A subsidiary hierarchy code is one greater than its parent		
					01. A branch hierarchy is the same value as it's headquarter.		
					indicators, can pinpoint the exact location of a business entity within a family tree. The hierarchy on the global ultimate =		
1759-1760	002	N	Z	Hierarchy Code	A two-position code, used with the status and subsidiary		
					name and family sequence within each group. Blank if not linked.		
1750-1758	009	N	Z	DIAS Code	A code which sequences a file in order by ultimate parent		
					worldwide. Every family member of tree carries the same count. Blank if not linked.		
					and all subsidiaries and branches of the entire family tree		
1745-1749	005	N	Z	Number of Family Members	The number of family members including the global ultimate		
1744-1744	001	Α	С	Global Ultimate D&B Region/Continent Code	Code for the region in which the ultimate company is located Blank if not linked.		
1735-1743	009	Α	С	Global Ultimate Postal Code	Postal (ZIP) code of the ultimate company. Blank if not linked.		
1732-1734	003	N	Z	Global Ultimate D&B Country Code	Code for the country where the company is located. Blank if not linked.		
				Abbreviation	company is located. Blank if not linked.		
1728-1731	004	Α	С	Global Ultimate State/Province	Present when US or Canadian ultimate. Blank if not linked.  Abbreviated name of the state/province where the ultimate		
1725-1727	003	N	Z	Global Ultimate D&B County Code	Blank if not linked.  Code for the county where the ultimate company is located.		
1719-1724	006	Α	С	Global Ultimate D&B City Code	Code for the city where the ultimate company is located.		
1699-1718	020	Α	С	Global Ultimate Country Name	Name of the country where the ultimate company is located.  Blank if not linked.		
1669-1698	030	Α	С	Global Ultimate State/Province	Name of the state or province in which the ultimate company is located. Blank if not linked.		
1639-1668	030	Α	С	Global Ultimate City Name	Name of the city where the ultimate company is located. Blank if not linked.		
1575-1638	064	Α	С	Global Ultimate Street Address	Physical address of the ultimate company. Blank if not linked.		
1485-1574	090	Α	С	Global Ultimate Business Name	Name of the ultimate company. Blank if not linked.		
					family. Global ultimate records carry their own case D-U-N-S number in this field so that a common sort and/or match area is available for all family members. Blank if not linked.		
1476-1484	009	N	Z	Global Ultimate D-U-N-S® Number	is available for all family members. Blank if not linked.		

Note: As it relates to LAT/LONG the fields will be at least 5 digits to the right of the decimal, where available.