


Lecture 18 Virtual Memory

Memory Management Virtual Memory OS Loader Main **Logical Address** Disk Memory Space of OS **Process P1** lower P1 P2 limit = 0P2 Code binary binary <u>Code</u> <u>Cod</u>e Code Data Data -P1 Heap Data Heap upper Stack Data limit = max Stack P3




- Page tables may be large, consuming much RAM
- Key observation: not all pages in a logical address space need to be kept in memory
 - in the simplest case, just keep the current page where the PC is executing
 - all other pages could be on disk
 - when another page is needed, retrieve the page from disk and place in memory before executing
 - this would be costly and slow, because it would happen every time that a page different from the current one is needed

- Instead of just keeping one page, keep a subset of a process's pages in memory
 - Load just what you need, not the entire address space
 - use memory as a cache of frequently or most recently used pages
 - rely on a program's behavior to exhibit locality of reference
 - if an instruction or data reference in a page was previously invoked, then that page is likely to be referenced again in the near future

- Most programs exhibit some form of locality
 - looping locally through the same set of instructions
 - branching through the same code
 - executing linearly, the next instruction is typically the next one immediately after the previous instruction, rather than some random jump
- Thus process execution revisits pages already stored in memory
 - so you don't have to go to disk each time the program counter (PC) jumps to a different page

- On-demand paging is used to page in new pages from disk to RAM
 - only when a page is needed is it loaded into memory from disk
- Can page in an entire process on demand:
 - starting with "zero" pages
 - the reference to the first instruction causes the first page of the process to be loaded on demand into RAM.
 - Subsequent pages are loaded on demand into RAM as the process executes.

- On-demand paging loads a page from disk into RAM only when needed
 - in the example below, pages A and C are in memory, but page B is not




Virtual Memory Advantages

- 1. Virtual address space can now exceed physical RAM!
 - Only a subset (most demanded) of pages are kept in RAM
 - We have decoupled virtual memory from physical memory.

2. Fit many more processes in memory


Virtual Memory Advantages

- 3. Decreases swap time
 - there is less to swap
- 4. Can have large sparse address spaces
 - most of the address space is unused
 - Does not taking up physical RAM
 - a large heap and stack that is mostly unused/empty won't take up any actual RAM until needed




- Open questions to be answered:
 - how is a needed page loaded into memory from disk?
 - how many pages in memory should be allocated to a process?
 - if the # of pages allocated to a process is exceeded, i.e. the cache is full, then how do you choose which page to replace?

On-demand paging causes a page fault, which goes through the following steps









RAM


0

2

3

4

On-demand paging causes a page fault, which goes through the following steps



On-demand paging causes a page fault, which goes through the following steps P1's Page Table **RAM** 4 0 0 OS trap to Disk page jump fault table handler 2 Α 2 3 В 4 Α

On-demand paging causes a page fault, which goes through the following steps P1's Page Table **RAM** 4 0 0 OS trap to Disk page jump 3 fault table handler 2 Α 2 3 В 4 Α

On-demand paging causes a page fault, which goes through the following steps P1's Page Table **RAM** 4 0 0 OS trap to Disk page jump 3 fault table handler 2 Α 2 В 3 В 4 Α

On-demand paging causes a page fault, which goes through the following steps P1's Page Table **RAM** 4 0 0 OS trap to 6 Disk page jump 3 fault table jmp B handler 2 Α 2 В 3 В 4 Α

- Page-fault steps to load a page into RAM:
 - 1. MMU detects a page is not in memory (invalid bit set) which causes a *page-fault trap* to OS
 - 2. OS saves registers and process state. Determines that the fault was due to demand paging and jumps to page fault handler
 - 3. Page fault handler
 - a) If reference to page not in logical A.S. then seg fault.
 - b) Else if reference to page in logical A.S., but not in RAM, then load page
 - c) OS finds a free frame
 - d) OS schedules a disk read. Other processes may run in meantime.
 - 4. Disk returns with interrupt when done reading desired page. OS writes desired page into free frame
 - OS updates page table, sets valid bit of page and its physical location
 - 6. Restart interrupted instruction that caused the page fault

- OS can retrieve the desired page either from the disk's
 - file system, or
 - swap space/backing store
 - faster, avoids overhead of file system lookup
- pages can be in swap space because:
 - the entire executable file was copied into swap space when the program was first started.
 - Avoids file system, but also allows the copied executable to be laid out contiguously on disk's swap space, for faster access to pages (no seek time)


- pages can be in swap space because:
 - as pages have to be replaced in RAM, they are written to swap space instead of the file system's portion of disk.
 - The next time they're needed, they're retrieved quickly from swap space, avoiding a file system lookup.

Performance of On-Demand Paging


- Want to limit the number/frequency of page faults, which cause a read from disk, which slows performance
 - disk read is about 10 ms
 - memory read is about 10 ns
- What is the average memory access time?
 - average access time = p*10 ms + (1-p)*10 ns, where p = probability of a page fault.
 - if p=.001, then average access time = 10 μ s >> 10 ns (1000 X greater!)
 - to keep average access time within 10% of 10 ns, would need a page fault rate lower than p<10⁻⁷
 - Reducing page fault frequency improves performance in a big way



- Demand paging loads a page from disk into RAM only when needed
 - in the example below, pages A and C in memory, but page B is not
 - How can we access B if all other frames are already used




P1's Address Space



B is not in memory and there are no frames available

P1's Page Table



RAM

0

2

4




X

Must decided which page is to be evicted from memory

- As processes execute and bring in more pages on demand into memory, eventually the system runs out of free frames
 - need a page replacement policy
 - Steps:
 - 1. select a victim frame that is not currently being used
 - 2. save or write the victim frame to disk, update the page table (page now invalid)
 - 3. load in the new desired page from disk
 - If out of free frames, each page fault causes 2 disk operations, one to write the victim, and one to read the desired page
 - this is a big performance penalty


In Step 3b, we modify traditional on-demand paging to include a write of the victim frame to disk



- To reduce the performance penalty of 2 disk operations, systems can employ a dirty/modify bit
 - modify bit = 0 initially
 - when a page in memory is written to, set the bit = 1
 - when a victim page is needed, select a page that has not been modified (dirty bit = 0)
 - such an unmodified page need not be written to disk, because its mirror image is already on disk!
 - this saves on disk I/O reduces to only 1 disk operation (read of desired page)


Page Table Status Bits

- Each entry in the page table can conceptually store several extra bits of metadata information along with the physical frame # f
 - Valid/invalid bits for memory protection, accessing an invalid page causes a page fault



Page Table Status Bits

- dirty bits has the page been modified for page replacement?
- R/W or Read-only bits for memory protection, writing to a read-only page causes a fault and a trap to the OS
- Reference bit useful for Clock page replacement algorithm



Recap ...

- Virtual memory
 - Keep only a few pages in memory, rest on disk
 - On-demand paging: retrieve a page when needed
 - Page fault
 - A referenced page is not loaded in memory
 - OS blocks the process and retrieves the referenced page
 - Significant performance overhead need to keep page fault frequency low, e.g. less than 1 in 10⁷ for overhead <10%
 - Page replacement algorithm
 - Principle of locality of reference
 - Dirty bit: choose a clean page before a dirty page