

Eidgenössische Technische Hochschule Zürich Swiss Federal Institute of Technology Zurich

Spring Term 2016



ADVANCED COMPUTER NETWORKS Project P1: Introduction to RDMA Programming

Assigned on: 12 May 2016

Due by: 1 June 2016, 23:59

1 Introduction

The goal of this project is to give an introduction to RDMA programming [3, 4] and related software [6]. This is a group project with the maximum group size of 2. This exercise assumes basic knowledge of Linux and C. Start with downloading the project handout tarball we provide from the website and extract it into a folder of your choice.

```
tar -xzvf rdma_assignment_handout.tar.gz
cd rdma_assignment_handout
tar -xzf softiwarp.tar.gz
```

You will find some reference material and helper scripts here.

2 Setting up the RDMA Framework for Development

In this section we provide the detailed instructions to install and configure the software/packages needed to solve this exercise. For this programming assignment, you will need a 64-bit Linux system (Ubuntu, Debian) with a kernel that is version 3.13.0 or newer. One option can be installing an image inside VirtualBox (http://www.virtualbox.org/). We have tested our solution using various configurations: a 64-bit system running Ubuntu (14.04.02 LTS Trusty Tahr) and 64-bit Ubuntu image running inside VirtualBox. We are providing a VM image where everything is already installed. You can import this VM in your virtualbox and it should give you working setup. The username for the VM is acn (password: nopass) and you should have sudo access with this user.

You only need to insert relevant kernel modules after a fresh reboot. You can use following script inserting proper kernel modules:

rdma_assignment_handout/addmodules.sh

2.1 Installation of RDMA Related Packages

In case you want to use some other machine for the development, then you can use following instructions as a guideline to setup the development environment. Following instructions assume Ubuntu/Debian based system. Please adapt the instructions based on your setup. You can also refer to [1] for additional information about installation, and for help in debugging installation related issues.

2.1.1 Installing kernel source packages

We will need to install kernel source as we will be needing it to compile the kernel modules needed for RDMA iWARP.

Here are the packages needed.

```
sudo apt-get install libtool autoconf automake linux-tools-common
sudo apt-get install fakeroot build-essential crash kexec-tools makedumpfile kernel-wedge
sudo apt-get build-dep linux
sudo apt-get install git-core libncurses5 libncurses5-dev libelf-dev
sudo apt-get install linux-headers-$(uname -r)
```

2.1.2 Installing RDMA dependencies

Here we describe the steps required to get the RDMA framework ready for development.

```
sudo apt-get install libibverbs1 libibcm1 libibcm-dev ibverbs-utils libibverbs-dev
sudo apt-get install libibverbs1 librdmacm-dev librdmacm1 rdmacm-utils
```

2.1.3 Installation of the udev Rules File for Ubuntu Systems

Copy following udev rules file in proper location to make sure that your system will create RDMA related devices in /udev/infiniband/ correctly when proper kernel modules are inserted.

```
sudo cp rmda_assignment_handout/90-ib.rules /etc/udev/rules.d/
```

Typically, udev will detect the new rules and incorporate them automatically. You may have to Reboot your system in order for this modification to take effect (or restart the udev manager) if it does not work for you directly.

2.1.4 Building the SoftiWARP Kernel Driver

The SoftiWARP RDMA device comes with a kernel module and a user space library. You can build the SoftiWARP kernel driver as follows:

Go into the rdma_assginment_handout/siw/kernel/softiwarp that exists under the directory you extracted the softiwarp code. Build it using:

```
make clean
make
sudo make install
```

2.1.5 Building the SoftiWARP userspace libary

Then go to the rdma_assginment_handout/siw/userlib/libsiw-0.1 directory inside your extracted softiwarp directory and build the SoftiWARP user library as follows:

```
./autogen.sh
./configure
make clean
sudo make install
sudo ldconfig
```

In case you are using custom location for installation, then you may have to set the LD_LIBRARY_PATH environment variable accordingly:

```
export LD_LIBRARY_PATH=/your/custom/location/
sudo ldconfig
```

Also, you need to make sure that the siw.driver file placed correctly in your system's /etc/libibverbs.d directory. You can do that by creating following soft link to the default installation directory (shown bellow), or by copying the file directly in the /etc/libibverbs.d directory.

sudo ln -s /usr/local/etc/libibverbs.d /etc/libibverbs.d

2.2 Loading Kernel Modules

We use Open Fabric Enterprise Distribution (OFED) RDMA framework [2]. The OFED RDMA stack is part of the Linux kernel distribution and contains kernel modules. SoftiWARP kernel modules built in the last step is a device specific module, which upon loading is linked to the rest of the OFED module. To load all required modules into the system, we have provided a script called addmodules.sh in your assignment folder. This script is fairly simple and tries to make sure that all the requirements are met. Take a look into the script if you are getting any error.

At this point you should be able to see the siw module loaded in your system. You can verify this by doing lsmod | grep "siw".

2.3 Verify

To verify if the system is ready for the RDMA development you should be able to see a few RDMA capable devices using command ibv_devices. A sample output is shown below:

```
atr@localhost:~$ ibv_devices

device node GUID

-----
siw_eth0 3c970e986e2f0000
siw_lo 7369775f6c6f0000
atr@localhost:~$
```

2.4 In Case of Problems

In general, if you are having trouble until this point, make sure that you have the following things done right:

- Installation of all the necessary RDMA packages.
- LD_LIBRARY_PATH is set correctly. Verify using echo \$LD_LIBRARY_PATH
- siw related modules are loaded. Verify using 1smod | grep "siw"
- strace command can also be useful for debugging. Do man strace to see how to use this command.

If nothing else works, email Patrick or Pravin about the problem.

3 The Sample RDMA Client Server Application

In this section we describe the main task that you need to do in the context of this assignment. We start with giving a brief overview about the code that has been given out. The code implements a simple RDMA server client program. The code is split into:

- rdma_common.[ch]: contains some common RDMA work routines that come in handy while coding such as memory allocation and registration etc.
- rdma_server.c : contains RDMA server side logic.
- rdma_client.c : contains RDMA client side logic.

For a better understanding read the code, which is well commented.

The goal of the client is to copy a string buffer (the contents of that buffer are given by the user using the -s parameter of rdma_client) from a source buffer (identified by src) to a destination buffer (identified by dst) using a remote server buffer as a temporary buffer. The required logical steps can be summarized as below:

The RDMA server code can be found in rdma_server.c.

- a) Start an RDMA server and wait until a client connects, see start_rdma_server().
- b) Setup and prepare client specific resources for a new incoming connection, see setup_client_resources().
- c) Accept the client connection, see accept_client_connection().
- d) Send the server's buffer RDMA metadata (address, length, STAG) to the client, see send_server_metadata_to_client() (you will implement this function).
- e) Wait for disconnect from the client, then clean up and shutdown, see disconnect_and_cleanup.

The RDMA client code can be found in rdma_client.c.

- a) Setup and prepare connection resources for a new client connection, see client_prepare_connection().
- b) Prepare communication buffers where the client will receive the metadata from the RDMA server, see client_pre_post_recv_buffer(). This function shows how to prepare a receive work request.
- c) Connect to the server, see client_connect_to_server().

- d) Send client side RDMA metadata (address, length, STAG) to the server and wait until the client has received metadata for the remote buffer from the server, see client_send_metadata_to_server(). This function shows how to prepare a send work request. RDMA read and write requests are prepared in a similar manner.
- e) Write a local src buffer to the remote server buffer, whose credentials the client received in the last step. Do this using RDMA write functionality. Then read the remote server buffer into another local dst buffer using RDMA read functionality. See client_remote_memory_ops() (you will implement this function).
- f) Verify that src and dst buffers contain the same content, see check_src_dst().
- g) Disconnect and cleanup the client connection, see client_disconnect_and_clean().

See also figure 1 for the control flow.

3.1 Your Task

The provided code sets up RDMA connection related resources for the server and the client. The client successfully connects to the server and waits to receive RDMA metadata from the server. You task is to implement the following functions in the code:

- send_server_metadata_to_client() in rdma_server.c
- client_remote_memory_ops() in rdma_client.c

3.2 Debugging

For debugging there is a compile time macro debug in rdma_common.h. Enable it by defining ACN_RDMA_DEBUG. For rdma related calls read the man page or refer to [5].

To see what is happening at the device level, you can compile the siw module with DPRINT_MASK defined to DBG_ALL in the siw_debug.h file. The output of the device can be seen by using the dmesg command while running the experiment. These messages can show you common mistakes such as base and bound violations, permission errors, invalid stags etc. for RDMA operations. Additionally, you can enable selective debugging by choosing an appropriate DPRINT_MASK. Read the comments in the file. You need to unload (sudo rmmod siw) and reload (sudo insmod siw.ko) the siw module everytime you compile it for changes to take effect.

3.3 Correct Sample Output

Once you have correctly implemented the missing parts of the code, the output of your programs should look something like what is reproduced below.

Server

```
atr@localhost$ ./rdma_server

Server is listening successfully at: 0.0.0.0 , port: 20886

A new connection is accepted from 127.0.0.1

Client side buffer information is received...

buffer attr, addr: 0xa58010 , len: 36 , stag : 0xf6e826
```

```
The client has requested buffer length of : 36 bytes A disconnect event is received from the client... Server shut-down is complete
```

Client

```
atr@localhost$ ./rdma_client -s "This is a test string for project P1"

Passed string is: This is a test string for project P1, with count 36

Trying to connect to server at: 127.0.0.1 port: 20886

The client is connected successfully

buffer attr, addr: 0x673f70, len: 36, stag: 0x47d0e0

SUCCESS, source and destination buffers match

Client resource clean up is complete
```

4 Hand-In Instructions

Please commit your solution to your SVN repository under the folder of assignment8 by the deadline. You only have to commit files that you have changed, i.e. at least rdma_client.c and rdma_server.c. See assignment 7 for detailed instructions on how to submit to the SVN repository.

4.1 Demo

You will have to demonstrate your solution in the exercise session in the last week of Semester (Thursday, June 2, 2016). When demonstrating your solution you should be able to show a working solution and demonstrate understanding how your implementation works.

References

- [1] Detailed blog about Installation. http://www.reflectionsofthevoid.com/2011/03/how-to-install-soft-iwarp-on-ubuntu.html.
- [2] OFED for Linux. https://www.openfabrics.org/index.php/resources/ofed-for-linux-ofed-for-windows/linux-sources.html.
- [3] RDMA Consortium. http://www.rdmaconsortium.org/.
- [4] Work on RDMA host software at IBM Research Zurich. http://www.zurich.ibm.com/sys/rdma/.
- [5] Detailed blog about RDMA. http://www.rdmamojo.com/.
- [6] SoftiWARP: Software iWARP kernel driver and user library for Linux. http://gitorious.org/softiwarp.




Figure 1: The interaction between server and client.

Appendix

When the provided code is run following output is generated on the client side:

Server:

Client:

```
acn@eucan-VirtualBox:code$ ./rdma_client -s "helloWorld"
Passed string is : helloWorld , with count 10
Trying to connect to server at : 127.0.0.1 port: 20886
The client is connected successfully
```

```
rdma_common.c : 185 : ERROR : Work completion (WC) has error status: -5 (means: Work Request Flus rdma_client.c : 295 : ERROR : We failed to get 2 work completions , ret = -5 rdma_client.c : 459 : ERROR : Failed to setup client connection , ret = -5
```

After an rdma_accept on the server side, the client is suppose to receive an ESTABLISHED event. But if server terminates (which happens in our case) before the client retrieves the event, the connection is gone and the client will get -22 on the event channel. But if the server is bit slower, the client might retrieve this event before the server exits. It is a non-deterministic case as network latencies are comparable to OS latencies.

To get a better picture you can insert this code snippet in the unimplemented function on the server side. Here the server does not terminate immediately but waits to receive client side credentials but then fails to send its own.

In this case, not the client fails to retrieve a valid receive event on the work completion index 1. Work completion index 0, that belonged to the send work request, is successful.