

Microsoft® C Compiler

for the MS-DOS® Operating System

Run-Time Library Reference

Microsoft Corporation

Information in this document is subject to change without notice and does not represent a commitment on the part of Microsoft Corporation. The software described in this document is furnished under a license agreement or nondisclosure agreement. The software may be used or copied only in accordance with the terms of the agreement. It is against the law to copy this software on magnetic tape, disk, or any other medium for any purpose other than the purchaser's personal use.

© Copyright Microsoft Corporation, 1984, 1985, 1986

If you have comments about the software, complete the Software Problem Report at the back of this manual and return it to Microsoft Corporation.

If you have comments about the software documentation, complete the Documentation Feedback reply card at the back of this manual and return it to Microsoft Corporation.

Microsoft, the Microsoft logo, MS, MS-DOS, and XENIX are registered trademarks of Microsoft Corporation. CodeView and The High Performance Software are trademarks of Microsoft Corporation.

UNIX is a trademark of AT&T Bell Laboratories.

Contents

Part 1 Overview 1

1 Introduction 3

1.1	About the C Library	5
1.2	About This Manual	6
1.3	Notational Conventions	8

2 Using C Library Routines 11

2.1	Introduction	13
2.2	Identifying Functions and Macros	13
2.3	Including Files	15
2.4	Declaring Functions	16
2.5	Argument Type Checking	17
2.6	Error Handling	19
2.7	File Names and Path Names	20
2.8	Binary and Text Modes	23
2.9	MS-DOS Considerations	24
2.10	Floating-Point Support	26
2.11	Using Huge Arrays with Library Functions	27

3 Global Variables and Standard Types 29

3.1	Introduction	31
3.2	_ambksz	31
3.3	daylight, timezone, tzname	32
3.4	_doserrno, errno, sys_errlist, sys_nerr	33
3.5	_fmode	34
3.6	_osmajor, _osminor	34
3.7	environ, _psp	35
3.8	Standard Types	36

4 Run-Time Routines by Category 39

4.1	Introduction	41
4.2	Buffer Manipulation	41
4.3	Character Classification and Conversion	42
4.4	Data Conversion	44
4.5	Directory Control	44
4.6	File Handling	45
4.7	Input and Output	46
4.8	Math	58
4.9	Memory Allocation	60
4.10	MS-DOS Interface	63
4.11	Process Control	64
4.12	Searching and Sorting	67
4.13	String Manipulation	68
4.14	Time	70
4.15	Variable-Length Argument Lists	71
4.16	Miscellaneous	71

5 Include Files 73

5.1	Introduction	75
5.2	assert.h	76
5.3	conio.h	76
5.4	ctype.h	76
5.5	direct.h	77
5.6	dos.h	77
5.7	errno.h	78
5.8	fcntl.h	79
5.9	float.h	79
5.10	io.h	79
5.11	limits.h	80
5.12	malloc.h	80
5.13	math.h	80
5.14	memory.h	81
5.15	process.h	81
5.16	search.h	82
5.17	setjmp.h	82
5.18	share.h	82
5.19	signal.h	82
5.20	stdarg.h	83
5.21	stddef.h	83
5.22	stdio.h	83
5.23	stdlib.h	85
5.24	string.h	85

5.25	sys\locking.h	86
5.26	sys\stat.h	86
5.27	sys\timeb.h	86
5.28	sys\types.h	86
5.29	sys\utime.h	87
5.30	time.h	87
5.31	varargs.h	87
5.32	v2tov3.h	87

Part 2 Reference 89

Appendixes 429

A Error Messages 431

A.1	Introduction	433
A.2	errno Values	433
A.3	Math Errors	436

B A Common Library for XENIX and MS-DOS 437

B.1	Introduction	439
B.2	Common Run-Time Routines	439
B.3	Common Global Variables	442
B.4	Common Include Files	443
B.5	Differences Between Common Routines	444

Index 455

Tables

Table 4.1	Forms of the spawn and exec Routines	67
Table R.1	printf Type Characters	308
Table R.2	printf Flag Characters	309
Table R.3	How printf Precision Values Affect Type	311
Table R.4	scanf Type Characters	338
Table A.1	errno Values and Their Meanings	434

Part 1

Overview

1	Introduction	3
2	Using C Library Routines	11
3	Global Variables and Standard Types	29
4	Run-Time Routines by Category	39
5	Include Files	73

1

2

3

Chapter 1

Introduction

1.1	About the C Library	5
1.2	About This Manual	6
1.3	Notational Conventions	8

1

2

3

1.1 About the C Library

The Microsoft® C Run-Time Library is a set of more than 200 predefined functions and macros designed for use in C programs. The run-time library makes programming easier by providing the following:

1. An interface to operating-system functions (such as opening and closing files)
2. Fast and efficient functions to perform common programming tasks (such as string manipulation), sparing the programmer the time and effort needed to write such functions

The run-time library is especially important in C programming because C programmers rely on the library for basic functions not provided by the language. These functions include, among others, input and output, storage allocation, and process control.

The functions in the Microsoft C Run-Time Library have been designed to maintain maximum compatibility between MS-DOS® and XENIX® or UNIX™ systems. Throughout this manual, references to XENIX systems are intended to encompass UNIX and UNIX-like systems as well.

Most of the functions in the C run-time library for MS-DOS operate compatibly with functions having the same names in the C run-time library for XENIX operating systems. If you are interested in portability, see Appendix B, "A Common Library for XENIX and MS-DOS." This appendix lists the functions of the run-time library that are specific to MS-DOS and describes differences (if any) between the operation of functions with the same names on XENIX and MS-DOS.

For additional compatibility, the math functions of the Microsoft C Run-Time Library have been extended to provide exception handling in the same manner as UNIX System V math functions.

For programmers interested in taking advantage of the specific features of MS-DOS, the library includes MS-DOS interface functions. These functions allow MS-DOS system calls and interrupts to be invoked from a C program. The library also contains console input and output functions to allow efficient reading and writing from the user's console.

To take advantage of the Microsoft C Compiler's type-checking capabilities, the include files that accompany the run-time library have been expanded. In addition to the definitions and declarations required by library functions and macros, the include files now contain function

declarations with argument-type lists. The argument-type lists enable type checking for calls to library functions. This feature can be extremely helpful in detecting subtle program errors resulting from type mismatches between actual and formal arguments to a function, and its use is highly recommended. However, you are not required to use argument type checking. The function declarations in the include files are enclosed in preprocessor `#if defined()` blocks, and are enabled only when you define the identifier `LINT_ARGS`.

To provide argument-type lists for all run-time functions, several new include files have been added to the list of standard include files for the C run-time library. The names of the new include files have been chosen to maintain as much compatibility as possible with the proposed ANSI (American National Standards Institute) standard for C and with XENIX and UNIX names.

1.2 About This Manual

The *Microsoft C Compiler Run-Time Library Reference* describes the contents of the Microsoft C Run-Time Library. The manual assumes that you are familiar with the C language and with MS-DOS. It also assumes that you know how to compile and link C programs on your MS-DOS system and that you can set up a compiler and linker environment using environment variables. If you have questions about compiling, linking, or setting up an environment, see the *Microsoft C Compiler User's Guide*, which covers these topics. If you have questions about the C language, see the *Microsoft C Compiler Language Reference*.

The *Microsoft C Compiler Run-Time Library Reference* has two major parts. Part 1, "Overview," gives an introduction to the C run-time library. It discusses general rules that apply to the run-time library as a whole and summarizes the elements of the run-time library.

Part 2, "Reference," gives descriptions of the run-time routines in alphabetical order for quick reference. Once you have familiarized yourself with the library rules and procedures, you will probably use the second part of the manual most often.

The remaining chapters of Part 1 are as follows:

Chapter 2, "Using C Library Routines," gives general rules for understanding and using C library routines and mentions special considerations that apply to certain routines. It is recommended that you read this chapter before using the run-time library; you may also want to turn to Chapter 2 when you have questions about library procedures.

Chapter 3, "Global Variables and Standard Types," describes variables and types that are defined in the run-time library and used by run-time library routines. This chapter also provides a cross-reference to the include file that defines or declares each variable or type. You may find these variables and types useful in your own routines. The variables and types are also described on the reference pages for the routines that use them in Part 2, "Reference."

Chapter 4, "Run-Time Routines by Category," breaks down the run-time library routines by category, lists the routines that fall into each category, and discusses considerations that apply to each category as a whole. The chapter is intended to complement Part 2, "Reference," making it easy to locate routines by task. Once you have located the names of the routines you want, you will need to turn to the appropriate page in Part 2, "Reference," for a detailed description.

Chapter 5, "Include Files," summarizes the contents of each include file provided with the run-time library.

The appendixes, which follow Part 2, provide more detailed information about error messages and about XENIX-compatible routines. Appendix A, "Error Messages," describes the error values and messages that can appear when using library routines. Appendix B, "A Common Library for XENIX and MS-DOS," lists routines of the MS-DOS C library that operate compatibly with routines of the same name on XENIX (and UNIX) systems. Appendix B also describes any differences between the MS-DOS and XENIX versions of the routines. Common global variables and include files are also discussed in this appendix.

The remainder of this chapter describes the notational conventions used throughout the manual.

1.3 Notational Conventions

The following notational conventions are used throughout this manual:

Convention	Meaning
Bold	C keywords, such as double and char , are set in bold type to distinguish them from ordinary identifiers and text. Within discussions of syntax, bold type indicates that the text must be entered exactly as shown.
	The names of run-time library routines, include files, global variables, standard types, constants, and identifiers used by the C library are also set in this font to emphasize that these names are reserved by the run-time library. For example, the routine name strcpy appears in this font; so does the include file stdio.h .
BOLD CAPITALS	Bold capital letters are used for the names of environment variables (such as TZ and PATH) and MS-DOS commands (such as SET and PATH). However, on MS-DOS, you are not required to use capital letters for these variables and commands.
<i>Italics</i>	Italics are used for the names of arguments to library routines. In an actual program, a specific name or value replaces the italicized argument name. For example, in <pre>double atof(<i>string</i>);</pre> the argument <i>string</i> is italicized to indicate that this is the general form for the atof routine. In an actual program, the user supplies a particular argument for the placeholder <i>string</i> . Occasionally, italics are used to emphasize particular words in the text.

Examples

Programming examples are displayed in a special typeface to resemble the output on your screen or the output of commonly used computer printers. Program fragments and variables quoted within regular text also appear in this format, as do error messages.

User input

Some examples show both program output and user input; in these cases, input is shown in a darker font. In the following example, .5 is entered by the user in response to the prompt Cosine value = :

Cosine value = .5
Arc cosine of 0.500000 = 1.047198

Ellipsis dots

.
. .

Vertical ellipsis dots are used in program examples to indicate that a portion of the program is omitted. For instance, in the following excerpt, the ellipsis dots between the two statements indicate that intervening program lines occur but are not shown:

```
int x, y;  
. .  
y = abs(x);
```

Horizontal ellipsis dots following an item indicate that more items having the same form may appear. For instance,

= { *expression* [, *expression*] ... }

indicates that one or more expressions separated by commas may appear between the braces ({ }).

[Double brackets]

Double brackets enclose optional arguments in the specification for each library routine. For example, in

`int open(pathname, oflag[], pmode]);`

the double brackets around *pmode* indicate that this argument is optional and that, when given, *pmode* must be separated from the previous argument by a comma.

Since the C language also uses brackets for array declarations and subscript expressions, these appear as single brackets in syntax discussions and examples containing arrays and subscript expressions. To illustrate,

```
char *args [4] ;
```

is an example showing the declaration of a four-element array; the brackets around 4 are a required part of the C language.

“Quotation marks”

Quotation marks set off terms defined in the text. For example, the term “token” appears in quotation marks when it is defined.

Some C constructs, such as strings, require quotation marks. Quotation marks required by the language have the form " " rather than “ ”. For example,

```
"abc"
```

is a C string.

SMALL CAPITALS

Small capital letters are used for the names of keys and key sequences such as CONTROL-C.

Chapter 2

Using C Library Routines

2.1	Introduction	13
2.2	Identifying Functions and Macros	13
2.3	Including Files	15
2.4	Declaring Functions	16
2.5	Argument Type Checking	17
2.6	Error Handling	19
2.7	File Names and Path Names	20
2.8	Binary and Text Modes	23
2.9	MS-DOS Considerations	24
2.10	Floating-Point Support	26
2.11	Using Huge Arrays with Library Functions	27

)

)

)

)

2.1 Introduction

To use a C library routine, simply call it in your program, just as if the routine were defined in your program. The C library functions are stored in compiled form in the library files that accompany your C compiler software.

At link time, your program must be linked with the appropriate C library file or files to resolve the references to the library functions and provide the code for the called library functions. The procedures for linking with the C library are discussed in detail in the *Microsoft C Compiler User's Guide*.

In most cases you must prepare for the call to the run-time library function by performing one or both of the following steps:

1. Include a given file in your program. Many routines require definitions and declarations that are provided by an include file.
2. Provide declarations for library functions that return values of any type but `int`. The compiler expects all functions to have `int` return type unless declared otherwise. You can provide these declarations by including the C library file containing the declarations or by explicitly declaring the functions within your program.

These are the minimum steps required; you may also want to take other steps, such as enabling type checking for the arguments in function calls.

The remainder of this chapter discusses the preparation procedures for using run-time library routines and special rules (such as file-name and pathname conventions) that may apply to some routines.

2.2 Identifying Functions and Macros

The words “function” and “routine” are used interchangeably throughout this manual, and in fact most of the routines in the C run-time library are C functions; that is, they consist of compiled C statements. However, some routines are implemented as “macros.” A macro is an identifier defined with the C preprocessor directive `#define` to represent a value or expression. Like a function, a macro can be defined to take zero or more arguments, which replace formal parameters in the macro definition. Defining and using macros are discussed in detail in the *Microsoft C Compiler Language Reference*.

The macros defined in the C run-time library behave like functions: they take arguments and return values, and they are invoked in a similar manner. The major advantage of using macros is faster execution time; their definitions are expanded in the preprocessing stage, eliminating the overhead required for a function call. However, because macros are expanded (replaced by their definitions) before compilation, they can increase the size of a program, particularly when there are multiple occurrences of the macro in the program. Unlike a function, which is defined only once regardless of how many times it is called, each occurrence of a macro is expanded. Functions and macros thus offer a trade-off between speed and size. In several cases, the C library provides both macro and function versions of the same library routine to allow you this choice.

Some important differences between functions and macros are described in the following list:

1. Some macros may treat arguments with side effects incorrectly when the macro is defined so that arguments are evaluated more than once. See the example that follows this list.
2. A macro identifier does not have the same properties as a function identifier. In particular, a macro identifier does not evaluate to an address, as a function identifier does. You cannot, therefore, use a macro identifier in contexts requiring a pointer. For instance, if you give a macro identifier as an argument in a function call, the *value* represented by the macro is passed; if you give a function identifier as an argument in a function call, the *address* of the function is passed.
3. Since macros are not functions, they cannot be declared, nor can pointers to macro identifiers be declared. Thus, type checking cannot be performed on macro arguments. The compiler does, however, detect cases where the wrong number of arguments is specified for the macro.
4. The library routines implemented as macros are defined through preprocessor directives in the library include files. To use a library macro, you must include the appropriate file, or the macro will be undefined.

The routines that are implemented as macros are marked with a note in Part 2, "Reference," of this manual. You can examine a particular macro definition in the corresponding include file to determine whether arguments with side effects will cause problems.

Example

```
#include <ctype.h>

int a = 'm';
a = toupper(a++);
```

This example uses the **toupper** routine from the standard C library. The **toupper** routine is implemented as a macro; its definition in **ctype.h** is as follows:

```
#define toupper(c)  ( (islower(c)) ? _toupper(c) : (c) )
```

The definition uses the conditional operator (? :). In the conditional expression, the argument **c** is evaluated twice: once to determine whether or not it is lowercase, and once to return the appropriate result. This causes the argument **a++** to be evaluated twice, thus increasing **a** twice rather than once. As a result, the value operated on by **islower** differs from the value operated on by **_toupper**.

Not all macros have this effect; you can determine whether a macro will handle side effects properly by examining the macro definition before using it.

2.3 Including Files

Many run-time routines use macros, constants, and types that are defined in separate include files. To use these routines, you must incorporate the specified file (using the preprocessor directive **#include**) into the source file being compiled.

The contents of each include file are different, depending on the needs of specific run-time routines. However, in general, include files contain combinations of the following:

- Definitions of manifest constants

For example, the constant **BUFSIZ**, which determines the size of buffers for buffered input and output operations, is defined in **stdio.h**.

- Definitions of types

Some run-time routines take data structures as arguments or return values with structure types. Include files set up the required structure type definitions. For example, most stream input and output operations use pointers to a structure of type **FILE**, defined in **stdio.h**.

- Two sets of function declarations

The first set of declarations gives return types and argument-type lists for run-time functions, while the second set declares only the return type. Declaring the return type is required for any function that returns a value with type other than **int**. (See Section 2.4, "Declaring Functions.") The presence of an argument-type list enables type checking for the arguments in a function call; see Section 2.5, "Argument Type Checking," for a discussion of this option.

- Macro definitions

Some routines in the run-time library are implemented as macros. The definitions for these macros are contained in the include files. To use one of these macros, you must include the appropriate file.

The reference page for each library routine lists the include file or files needed by the routine.

2.4 Declaring Functions

Whenever you use a library function that returns any type of value but an **int**, you should make sure that the function is declared before it is called. The easiest way to do this is to include the file containing declarations for that function, causing the appropriate declarations to be placed in your program.

Two sets of function declarations are provided in each include file. The first set declares both the return type and the argument-type list for the function. This set is included only when you enable argument type checking, as described in Section 2.5. Use of the argument-type-checking feature is highly recommended, since mismatches between actual and formal arguments to a function can cause serious and possibly hard-to-detect errors.

The second set of function declarations declares only the return type. This set is included when argument type checking is *not* enabled.

Your program can contain more than one declaration of the same function, as long as the declarations are compatible. This is an important feature to remember if you have older programs whose function declarations do not contain argument-type lists. For instance, if your program contains the declaration

```
char *calloc( );
```

you can also include the following declaration:

```
char *calloc(unsigned, unsigned);
```

Although the two declarations are not identical, they are compatible, so no conflict occurs.

You may provide your own function declarations instead of using the declarations in the library include files if you wish. It is recommended, however, that you consult the declarations in the include files to make sure that your declarations are correct.

2.5 Argument Type Checking

The Microsoft C Compiler offers a type-checking feature for the arguments in a function call. Type checking is performed whenever an argument-type list is present in a function declaration and the declaration appears before the definition or use of the function in a program. The form of the argument-type list and the type-checking method are discussed in full in the *Microsoft C Compiler Language Reference*.

For functions that you write yourself, you are responsible for setting up argument-type lists to invoke type checking. You can also use the /Zg command-line option to cause the compiler to generate a list of function declarations for all functions defined in a particular source file; the list can then be incorporated into your program. See Chapter 3, "Compiling," of the *Microsoft C Compiler User's Guide* for details on using the /Zg option.

For functions in the C run-time library, you can use the procedures outlined in this section to perform type checking on arguments. Every function in the C run-time library is declared in one or more of the library include files. Two declarations are given for each function: one with and

one without an argument-type list. The function declarations are enclosed in an `#if defined()` preprocessor block. If you define an identifier named **LINT_ARGS**, the declarations containing argument-type lists are processed and compiled, thus enabling argument type checking. If the **LINT_ARGS** identifier is not defined, the declarations without argument-type lists are included, and argument type checking will not be performed.

By default, **LINT_ARGS** is undefined, so no type checking is performed for library function arguments. You can define **LINT_ARGS** in one of two ways:

1. Use the `/D` command-line option to define **LINT_ARGS** at compile time.
2. Define **LINT_ARGS** with a `#define` directive in your source file. For the given file to be effective, the `#define` directive must occur *before* the `#include` directive.

The value of **LINT_ARGS** is not significant; you can define it to any value, including an empty value.

Note that the **LINT_ARGS** definition applies only to the library function declarations given in the include files. The function declarations in your source program or in your own include files are not affected. You can make the inclusion of your own declarations dependent on the **LINT_ARGS** identifier by using an `#if` or `#if defined()` directive. Refer to the library include files for a model.

Only limited type checking can be performed on functions that take a variable number of arguments. The following run-time functions are affected by this limitation:

- In calls to **cprintf**, **cscanf**, **printf**, and **scanf**, type checking is performed only on the first argument: the format string.
- In calls to **fprintf**, **fscanf**, **sprintf**, and **sscanf**, type checking is performed on the first two arguments: the file or buffer and the format string.
- In calls to **open**, only the first two arguments are type checked: the path name and open flag.
- In calls to **sopen**, the first three arguments are type checked: the path name, open flag, and sharing mode.

- In calls to **exec1**, **execle**, **execlp**, and **execlpe**, type checking is performed on the first two arguments: the path name and the first argument pointer.
- In calls to **spawnl**, **spawnle**, **spawnlp**, and **spawnlpe**, type checking is performed on the first three arguments: the mode flag, the path name, and the first argument pointer.

2.6 Error Handling

When calling a function, it is a good idea to provide for detection and handling of error returns, if any. Otherwise, your program may produce unexpected results.

For run-time library functions, you can determine the expected return value from the return-value discussion on each library page. In some cases no established error return exists for a function. This usually occurs when the range of legal return values makes it impossible to return a unique error value.

The discussion of some functions indicates that when an error occurs, a global variable named **errno** is set to a value indicating the type of error. Note that you cannot depend upon **errno** being set unless the description of the function explicitly mentions the **errno** variable.

When using functions that set **errno**, you can test the **errno** values against the error values defined in **errno.h**, or you can use the **perror** or **strerror** functions. If you want to print the system error message to standard error (**stderr**), use **perror**; if you want to store the error message in a string for later use in your program, use **strerror**. For a listing of **errno** values and the associated error messages, see Appendix A, "Error Messages."

When you use **errno**, **perror**, and **strerror**, remember that the value of **errno** reflects the error value for the last call that set **errno**. To prevent misleading results, before you access **errno** you should always test the return value to verify that an error actually occurred. Once you determine that an error occurred, you should use **errno** or **perror** immediately. Otherwise, the value of **errno** may be changed by intervening calls.

The math functions set **errno** upon error in the manner described on the reference page for each math function in Part 2 of this manual. Math functions handle errors by invoking a function named **matherr**. You can choose to handle math errors differently by writing your own error function

and naming it **matherr**. When you provide your own **matherr** function, that function is used in place of the run-time library version. You must follow certain rules when writing your own **matherr** function, as outlined on the **matherr** reference page in Part 2 of this manual.

You can check for errors in stream operations by calling the **ferror** function. The **ferror** function detects whether the error indicator has been set for a given stream. The error indicator is cleared automatically when the stream is closed or rewound, or the **clearerr** function can be called to reset the error indicator.

Errors in low-level input and output operations cause **errno** to be set.

The **feof** function tests for end-of-file on a given stream. An end-of-file condition in low-level input and output can be detected with the **eof** function or when a **read** operation returns 0 as the number of bytes read.

2.7 File Names and Path Names

Many functions in the run-time library accept strings representing path names and file names as arguments. The functions process the arguments and pass them to the operating system, which is ultimately responsible for creating and maintaining files and directories. Thus, it is important to keep in mind not only the C conventions for strings, but also the operating-system rules for file names and path names and the differences between MS-DOS and XENIX rules. There are several considerations:

1. Case sensitivity
2. Subdirectory conventions
3. Delimiters for path-name components

The C language is case sensitive, meaning that it distinguishes between uppercase and lowercase letters. The MS-DOS operating system is not case sensitive. When accessing files and directories on MS-DOS, you cannot use case differences to distinguish between identical names. For example, the names "FILEA" and "fileA" are equivalent and refer to the same file.

Portability considerations may also affect how you choose file names and path names. For instance, if you plan to port your code to a XENIX system, you should take the XENIX naming conventions into account. Unlike MS-DOS, XENIX is case sensitive. Thus, the following two directives are equivalent on MS-DOS but not on XENIX:

```
#include <STDIO.H>
#include <stdio.h>
```

To produce portable code, you should use the name that works correctly on XENIX, since either case works on MS-DOS.

The convention of storing some include files in a subdirectory named "sys" is also a XENIX convention. The convention is adopted in this manual, which includes the "sys" subdirectory in the specification for the appropriate include files. If you're not concerned with portability, you can disregard this convention and set up your include files accordingly. If you are concerned with portability, using the "sys" subdirectory can make portability between XENIX and MS-DOS easier.

The MS-DOS and XENIX operating systems differ in the handling of path-name delimiters. XENIX uses the forward slash (/) to delimit the components of path names, while MS-DOS ordinarily uses the backslash (\). However, MS-DOS is able to recognize the forward slash (/) as a delimiter internally in situations where a path name is expected. Thus, you can use either a backslash or a forward slash in MS-DOS path names within C programs, as long as the context is unambiguous and a path name is clearly expected.

Note

In C strings, the backslash is an escape character. It signals that a special escape sequence follows. If an ordinary character follows the backslash, the backslash is disregarded and the character is printed. Thus, the sequence "\\\" is required to produce a single backslash in a C string. (See your *Microsoft C Compiler Language Reference* for a full discussion of escape sequences.)

The above rule applies to most of the functions in the run-time library: wherever a path-name argument is required, you can use either a forward slash or a backslash as a delimiter. If you are concerned with portability to XENIX, you should use the forward slash.

However, the exceptions to the rule are important. The following functions accept string arguments that are not known in advance to be path names (they may be path names, but are not required to be). In these cases, the arguments are treated as C strings, and special rules apply:

- In the **exec** and **spawn** families of functions, you pass the name of a program to be executed as a child process and then pass strings representing arguments to the child process. The path name of the program to be executed as the child process can use either forward slashes or backslashes as delimiters, since a path-name argument is expected. However, it is recommended that you use backslashes in any path-name arguments to the child process, since the program being executed as the child process may simply expect a string argument that is not necessarily a path name.
- In the **system** call, you pass a command to be executed by MS-DOS; this command may or may not include a path name.

In these cases, only the backslash (\) separator should be used as a path-name delimiter. The forward slash (/) will not be recognized.

When you want to pass a path-name argument to the child process in an **exec** or **spawn** call, or when you use a path name in a **system** call, you must use the double-backslash sequence (\\) to represent a single path-name delimiter.

Examples

```
***** Example 1 *****
result = system("DIR B:\\TOP\\DOWN");
***** Example 2 *****
spawnl(P_WAIT, "bin/show", "show", "sub", "bin\\tell", NULL);
```

In the first example, double backslashes must be used in the call to **system** to represent the path name "B:\\TOP\\DOWN". Note that not all calls to **system** use a path name; for example,

```
result = system("DIR");
```

does not contain a path name.

In the second example, the **spawnl** function is used to execute the file named SHOW.EXE in the BIN subdirectory. Since a path name is expected as the second argument, the forward slash can be used. (A double backslash would also be acceptable.) The first two arguments passed to SHOW.EXE are the strings show and sub. The third argument is a string representing

a path name. Since this argument does not require a path name, the sequence \\ must be used to represent a single backslash between `bin` and `tell`.

2.8 Binary and Text Modes

Most C programs use one or more data files for input and output. Under MS-DOS, data files are ordinarily processed in "text" mode. In text mode, carriage-return-line-feed combinations (CR-LF) are translated into a single line-feed (LF) character on input. Line-feed characters are translated to carriage-return-line-feed combinations on output.

In some cases you may want to process files without making these translations. In binary mode, carriage-return-line-feed translations are suppressed.

You can control the translation mode for program files in the following ways:

- To process a few selected files in binary mode, while retaining the default text mode for most files, you can specify binary mode when you open the selected files. The `fopen` function opens a file in binary mode when the letter "b" is specified in the access *type* string for the file. If you use the `open` function, you can specify the `O_BINARY` flag in the *oflag* argument to cause the file to be opened in binary mode. For more information, see the reference pages for these functions in Part 2 of this manual.
- To process most or all files in binary mode, you can change the default mode to binary. The global variable `_fmode` controls the default translation mode. When `_fmode` is set to `O_BINARY`, the default mode is binary; otherwise, the default mode is text, except for `stdaux` and `stdprn`, which are opened in binary mode by default. The initial setting of `_fmode` is text, by default.

You can change the value of `_fmode` in one of two ways. First, you can link with the file `BINMODE.OBJ` (supplied with your compiler software). Linking with `BINMODE.OBJ` changes the initial setting of `_fmode` to `O_BINARY`, causing all files except `stdin`, `stdout`, and `stderr` to be opened in binary mode. This option is described in the *Microsoft C Compiler User's Guide*.

Second, you can change the value of `_fmode` directly, by setting it to `O_BINARY` in your program. This has the same effect as linking with `BINMODE.OBJ`.

You can still override the default mode (now binary) for particular files by opening them in text mode. The **fopen** function opens a file in text mode when the letter "t" is specified in the access *type* string for the file. If you use the **open** function, you can specify the **O_TEXT** flag in the *oflag* argument to cause the file to be opened in text mode. For more information, see the reference pages for these functions.

- The **stdin**, **stdout**, and **stderr** streams are opened in text mode by default; **stdaux** and **stdprn** are opened in binary mode. To process **stdin**, **stdout**, or **stderr** in binary mode instead, or to process **stdaux** or **stdprn** in text mode, use the **setmode** function. This function can also be used to change the mode of a file after it has been opened. The **setmode** function takes two arguments, a file handle and a translation-mode argument, and sets the mode of the file accordingly.

2.9 MS-DOS Considerations

The use of some functions in the run-time library is affected by the version of MS-DOS you are using. These functions are listed and described below:

Function	Description
dosexterr , locking , sopen	These three functions are effective only on MS-DOS versions 3.0 and later. The sopen function opens a file with file-sharing attributes; this function should be used in place of open when you want a file to have such attributes. The locking function locks all or part of a file from access by other users. The dosexterr function provides error handling for system call 59H in MS-DOS versions 3.0 and later.
dup , dup2	In certain cases, using the dup and dup2 functions on versions of MS-DOS earlier than 3.0 may cause unexpected results. When you use dup or dup2 to create a duplicate file handle for stdin , stdout , stderr , stdaux , or stdprn under versions of MS-DOS

earlier than 3.0, calling the **close** function with either handle causes errors in later I/O operations using the other handle. Under MS-DOS versions 3.0 and later, the **close** is handled correctly and does not cause later errors.

exec, spawn

When using the **exec** and **spawn** families of functions under versions of MS-DOS earlier than 3.0, the value of the *arg0* or *argv[0]* argument is not available to the user; a null string is stored in that position. Under MS-DOS versions 3.0 and later, the value of *arg0* or *argv[0]* is available to the user.

To write programs that will run on all versions of MS-DOS, you can use the **_osmajor** and **_osminor** variables (discussed in Section 3.5 of Chapter 3, "Global Variables and Standard Types") to test the current operating-system version number and take the appropriate action based on the result of the test.

Example

In the following example, the global variable **_osmajor** is tested to determine whether the file TEST.DAT should be opened using the **open** function (under versions of MS-DOS earlier than 3.0) or the **sopen** function (MS-DOS versions 3.0 and later):

```
unsigned char _osmajor;
.
.
.
if (_osmajor < 3)
    open("TEST.DAT", O_RDWR);
else
    sopen("TEST.DAT", O_RDWR, SH_DENYWR);
```

2.10 Floating-Point Support

The math functions supplied in the C run-time library require floating-point support to perform calculations with real numbers. This support can be provided by the floating-point libraries that accompany your compiler software or by an 8087 or 80287 coprocessor. (For information on selecting and using a floating-point library with your program, see the *Microsoft C Compiler User's Guide*.) The names of the functions that require floating-point support are listed below:

acos	_clear87*	exp	frexp	sin
asin	_control87*	fabs	gcvt	sinh
atan	cos	fcvt	hypot	sqrt
atan2	cosh	fieeetomsbin	ldexp	_status87*
atof	dieeetomsbin	floor	log	strtod
bessel[†]	difftime	fmod	log10	tan
cabs	dmsbintoieee	fmsbintoieee	modf	tanh
ceil	ecvt	_fpreset	pow	

* Not available with the **/FPa** compiler option

[†] The **bessel** function does not correspond to a single function, but to six functions named **j0**, **j1**, **jn**, **y0**, **y1**, and **yn**.

In addition, the **printf** family of functions (**cprintf**, **fprintf**, **printf**, **sprintf**, **vfprintf**, **vprintf**, and **vsprintf**) requires support for floating-point input and output if used to print floating-point values.

The C compiler tries to detect whether floating-point values are used in a program so that supporting functions are loaded only if required. This behavior provides a considerable space savings for programs that do not require floating-point support.

When you use a floating-point type character in the format string for the **printf** or **scanf** functions (**cprintf**, **fprintf**, **printf**, **sprintf**, **vfprintf**, **vprintf**, **vsprintf**, **cscanf**, **fscanf**, **scanf**, or **sscanf**), make sure that you specify floating-point values or pointers to floating-point values in the argument list to correspond to any floating-point type characters in the format string. The presence of floating-point arguments allows the compiler to detect the use of floating-point values. If a floating-point type character is used to print, for example, an integer argument, the use of floating-point values will not be detected because the compiler does not actually read the format string used in the **printf** and **scanf** functions. For instance, the following program produces an error at run time:

```
main( )           /* THIS EXAMPLE PRODUCES AN ERROR */
{
    long f = 10L;
    printf("%f", f);
}
```

In the preceding example, the functions for floating-point I/O are not loaded for the following reasons:

- No floating-point arguments are given in the call to **printf**.
- No floating-point values are used anywhere else in the program.

As a result, the following error occurs:

Floating point not loaded

The following is a corrected version of the above call to **printf**:

This version corrects the error by casting the long integer value to **double** type.

2.11 Using Huge Arrays with Library Functions

In programs that use the small, compact, medium, and large memory models, Microsoft C allows you to use arrays exceeding the 64K limit of physical memory in these models by explicitly declaring the arrays as **huge**. (See Chapter 8 of the *Microsoft C Compiler User's Guide*, "Working with Memory Models," for a complete discussion of memory models and the **near**, **far**, and **huge** keywords.) However, you cannot generally pass **huge** data items as arguments to C library functions. In the case of small and medium models, where the default size of a data pointer is **near** (16 bits), the only routines that accept huge pointers are **malloc** and **free**. In the compact-model library used by compact-model programs, and in the large-model library used by both large-model and huge-model programs, only the functions listed below use argument arithmetic that works with huge items:

bsearch	malloc	lsearch	memcmp	memset
fread	free	memccpy	memcpy	qsort
fwrite	lfind	memchr	memicmp	

With this set of functions, you can read from, write to, search, sort, copy, initialize, compare, or dynamically allocate and free huge arrays; any of these functions can be passed a huge pointer in a compact-, large-, or huge-model program without difficulty.

Chapter 3

Global Variables and Standard Types

- 3.1 Introduction 31
- 3.2 _amblksize 31
- 3.3 daylight, timezone, tzname 32
- 3.4 _doserrno, errno, sys_errlist, sys_nerr 33
- 3.5 _fmode 34
- 3.6 _osmajor, _osminor 34
- 3.7 environ, _psp 35
- 3.8 Standard Types 36

(

)

(

3.1 Introduction

The C run-time library contains definitions for a number of variables and types used by library routines. You can access these variables and types by including the files in which they are declared or by giving appropriate declarations in your program, as shown in the following sections.

3.2 _amblksiz

```
int _amblksiz;
```

The **_amblksiz** variable can be used to control the amount of memory space in the heap that is used by C for dynamic memory allocation. This variable is declared in the include file **malloc.h**.

The first time your program calls one of the dynamic memory allocation functions such as **calloc** or **malloc**, it asks the operating system for an initial amount of heap space that is typically much larger than the amount of memory requested by **calloc** or **malloc**. This amount is indicated by **_amblksiz**, whose default value is 8K. Subsequent memory allocations are allotted from this 8K of memory, resulting in fewer calls to the operating system when many relatively small items are being allocated. C calls the operating system again only if the amount of memory used by dynamic memory allocations exceeds the currently allocated space.

If the requested size in your C program is greater than **_amblksiz**, multiple blocks, each of size **_amblksiz**, are allocated until the request is satisfied; since the amount of heap space allocated is more than the amount requested, subsequent allocations can cause fragmentation of heap space. You can control this fragmentation by using **_amblksiz** to change the default “memory chunk” to whatever value you like, as in the following example:

```
_amblksiz = 2000;
```

Since the heap allocator always rounds the DOS request to the nearest power of two greater than or equal to **_amblksiz**, the preceding statement causes the heap allocator to reserve memory in the heap in multiples of 2K.

3.3 **daylight**, **timezone**, **tzname**

```
int daylight;
long timezone;
char *tzname[2];
```

The **daylight**, **timezone**, and **tzname** variables are used by several of the time and date functions to make local-time adjustments and are declared in the include file **time.h**. The values of the variables are determined by the setting of an environment variable named **TZ**.

You can control local-time adjustments by setting the **TZ** environment variable. The value of the environment variable **TZ** must be a three-letter time zone, followed by a possibly signed number giving the difference in hours between Greenwich mean time and local time. The number is positive moving west from Greenwich, negative moving east. The number may be followed by a three-letter daylight saving time zone. For example, the command

```
SET TZ=EST5EDT
```

specifies that the local-time zone is EST (Eastern standard time), that local time is five hours earlier than Greenwich mean time, and that daylight saving time (EDT) is in effect. Omitting the daylight saving time zone, as shown below, means that no corrections will be made for daylight saving time:

```
SET TZ=EST
```

When you call the **ftime** or **localtime** function, the values of the three variables **daylight**, **timezone**, and **tzname** are determined from the **TZ** setting. The **daylight** variable is given a nonzero value if a daylight saving time zone is present in the **TZ** setting; otherwise, **daylight** is 0. The **timezone** variable is assigned the difference in seconds (calculated by converting the hours given in the **TZ** setting) between Greenwich mean time and local time. The first element of the **tzname** variable is the string value of the three-letter time zone from the **TZ** setting; the second element is the string value of the daylight saving time zone. If the daylight saving time zone is omitted from the **TZ** setting, **tzname**[1] is an empty string.

If you do not explicitly assign a value to **TZ** before calling **ftime** or **localtime**, the following default setting is used:

```
PST8PDT
```

The **ftime** and **localtime** functions call another function, **tzset**, to assign values to the three global variables from the **TZ** setting. You can also call **tzset** directly if you like; see the **tzset** reference page in Part 2 of this manual for details.

3.4 – doserrno, errno, sys_errlist, sys_nerr

```
int _doserrno;
int errno;
char *sys_errlist[];
int sys_nerr;
```

The **errno**, **sys_errlist**, and **sys_nerr** variables are used by the **perror** function to print error information and are declared in the include file **stdlib.h**. When an error occurs in a system-level call, the **errno** variable is set to an integer value to reflect the type of error. The **perror** function uses the **errno** value to look up (index) the corresponding error message in the **sys_errlist** table. The value of the **sys_nerr** variable is defined as the number of elements in the **sys_errlist** array. For a listing of the **errno** values and the corresponding error messages, see Appendix A, “Error Messages.”

The **errno** values on MS-DOS are a subset of the values for **errno** on XENIX systems. Therefore, the value assigned to **errno** in case of error does not necessarily correspond to the actual error code returned by an MS-DOS system call. Instead, the actual MS-DOS error codes are mapped onto the **perror** values. If you want to access the actual MS-DOS error code, use the **_doserrno** variable. When an error occurs in a system call, the **_doserrno** variable is assigned the actual error code returned by the corresponding MS-DOS system call. (See the *Microsoft MS-DOS Programmer’s Reference Manual* for details on MS-DOS error returns.)

In general, you should use **_doserrno** only for error detection in operations involving input and output, since the **errno** values for input and output errors have MS-DOS error-code equivalents. Not all of the error values available for **errno** have exact MS-DOS error-code equivalents, and some may have no equivalents, causing the value of **_doserrno** to be undefined.

3.5 _fmode

```
int _fmode;
```

The **_fmode** variable controls the default file-translation mode. It is declared in **stdlib.h**. By default, the value of **_fmode** is 0, causing files to be translated in text mode (unless specifically opened or set to binary mode). When **_fmode** is set to **O_BINARY**, the default mode is binary. You can set **_fmode** to **O_BINARY** by linking with **BINMODE.OBJ** or by assigning it the value **O_BINARY**. See Section 2.8, “Binary and Text Modes,” in Chapter 2, “Using C Library Routines,” for a discussion of file-translation modes and the use of the **_fmode** variable.

3.6 _osmajor, _osminor

```
unsigned char _osmajor;
unsigned char _osminor;
```

The **_osmajor** and **_osminor** variables provide information about the version number of MS-DOS currently in use. They are declared in **stdlib.h**. The **_osmajor** variable holds the “major” version number. For example, under MS-DOS Version 2.0, **_osmajor** is equal to 2, while under MS-DOS Version 3.0, **_osmajor** is 3.

The **_osminor** variable stores the “minor” version number. For example, under MS-DOS Version 2.0, **_osminor** is 0 (zero), while under MS-DOS Version 2.1, **_osminor** is 1.

These variables can be useful when you want to write code to run on different versions of MS-DOS. For example, you can test the **_osmajor** variable before making a call to **sopen**; if the major version number is earlier (less) than 3, **open** should be used instead of **sopen**.

3.7 environ, - psp

```
char *environ[ ];  
unsigned int - psp;
```

The **environ** and **- psp** variables provide access to memory areas containing process-specific information. Both variables are declared in the include file **stdlib.h**.

The **environ** variable is an array of pointers to the strings that constitute the process environment. The environment consists of one or more entries of the form

name=string

where *name* is the name of an environment variable and *string* is the value of that variable. The *string* may be empty. The initial environment settings are taken from the MS-DOS environment at the time of the program's execution.

The **getenv** and **putenv** routines use the **environ** variable to access and modify the environment table. When **putenv** is called to add or delete environment settings, the environment table changes in size, and its location in memory may also change, depending on the program's memory requirements. The **environ** variable is adjusted in these cases and will always point to the correct table location.

The **- psp** variable contains the segment address of the program segment prefix (PSP) for the process. The PSP contains execution information about the process, such as a copy of the command line that invoked the process and the return address for process terminate or interrupt. (See your *Microsoft MS-DOS Programmer's Reference Manual* for details.) The **- psp** variable can be used to form a long pointer to the PSP, where **- psp** is the segment value and 0 is the offset value.

3.8 Standard Types

A number of run-time library routines use structure values whose types are defined in include files. These types are listed and described as follows, and the include file that defines each type is given. For a listing of the actual structure definitions, see the description of the appropriate include file in Chapter 5, "Include Files."

Standard Type	Description
complex	The complex structure, defined in math.h , stores the real and imaginary parts of a complex number and is used by the cabs function.
DOSERROR	The DOSERROR structure, defined in dos.h , stores values returned by the MS-DOS system call 59H (available under MS-DOS versions 3.0 and later).
exception	The exception structure, defined in math.h , stores error information for math routines and is used by the matherr routine.
FILE	The FILE structure, defined in stdio.h , is the structure used in all stream input and output operations. The fields of the FILE structure store information about the current state of the stream.
jmp_buf	The jmp_buf type, declared in setjmp.h , is an array type rather than a structure type. It defines the buffer used by the setjmp and longjmp routines to save and restore the program environment.
REGS	The REGS union, defined in dos.h , stores byte and word register values to be passed to and returned from calls to the MS-DOS interface functions.
SREGS	The SREGS structure, defined in dos.h , stores the values of the ES , CS , SS , and DS registers. This structure is used by the MS-DOS interface functions that require segment register values (int86x , intdosx , and segread).

stat	The stat structure, defined in sys\stat.h , contains file-status information returned by the stat and fstat routines.
timeb	The timeb structure, defined in sys\timeb.h , is used by the ftime routine to store the current system time in a broken-down format.
tm	The tm structure, defined in time.h , is used by the asctime , gmtime , and localtime functions to store and retrieve time information.
utimbuf	The utimbuf structure, defined in sys\utime.h , stores file access and modification times used by the utime function to change file-modification dates.

()

()

()

Chapter 4

Run-Time Routines by Category

4.1	Introduction	41
4.2	Buffer Manipulation	41
4.3	Character Classification and Conversion	42
4.4	Data Conversion	44
4.5	Directory Control	44
4.6	File Handling	45
4.7	Input and Output	46
4.7.1	Stream Routines	47
4.7.1.1	Opening a Stream	49
4.7.1.2	Predefined Stream Pointers: stdin, stdout, stderr, stdaux, stdprn	50
4.7.1.3	Controlling Stream Buffering	51
4.7.1.4	Closing Streams	52
4.7.1.5	Reading and Writing Data	52
4.7.1.6	Detecting Errors	53
4.7.2	Low-Level Routines	53
4.7.2.1	Opening a File	54
4.7.2.2	Predefined Handles	54
4.7.2.3	Reading and Writing Data	56
4.7.2.4	Closing Files	56
4.7.3	Console and Port I/O Routines	56
4.8	Math	58
4.9	Memory Allocation	60
4.10	MS-DOS Interface	63

4.11	Process Control	64
4.12	Searching and Sorting	67
4.13	String Manipulation	68
4.14	Time	70
4.15	Variable-Length Argument Lists	71
4.16	Miscellaneous	71

4.1 Introduction

This chapter describes the major categories of routines included in the C run-time libraries. The discussions of these categories are intended to give a brief overview of the capabilities of the run-time library. For a complete description of the syntax and use of each routine, see Part 2, “Reference,” of this manual.

4.2 Buffer Manipulation

Routine	Use
memccpy	Copies characters from one buffer to another, until a given character or a given number of characters has been copied
memchr	Returns a pointer to the first occurrence, within a specified number of characters, of a given character in the buffer
memcmp	Compares a specified number of characters from two buffers
memicmp	Compares a specified number of characters from two buffers without regard to the case of the letters (uppercase and lowercase treated as equivalent)
memcpy	Copies a specified number of characters from one buffer to another
memset	Uses a given character to initialize a specified number of bytes in the buffer
moveData	Copies a specified number of characters from one buffer to another, even when buffers are in different segments

The buffer-manipulation routines are useful for working with areas of memory on a character-by-character basis. Buffers are arrays of characters (bytes). However, unlike strings, they are not usually terminated with a null character ('\0'). Therefore, the buffer-manipulation routines always take a length or count argument.

Function declarations for the buffer-manipulation routines are given in the include files **memory.h** and **string.h**.

4.3 Character Classification and Conversion

Routine	Use
isalnum	Tests for alphanumeric character
isalpha	Tests for alphabetic character
isascii	Tests for ASCII character
iscntrl	Tests for control character
isdigit	Tests for decimal digit
isgraph	Tests for printable character except space
islower	Tests for lowercase character
isprint	Tests for printable character
ispunct	Tests for punctuation character
isspace	Tests for white-space character
isupper	Tests for uppercase character
isxdigit	Tests for hexadecimal digit
toascii	Converts character to ASCII code
tolower	Tests character and converts to lowercase if uppercase
toupper	Tests character and converts to uppercase if lowercase
_tolower	Converts character to lowercase (unconditional)
_toupper	Converts character to uppercase (unconditional)

The character-classification and conversion routines let you test individual characters in a variety of ways, and convert between uppercase and lowercase characters. The classification routines identify a character by finding it in a table of classification codes; using these routines to classify a character is generally faster than writing a test expression such as the following:

```
if ((c >= '0') || c <= '0x7f')
```

The **tolower** and **toupper** routines are implemented both as functions and as macros; the remainder of the routines in this category are implemented only as macros. All of the macros are defined in **ctype.h**, and this file must be included or the macros will be undefined.

The **toupper** and **tolower** macros evaluate their argument twice and therefore cause arguments with side effects to give incorrect results. For this reason, you may want to use the function versions of these routines instead.

The macro versions of **tolower** and **toupper** are used by default when you include **ctype.h**. To use the function versions instead, you must give **#undef** preprocessor directives for **tolower** and **toupper** *after* the **#include** directive for **ctype.h** but *before* you call the routines. This procedure removes the macro definitions and causes occurrences of **tolower** and **toupper** to be treated as function calls to the **tolower** and **toupper** library functions.

If you want to use the function versions of **toupper** and **tolower** and you do not use any of the other character-classification macros in your program, you can simply omit the **ctype.h** include file. In this case no macro definitions are present for **tolower** and **toupper**, so the function versions will be used.

Function declarations for the **tolower** and **toupper** functions are given in the include file **stdlib.h** instead of **ctype.h** to avoid conflict with the macro definitions. When you want to use **tolower** and **toupper** as functions and include the declarations from **stdlib.h**, you must follow this sequence:

1. Include **ctype.h** if required for other macro definitions.
2. If **ctype.h** was included, give **#undef** directives for **tolower** and **toupper**.
3. Include **stdlib.h**.

The declarations of **tolower** and **toupper** in **stdlib.h** are enclosed in an **#ifndef** block and are processed only if the corresponding identifier (**toupper** or **tolower**) is not defined.

4.4 Data Conversion

Routine	Use
atof	Converts string to float
atoi	Converts string to int
atol	Converts string to long
ecvt	Converts double to string
fcvt	Converts double to string
gcvt	Converts double to string
itoa	Converts int to string
ltoa	Converts long to string
strtod	Converts string to double
strtol	Converts string to a long decimal integer that is equal to a number with the specified radix
ultoa	Converts unsigned long to string

The data-conversion routines convert numbers to strings of ASCII characters and vice versa. These routines are implemented as functions, and all are declared in the include file **stdlib.h**. The **atof** function, which converts a string to a floating-point value, is also declared in **math.h**.

4.5 Directory Control

Routine	Use
chdir	Changes current working directory
getcwd	Gets current working directory
mkdir	Makes a new directory
rmdir	Removes a directory

The directory-control routines let you access, modify, and obtain information about the directory structure from within your program. You can get the current working directory, change directories, and add or remove directories.

The directory routines are functions and are declared in the include file **direct.h**.

4.6 File Handling

Routine	Use
access	Checks file-permission setting
chmod	Changes file-permission setting
chsize	Changes file size
filelength	Checks file length
fstat	Gets file-status information on handle
isatty	Checks for character device
locking	Locks areas of file (available with MS-DOS versions 3.0 and later)
mktemp	Creates unique file name
remove	Deletes file
rename	Renames file
setmode	Sets file-translation mode
stat	Gets file-status information on named file
umask	Sets default-permission mask
unlink	Deletes file

The file-handling routines work on a file designated by a path name or file handle. They modify or give information about the designated file. All of these routines except **fstat** and **stat** are declared in the include file **io.h**. The **fstat** and **stat** functions are declared in **sys\stat.h**. The **remove** and **rename** functions are also declared in **stdio.h**.

The **access**, **chmod**, **remove**, **rename**, **stat**, and **unlink** routines operate on files specified by a path name or file name.

The **chsize**, **filelength**, **isatty**, **locking**, **setmode**, and **fstat** routines work with files designated by a file handle. The **locking** routine works only under MS-DOS versions 3.0 and later; it locks a region of a file against access by other users.

The **mktemp** and **umask** routines have slightly different functions than the above routines. The **mktemp** routine creates a unique file name. Programs can use **mktemp** to create unique file names that do not conflict with the names of existing files. The **umask** routine sets the default permission mask for any new files created in a program. The mask may override the permission setting given in the **open** or **creat** call for the new file.

4.7 Input and Output

The input and output routines of the standard C library allow you to read and write data to and from files and devices. In C, there are no predefined file structures; all data are treated as sequences of bytes. The following three types of input and output (I/O) functions are available:

1. Stream I/O
2. Low-level I/O
3. Console and port I/O

The “stream” functions treat a data file or data item as a stream of individual characters. By choosing among the many stream functions available, you can process data in different sizes and formats, from single characters to large data structures.

When a file is opened for I/O using the stream functions, the opened file is associated with a structure of type **FILE** (defined in **stdio.h**) containing basic information about the file. A pointer to the **FILE** structure is returned when the stream is opened. This pointer (also called the stream pointer, or just *stream*) is used in subsequent operations to refer to the file.

The stream functions provide for (optionally) buffered, formatted, or unformatted input and output. When a stream is buffered, data that is read from or written to the stream is collected in an intermediate storage location called a buffer. When writing, the output buffer's contents are written to the appropriate final location when the buffer is full, the stream is closed, or the program terminates normally. The buffer is said to be “flushed” when this occurs. When reading, a block of data is placed in the input buffer and data are read from the buffer; when the input buffer is empty, the next block of data is transferred into the buffer.

Buffering produces efficient I/O because the system can transfer a large block of data in a single operation rather than performing an I/O operation each time a data item is read from or written to a stream. However, if a program terminates abnormally, output buffers may not be flushed, resulting in loss of data.

The console and port I/O routines can be considered an extension of the stream routines. They allow you to read or write to a console (terminal) or an input/output port (such as a printer port). The port I/O routines simply read and write data in bytes. Some additional options are available with console I/O routines. For example, you can detect whether a character has been typed at the console. You can also choose between echoing characters to the screen as they are read, or reading characters without echoing.

The “low-level” input and output routines do not perform buffering and formatting; they may be considered as invoking the operating system’s input and output capabilities directly. These routines let you access files and peripheral devices at a more basic level than the stream functions.

When a file is opened with a low-level routine, a file *handle* is associated with the opened file. This handle is an integer value that is used to refer to the file in subsequent operations.

Warning

Stream routines and low-level routines are generally incompatible, so either stream or low-level functions should be used consistently on a given file. Since stream functions are buffered and low-level functions are not, attempting to access the same file or device by two different methods causes confusion and may result in the loss of data in buffers.

4.7.1 Stream Routines

Routine	Use
clearerr	Clears the error indicator for a stream
fclose	Closes a stream
fcloseall	Closes all open streams

fdopen	Opens a stream using a <i>handle</i>
feof	Tests for end-of-file on a stream
ferror	Tests for error on a stream
fflush	Flushes a stream
fgetc	Reads a character from <i>stream</i> (function version)
fgetchar	Reads a character from stdin (function version)
fgets	Reads a string from <i>stream</i>
fileno	Gets file handle associated with <i>stream</i>
flushall	Flushes all streams
fopen	Opens a stream
fprintf	Writes formatted data to <i>stream</i>
fputc	Writes a character to <i>stream</i> (function version)
fputchar	Writes a character to stdout (function version)
fputs	Writes a string to <i>stream</i>
fread	Reads unformatted data from <i>stream</i>
freopen	Reassigns a FILE pointer
fscanf	Reads formatted data from <i>stream</i>
fseek	Repositions file pointer to given location
ftell	Gets current file-pointer position
fwrite	Writes unformatted data items to <i>stream</i>
getc	Reads a character from <i>stream</i> (macro version)
getchar	Reads a character from stdin (macro version)
gets	Reads a line from stdin
getw	Reads a binary int from <i>stream</i>
printf	Writes formatted data to stdout
putc	Writes a character to <i>stream</i> (macro version)
putchar	Writes a character to stdout (macro version)
puts	Writes a line to <i>stream</i>
putw	Writes a binary int to <i>stream</i>

rewind	Repositions file pointer to beginning of stream
rmtmp	Removes temporary files created by tmpfile
scanf	Reads formatted data from stdin
setbuf	Controls stream buffering
setvbuf	Controls stream buffering and buffer size
sprintf	Writes formatted data to string
sscanf	Reads formatted data from string
tempnam	Generates a temporary file name in given directory
tmpfile	Creates a temporary file
tmpnam	Generates a temporary file name
ungetc	Places a character in the buffer
vfprintf	Writes formatted data to <i>stream</i>
vprintf	Writes formatted data to stdout
vsprintf	Writes formatted data to a string

To use the stream functions you must include the file **stdio.h** in your program. This file defines constants, types, and structures used in the stream functions, and contains function declarations and macro definitions for the stream routines.

Some of the constants defined in **stdio.h** may be useful in your program. The manifest constant **EOF** is defined to be the value returned at end-of-file. **NULL** is the null pointer. **FILE** is the structure that maintains information about a stream. **BUFSIZ** defines the default size of stream buffers, in bytes.

4.7.1.1 Opening a Stream

A stream must be opened using the **fdopen**, **fopen**, or **freopen** function before input and output can be performed on that stream. When opening a stream, the named stream can be opened for reading, writing, or both, and can be opened either in text or in binary mode.

The **fdopen**, **fopen**, and **freopen** functions return a **FILE** pointer, which is used to refer to the stream. When you call one of these functions, assign

the return value to a **FILE** pointer variable and use that variable to refer to the opened stream. For example, if your program contains the line

```
infile = fopen ("test.dat", "r");
```

you can use the **FILE** pointer variable `infile` to refer to the stream.

4.7.1.2 Predefined Stream Pointers: `stdin`, `stdout`, `stderr`, `stdaux`, `stdprn`

When a program begins execution, five streams are automatically opened. These streams are the standard input, standard output, standard error, standard auxiliary, and standard print. By default, the standard input, standard output, and standard error refer to the user's console. This means that whenever a program expects input from the "standard input," it receives that input from the console. Similarly, a program that writes to the "standard output" prints its data to the console. Error messages generated by the library routines are sent to the "standard error," meaning that error messages appear on the user's console.

The assignment of the "standard auxiliary" and "standard print" streams depends on the machine configuration; these streams usually refer to an auxiliary port and a printer, respectively, but they might not be set up on a particular system. Be sure to check your machine configuration before using these streams.

When you use the stream functions, you can refer to the standard input, standard output, standard error, standard auxiliary, and standard print by using the following predefined **FILE** pointers:

Stream	Device
<code>stdin</code>	Standard input
<code>stdout</code>	Standard output
<code>stderr</code>	Standard error
<code>stdaux</code>	Standard auxiliary
<code>stdprn</code>	Standard print

You can use these pointers in any function that requires a stream pointer as an argument. Some functions, such as `getchar` and `putchar`, are designed

to use **stdin** or **stdout** automatically. The pointers **stdin**, **stdout**, **stderr**, **stdaux**, and **stdprn** are constants, not variables; do not try to assign them a new stream pointer value.

You can use the MS-DOS redirection symbols (<, >, or >>) or the pipe symbol (!) to redefine the standard input and standard output for a particular program. (See your operating-system manual for a complete discussion of redirection and pipes.) For example, if you execute a program and redirect its output to a file named *results*, the program writes to the *results* file each time the standard output is specified in a write operation. Note that you don't change the program when you redirect the output. You simply change the file associated with **stdout** for a single execution of the program.

You can redefine **stdin**, **stdout**, **stderr**, **stdaux**, or **stdprn** so that it refers to a disk file or to a device. The **freopen** routine is used for this purpose. See the **freopen** reference page in Part 2 of this manual for a description of this option.

Important

At the MS-DOS command level, **stderr** (standard error) cannot be redirected.

4.7.1.3 Controlling Stream Buffering

Files opened using the stream functions are buffered by default, except for the preopened streams **stdin**, **stdout**, **stderr**, **stdaux**, and **stdprn**. The **stderr** and **stdaux** streams are unbuffered by default, unless they are being used in one of the **printf** or **scanf** family of functions, in which case they are assigned a temporary buffer. These two streams can also be buffered with **setbuf** or **setvbuf**. The **stdin**, **stdout**, and **stdprn** streams are buffered; this buffer is flushed whenever it is full, or whenever the function causing I/O terminates.

By using the **setbuf** or **setvbuf** functions, you can cause a stream to be unbuffered, or you can associate a buffer with an unbuffered stream. Buffers allocated by the system are not accessible to the user, but buffers allocated with **setbuf** or **setvbuf** are named by the user and can be manipulated as if they were variables. Buffers can be any size: if you use **setbuf**, this size is

set by the manifest constant **BUFSIZ** in **stdio.h**; if you use **setvbuf**, you can set the size of the buffer yourself. (See **setbuf** and **setvbuf** in the reference section of this manual.)

Buffers are automatically flushed when they are full, when the associated file is closed, or when a program terminates normally. You can flush buffers at other times by using the **fflush** and **flushall** routines. The **fflush** routine flushes a single specified stream, while **flushall** flushes all streams that are open and buffered.

4.7.1.4 Closing Streams

The **fclose** and **fcloseall** functions close a stream or streams. The **fclose** routine closes a single specified stream; **fcloseall** closes all open streams except **stdin**, **stdout**, **stderr**, **stdaux**, and **stdprn**. If your program does not explicitly close a stream, the stream is automatically closed when the program terminates. However, it is good practice to close a stream when finished with it, as the number of streams that can be open at a given time is limited.

4.7.1.5 Reading and Writing Data

The stream functions allow you to transfer data in a variety of ways. You can read and write binary data (a sequence of bytes), or specify reading and writing by characters, lines, or more complicated formats. The stream functions for reading and writing data are summarized at the beginning of this section; for a full description of each function, see Part 2, "Reference," of this manual.

Reading and writing operations on streams always begin at the current position of the stream, known as the "file pointer" for the stream. The file pointer is changed to reflect the new position after a read or write operation takes place. For example, if you read a single character from a stream, the file pointer is increased by 1 byte so that the next operation begins with the first unread character. If a stream is opened for appending, the file pointer is automatically positioned at the end of the file before each write operation.

The **feof** macro detects an end-of-file condition on a stream. Once the end-of-file indicator is set, it remains set until the file is closed, or until **clearerr** or **rewind** is called.

You can position the file pointer anywhere in a file by using the **fseek** function. The next operation occurs at the position you specified. The **rewind** function positions the file pointer at the beginning of the file. Use the **ftell** function to determine the current position of the file pointer.

Streams associated with a device (such as a console) do not have file pointers. Data coming from or going to a console cannot be accessed randomly. Routines that set or get the file pointer position (such as **fseek**, **ftell**, or **rewind**) will have undefined results if used on a stream associated with a device.

4.7.1.6 Detecting Errors

When an error occurs in a stream operation, an error indicator for the stream is set. You can use the **perror** macro to test the error indicator and determine whether an error has occurred. Once an error has occurred, the error indicator for the stream remains set until the stream is closed, or until you explicitly clear the error indicator by calling **clearerr** or **rewind**.

4.7.2 Low-Level Routines

Routine	Use
close	Closes a file
creat	Creates a file
dup	Creates a second <i>handle</i> for a file
dup2	Reassigns a file <i>handle</i>
eof	Tests for end-of-file
lseek	Repositions file pointer to a given location
open	Opens a file
read	Reads data from a file
sopen	Opens a file for file sharing
tell	Gets current file pointer position
write	Writes data to a file

Low-level input and output calls do not buffer or format data. Files opened by low-level calls are referenced by a file handle, an integer value used by the operating system to refer to the file. The **open** function is used to open files; on MS-DOS versions 3.0 and later, **sopen** may be used to open a file with file-sharing attributes.

Low-level functions, unlike the stream functions, do not require the include file **stdio.h**. However, some common constants are defined in **stdio.h**; for example, the end-of-file indicator, **EOF**, may be useful. If your program requires these constants, you must include **stdio.h**.

Declarations for the low-level functions are given in the include file **io.h**.

4.7.2.1 Opening a File

A file must be opened with the **open**, **sopen**, or **creat** function before input and output with the low-level functions can be performed on that file. The file can be opened for reading, writing, or both, and opened in either text or binary mode. The include file **fcntl.h** must be included when opening a file, as it contains definitions for flags used in **open**. In some cases the files **sys\types.h** and **sys\stat.h** must also be included; for more information see the reference page for **open** in Part 2 of this manual.

These functions return a file *handle*, to be used to refer to the file in later operations. When you call one of these functions, assign the return value to an integer variable and use that variable to refer to the opened file.

4.7.2.2 Predefined Handles

When a program begins execution, five file handles, corresponding to the standard input, standard output, standard error, standard auxiliary, and standard print, are already assigned. By using the following predefined handles, a program can call low-level functions to access the standard input, standard output, standard error, standard auxiliary, and standard print streams (described with the stream functions in Section 4.7.1.2).

Stream	Handle
stdin	0
stdout	1
stderr	2
stdaux	3
stdprn	4

You can use these file handles in your program without previously opening the associated files. They are automatically opened when the program begins, as shown by the output from the following short program, which uses the **fileno** function to print the file handle values assigned to the standard input, standard output, standard error, standard auxiliary, and standard print streams:

```
#include <stdio.h>

main( )
{
    printf("stdin: %d\n", fileno(stdin));
    printf("stdout: %d\n", fileno(stdout));
    printf("stderr: %d\n", fileno(stderr));
    printf("stdaux: %d\n", fileno(stdaux));
    printf("stdprn: %d\n", fileno(stdprn));
}
```

Output:

```
stdin: 0
stdout: 1
stderr: 2
stdaux: 3
stdprn: 4
```

As with the stream functions, you can use redirection and pipe symbols when you execute your program to redirect the standard input and standard output. The **dup** and **dup2** functions allow you to assign multiple handles for the same file; these functions are typically used to associate the predefined file handles with different files.

Important

At the MS-DOS command level, **stderr** (standard error) cannot be redirected.

4.7.2.3 Reading and Writing Data

Two basic functions, **read** and **write**, perform input and output. As with the stream functions, reading and writing operations always begin at the current position in the file. The current position is updated each time a read or write operation occurs.

The **eof** routine can be used to test for an end-of-file condition. Low-level I/O routines set the **errno** variable when an error occurs. This means that you can use the **perror** function to print information about I/O errors, or the **strerror** function to store this error information in a string.

You can position the file pointer anywhere in a file by using the **lseek** function; the next operation occurs at the position you specified. Use the **tell** function to determine the current position of the file pointer.

Devices (such as the console) do not have file pointers. The **lseek** and **tell** routines have undefined results if used on a handle associated with a device.

4.7.2.4 Closing Files

The **close** function closes an open file. Open files are automatically closed when a program terminates. However, it is a good practice to close a file when finished with it, as the number of files that can be open at a given time is limited.

4.7.3 Console and Port I/O Routines

Routine	Use
cgets	Reads a string from the console
cprintf	Writes formatted data to the console

cputs	Writes a string to the console
cscanf	Reads formatted data from the console
getch	Reads a character from the console
getche	Reads a character from the console and echoes it
inp	Reads specified I/O port
kbhit	Checks for a keystroke at the console
outp	Writes to specified I/O port
putch	Writes a character to the console
ungetch	“Ungets” the last character read from the console so that it becomes the next character read

The console and port I/O routines are implemented as functions and are declared in the include file **conio.h**. These functions perform reading and writing operations on your console or on the specified port. The **cgets**, **cscanf**, **getch**, **getche**, and **kbhit** routines take input from the console, while **cprintf**, **cputs**, **putch**, and **ungetch** write to the console. Redirecting the standard input or standard output from the command line causes the input or output of these functions to be redirected.

The console or port does not have to be opened or closed before I/O is performed, so there are no open or close routines in this category. The port I/O routines (**inp** and **outp**) read or write 1 byte at a time from the specified port. The console I/O routines allow reading and writing of strings (**cgets** and **cputs**), formatted data (**cscanf** and **cprintf**), and characters. Several options are available when reading and writing characters.

The **putch** routine writes a character to the console. The **getch** and **getche** routines read a character from the console; **getche** echoes the character back to the console, while **getch** does not. The **ungetch** routine “ungets” the last character read; the next read operation on the console begins with the “ungotten” character.

The **kbhit** routine determines whether a key has been struck at the console. This routine allows you to test for keyboard input before you attempt to read from the console.

Notes

The console I/O routines use the corresponding low-numbered MS-DOS system calls to read and write characters. See your *Microsoft MS-DOS Programmer's Reference Manual* for details on the system calls.

These console routines are not compatible with stream or low-level library routines, and should not be used with them.

4.8 Math

Routine	Use
acos(x)	Calculates arc cosine of x
asin(x)	Calculates arc sine of x
atan(x)	Calculates arc tangent of x
atan2(y,x)	Calculates arc tangent of y/x
bessel*	Calculates Bessel functions
cabs(z)	Finds absolute value of complex number z
ceil(x)	Finds integer ceiling of x
_clear87()†	Gets and clears floating-point status word
_control87(new,mask)†	Gets old floating-point control word, and sets new control-word value
cos(x)	Calculates cosine of x
cosh(x)	Calculates hyperbolic cosine of x
dieetombsbin(&x,&y)	Converts IEEE double-precision number (x) to Microsoft binary format (y)
dmsbtointeee(&x,&y)	Converts Microsoft binary double-precision number (x) to IEEE format (y)
exp(x)	Calculates exponential function of x
fabs(x)	Finds absolute value of x

fieetombsbin(&x,&y)	Converts IEEE single-precision number (x) to Microsoft binary format (y)
floor(x)	Finds largest integer less than or equal to x
fmod(x,y)	Finds floating-point remainder of x/y
fmsbintoieee(&x,&y)	Converts Microsoft binary single-precision number (x) to IEEE format (y)
_fpreset()	Reinitializes the floating-point math package
frexp($x,&n$)	Shows x as product of mantissa (the value returned by frexp) and 2^n
hypot(x,y)	Calculates hypotenuse of right triangle with sides x and y
ldexp(x,exp)	Calculates x times 2^{exp}
log(x)	Calculates natural logarithm of x
log10(x)	Calculates base 10 logarithm of x
matherr(x)	Handles math errors
modf($x,&n$)	Breaks down x into integer (the value returned by modf) and fractional (n) parts
pow(x,y)	Calculates x^y
sin(x)	Calculates sine of x
sinh(x)	Calculates hyperbolic sine of x
sqr(x)	Finds square root of x
_status87()†	Gets the floating-point status word
tan(x)	Calculates tangent of x
tanh(x)	Calculates hyperbolic tangent of x

* The **bessel** routine does not correspond to a single function, but to six functions named **j0**, **j1**, **jn**, **y0**, **y1**, and **yn**.

† Not available with the **/FPa** compiler option

The math routines allow you to perform common mathematical calculations. All math routines work with floating-point values, and therefore require floating-point support (see Section 2.10, “Floating-Point Support,” in Chapter 2, “Using C Library Routines”). Function declarations for the

math routines are given in the include file **math.h**, with the exception of **_clear87**, **_control87**, **_fpreset**, and **_status87**, whose definitions are given in the **float.h** include file.

The **matherr** routine is invoked by the math functions when errors occur. This routine is defined in the library, but can be redefined by the user if different error-handling procedures are desired. The user-defined **matherr** function, if given, must conform to the specifications given on the **matherr** reference page in Part 2 of this manual.

You are not required to supply a definition for **matherr**. If no definition is present, the default error returns for each routine are used. See the reference page for each routine in Part 2 of this manual for a description of that routine's error returns.

4.9 Memory Allocation

Routine	Use
alloca	Allocates a block of memory from the program's stack
alloc	Allocates storage for array
_expand	Reallocates block of memory without moving its location
_ffree	Frees a block allocated by _fmalloc
_fmalloc	Allocates a block of memory outside the default data segment, returns a far pointer
free	Frees a block allocated with calloc , malloc , or realloc
_freect	Returns approximate number of items of given size that could be allocated
_fmsize	Returns size of memory block pointed to by far pointer
halloc	Allocates storage for huge array
hfree	Frees a block allocated by halloc

malloc	Allocates a block
_memavl	Returns approximate number of bytes available in memory for allocation
_msize	Returns size of block allocated by calloc , malloc , or realloc
_nfree	Frees a block allocated by _nmalloc
_nmalloc	Allocates a block of memory in default data segment, returns a near pointer
_nmsize	Returns size of memory block pointed to by near pointer
realloc	Reallocates a block
sbrk	Resets break value
stackavail	Returns size of stack space available for allocation with alloca

The memory-allocation routines allow you to allocate, free, and reallocate blocks of memory. They are declared in the include file **malloc.h**.

The **calloc** and **malloc** routines allocate memory blocks. The **malloc** routine allocates a given number of bytes, while **calloc** allocates and initializes to 0 an array with elements of a given size. The routines **_fmalloc** and **_nmalloc** are similar to **malloc**, except that **_fmalloc** and **_nmalloc** allow you to allocate a block of bytes while overcoming the addressing limitations of the current memory model. The **malloc** routine performs essentially the same function as **calloc**, with the difference that **malloc** allocates space for **huge** arrays (those exceeding 64K in size). Arrays allocated with **malloc** must satisfy the requirements for huge arrays discussed in Section 8.2.5 of the *Microsoft C Compiler User's Guide*, "Creating Huge-Model Programs."

The **realloc** and **_expand** routines change the size of an allocated block. The **_expand** function always attempts to change the size of an allocated block without moving its heap location; it expands the size of the block to the size requested, or as much as the current location will allow, whichever is smaller. In contrast, **realloc** changes the location in the heap if there is not enough room.

The **malloc** routine returns a **huge** pointer to a **char**, **_fmalloc** returns a **far** pointer to a **char**, and **_nmalloc** returns a **near** pointer to a **char**; all the rest of the allocation routines return a **char** pointer. The space to

which these routines point satisfies the alignment requirements of any type of object. When allocating items of types other than **char**, use a type cast on the return value.

The **free** routine (for **calloc**, **malloc**, and **realloc**), the **_ffree** routine (for **_fmalloc**), the **_nfree** routine (for **_nmalloc**), and the **hfree** routine (for **halloc**) all deallocate memory that was previously allocated, making it available for subsequent allocation requests.

The **_freetct** and **_memavl** routines tell you how much memory is available for dynamic memory allocation in the default data segment; **_freetct** returns the approximate number of items of a given size that can be allocated, while **_memavl** returns the total number of bytes available for allocation requests.

The **_msize** function returns the size of a memory block allocated by a call to **calloc**, **_expand**, **malloc**, or **realloc**. The **_fmsize** and **_nmsize** functions return the size of a memory block allocated by a call to **_fmalloc** or **_nmalloc**, respectively.

The **sbrk** routine is a lower-level memory-allocation routine. It increases the program's break value, allowing the program to take advantage of available unallocated memory.

Warning

In general, a program that uses the **sbrk** routine should not use the other memory-allocation routines, although their use is not prohibited. In particular, using **sbrk** to decrease the break value may cause unpredictable results from calls to the other subsequent memory-allocation routines.

The preceding routines all allocate memory dynamically from the heap. Microsoft C also provides two memory functions, **alloca** and **stackavail**, for allocating space from the stack and determining the amount of available stack space. The **alloca** routine allocates the requested number of bytes from the stack, which are freed when control returns from the function calling **alloca**. The **stackavail** routine lets your program know how much memory (in bytes) is available on the stack.

4.10 MS-DOS Interface

Routine	Use
bdos	Invokes MS-DOS system call; uses only DX and AL registers
dosexterr	Obtains register values from MS-DOS system call 59H
FP_OFF	Returns offset portion of a far pointer
FP_SEG	Returns segment portion of a far pointer
int86	Invokes MS-DOS interrupts
int86x	Invokes MS-DOS interrupts
intdos	Invokes MS-DOS system call; uses registers other than DX and AL
intdosx	Invokes MS-DOS system call; uses registers other than DX and AL
segread	Returns current values of segment registers

These routines provide access to MS-DOS system calls and interrupts. See your *Microsoft MS-DOS Programmer's Reference Manual* for information on system calls and interrupts.

The **FP_OFF** and **FP_SEG** routines are provided to allow the user easy access to the segment and offset portions of a **far** pointer value. **FP_OFF** and **FP_SEG** are implemented as macros and defined in **dos.h**. The remaining routines are implemented as functions and declared in **dos.h**.

The **dosexterr** function obtains and stores the register values returned by MS-DOS system call 59H (extended error handling). This function is provided for use with MS-DOS versions 3.0 and later.

The **bdos** routine is useful for invoking MS-DOS calls that use either or both of the **DX (DH/DL)** and **AL** registers for arguments. However, **bdos** should not be used to invoke system calls that return an error code in **AX** if the carry flag is set; the program cannot detect whether the carry flag is set, making it impossible to determine whether the value in **AX** is a legitimate value or an error value. In this case, the **intdos** routine should be used instead, since it allows the program to detect whether the carry flag is set. The **intdos** routine can also be used to invoke MS-DOS calls that use registers other than **DX** and **AL**.

The **intdosx** routine is similar to the **intdos** routine, but is used when **ES** is required by the system call, when **DS** must contain a value other than the default data segment (for instance, when a **far** pointer is used), or when making the system call in a large-model program. When calling **intdosx**, give an argument that specifies the segment values to be used in the call.

The **int86** routine can be used to invoke MS-DOS interrupts. The **int86x** routine is similar, but, like the **intdosx** routine, is designed to work with large-model programs and far items, as described in the preceding paragraph for **intdosx**.

The **segread** routine returns the current values of the segment registers. This routine is typically used with the **intdosx** and **int86x** routines to obtain the correct segment values.

4.11 Process Control

Routine	Use
abort	Aborts a process
execl	Executes child process with argument list
execle	Executes child process with argument list and given environment
execlp	Executes child process using PATH variable and argument list
execlepe	Executes child process using PATH variable, given environment, and argument list
execv	Executes child process with argument array
execve	Executes child process with argument array and given environment
execvp	Executes child process using PATH variable and argument array
execvpe	Executes child process using PATH variable, given environment, and argument array
exit	Terminates process

_exit	Terminates process without flushing buffers
getpid	Gets process ID number
onexit	Executes functions at program termination
signal	Handles an interrupt signal
spawnl	Executes child process with argument list
spawnle	Executes child process with argument list and given environment
spawnlp	Executes child process using PATH variable and argument list
spawnlpe	Executes child process using PATH variable, given environment, and argument list
spawnv	Executes child process with argument array
spawnve	Executes child process with argument array and given environment
spawnvp	Executes child process using PATH variable and argument array
spawnvpe	Executes child process using PATH variable, given environment, and argument array
system	Executes an MS-DOS command

The term "process" refers to a program being executed by the operating system. A process consists of the program's code and data, plus information pertaining to the status of the process, such as the number of open files. Whenever you execute a program at the MS-DOS level, you start a process. In addition, you can start, stop, and manage processes from within a program by using the process-control routines.

The process-control routines allow you to do the following:

1. Identify a process by a unique number (**getpid**)
2. Terminate a process (**abort**, **exit**, and **_exit**)
3. Handle an interrupt signal (**signal**)
4. Start a new process (the **exec** and **spawn** families of routines, plus the **system** routine)

All process-control functions except **signal** are declared in the include file **process.h**. The **signal** function is declared in **signal.h**. The **abort**, **exit**, and **system** functions are also declared in the **stdlib.h** include file.

The **abort** and **_exit** functions perform an immediate exit without flushing stream buffers. The **exit** call performs an exit after flushing stream buffers.

The **system** call executes a given MS-DOS command. The **exec** and **spawn** routines start a new process, called the "child" process. The difference between the **exec** and **spawn** routines is that the **spawn** routines are capable of returning control from the child process to its caller (the "parent" process). Both the parent process and the child process are present in memory (unless **P_OVERLAY** is specified).

In the **exec** routines, the child process overlays the parent process, so returning control to the parent process is impossible (unless an error occurs when attempting to start execution of the child process).

There are eight forms each of the **spawn** and **exec** routines. The differences between the forms are summarized in Table 4.1. The function names are given in the first column. The second column specifies whether the current **PATH** setting is used to locate the file to be executed as the child process.

The third column describes the method for passing arguments to the child process. Passing an argument list means that the arguments to the child process are listed as separate arguments in the **exec** or **spawn** call; passing an argument array means that the arguments are stored in an array, and a pointer to the array is passed to the child process. The argument-list method is typically used when the number of arguments is constant or is known at compile time, while the argument-array method is useful when the number of arguments must be determined at run time.

The last column specifies if the child process inherits the environment settings of its parent or if a table of environment settings can be passed to set up a different environment for the child process.

Table 4.1
Forms of the spawn and exec Routines

Routines	Use of PATH Setting	Argument-Passing Convention	Environment
<code>execl,</code> <code>spawnl</code>	Do not use PATH	Argument list	Inherited from parent
<code>execle,</code> <code>spawnle</code>	Do not use PATH	Argument list	Pointer to environment table for child process passed as last argument
<code>execlp,</code> <code>spawnlpe</code>	Use PATH	Argument list	Inherited from parent
<code>execle,</code> <code>spawnlpe</code>	Use PATH	Argument list	Pointer to environment table for child process passed as last argument
<code>execv,</code> <code>spawnnv</code>	Do not use PATH	Argument array	Inherited from parent
<code>execve,</code> <code>spawnnve</code>	Do not use PATH	Argument array	Pointer to environment table for child process passed as last argument
<code>execvp,</code> <code>spawnvp</code>	Use PATH	Argument array	Inherited from parent
<code>execvpe,</code> <code>spawnvpe</code>	Use PATH	Argument array	Pointer to environment table for child process passed as last argument

4.12 Searching and Sorting

Routine	Use
<code>bsearch</code>	Performs binary search
<code>lfind</code>	Performs linear search for given value

lsearch	Performs linear search for given value, which is added to array if not found
qsort	Performs quick sort

The **bsearch**, **lfind**, **lsearch**, and **qsort** functions provide helpful binary-search, linear-search and quick-sort utilities. They are declared in the include file **search.h**.

4.13 String Manipulation

Routine	Use
strcat	Appends a string
strchr	Finds first occurrence of a given character in string
strcmp	Compares two strings
strcmpi	Compares two strings without regard to case ("i" indicates that this function is "case insensitive")
strcpy	Copies one string to another
strcspn	Finds first occurrence of a character from given character set in string
strdup	Duplicates string
strerror	Saves system error message and optional user-error message in string
stricmp	Compares two strings without regard to case (identical to strcmpi)
strlen	Finds length of string
strlwr	Converts string to lowercase
strncat	Appends <i>n</i> characters of string
strncmp	Compares <i>n</i> characters of two strings
strncpy	Copies <i>n</i> characters of one string to another
strnicmp	Compares <i>n</i> characters of two strings without regard to case ("i" indicates that this function is "case insensitive")

strnset	Sets <i>n</i> characters of string to given character
strupr	Finds first occurrence of character from one string in another
strrchr	Finds last occurrence of given character in string
strrev	Reverses string
strset	Sets all characters of string to given character
strspn	Finds first substring from given character set in string
strstr	Finds first occurrence of given string in another string
strtok	Finds next token in string
strupr	Converts string to uppercase

The string functions are declared in the include file **string.h**. A wide variety of string functions is available in the run-time library. With these functions, you can do the following:

- Perform string comparisons
- Search for strings, individual characters, or characters from a given set
- Copy strings
- Convert strings to a different case
- Set characters of the string to a given character
- Reverse the characters of strings
- Break strings into tokens
- Store error messages in a string

All string functions work on null-terminated character strings. When working with character arrays that do not end with a null character, you can use the buffer-manipulation routines, described earlier in this chapter.

4.14 Time

Routine	Use
asctime	Converts time from structure to character string
ctime	Converts time from long integer to character string
difftime	Computes the difference between two times
ftime	Gets current system time as structure
gmtime	Converts time from integer to structure
localtime	Converts time from integer to structure with local correction
time	Gets current system time as long integer
tzset	Sets external time variables from environment time variable
utime	Sets file-modification time

The time functions allow you to obtain the current time, then convert and store it according to your particular needs. The current time is always taken from the system time. The **time** and **ftime** functions return the current time as the number of seconds elapsed since Greenwich mean time, January 1, 1970. This value can be converted, adjusted, and stored in a variety of ways, using the **asctime**, **ctime**, **gmtime**, and **localtime** functions. The **utime** function sets the modification time for a specified file, using either the current time or a time value stored in a structure.

The **ftime** function requires two include files: **sys\types.h** and **sys\timeb.h**. The **ftime** function is declared in **sys\timeb.h**. The **utime** function also requires two include files: **sys\types.h** and **sys\utime.h**. The **utime** function is declared in **sys\utime.h**. The remainder of the time functions are declared in the include file **time.h**.

When you want to use **ftime** or **localtime** to make adjustments for local time, you must define an environment variable named **TZ**. See Section 3.2 on the global variables **daylight**, **timezone**, and **tzname** for a discussion of the **TZ** variable; **TZ** is also described on the **tzset** reference page in Part 2 of this manual.

4.15 Variable-Length Argument Lists

Routine	Use
va_arg	Retrieves argument from list
va_end	Resets pointer
va_start	Sets pointer to beginning of argument list

The **va_arg**, **va_end**, and **va_start** routines are macros that provide a portable way to access the arguments to a function when the function takes a variable number of arguments. Two versions of the macros are available: the macros defined in the **vararg.h** include file, which are compatible with the UNIX System V definition, and the macros defined in **stdarg.h**, which conform to the proposed ANSI C standard.

For more information on the differences between the two versions and for an explanation of using the macros, see the appropriate reference pages in Part 2 of this manual.

4.16 Miscellaneous

Routine	Use
abs	Finds absolute value of integer value
assert	Tests for logic error
getenv	Gets value of environment variable
labs	Finds absolute value of long integer value
longjmp	Restores a saved stack environment
perror	Prints error message
putenv	Adds or modifies value of environment variable
rand	Gets a pseudorandom number
setjmp	Saves a stack environment
srand	Initializes pseudorandom series
swab	Swaps bytes of data

The “miscellaneous” category covers a number of commonly used routines that do not fit easily into any of the other categories. All routines except **assert**, **longjmp**, and **setjmp** are declared in **stdlib.h**. The **assert** routine is a macro and is defined in **assert.h**. The **setjmp.h** and **longjmp.h** functions are declared in **setjmp.h**.

The **abs** and **labs** functions return the absolute value of an **int** and a **long** value, respectively. These two functions are defined in both the **math.h** and **stdlib.h** include files. (A macro named **abs** is also available in the include file **v2tov3.h**; the macro gives the absolute value for any type.)

The **assert** macro is typically used to test for program logic errors; it prints a message when a given “assertion” fails to hold true. Defining the identifier **NDEBUG** to any value causes occurrences of **assert** to be removed from the source file, thus allowing you to turn off assertion checking without modifying the source file.

The **getenv** and **putenv** routines provide access to the environment table. The global variable **environ** also points to the environment table, but it is recommended that you use the **getenv** and **putenv** routines to access and modify environment settings rather than accessing the environment table directly.

The **perror** routine prints the system error message, along with an optional user-supplied message, for the last system-level call that produced an error. The **perror** routine is declared in the include files **stdlib.h** and **stdio.h**. The error number is obtained from the **errno** variable. The system message is taken from the **sys_errlist** array. The **errno** variable is only guaranteed to be set upon error for those routines that explicitly mention the **errno** variable in the “Return Value” section of the reference pages in Part 2 of this manual.

The **rand** and **srand** functions initialize and generate a pseudorandom sequence of integers.

The **setjmp** and **longjmp** functions save and restore a stack environment. These routines let you execute a nonlocal goto.

The **swab** routine (also declared in **stdlib.h**) swaps bytes of binary data. It is typically used to prepare data for transfer to a machine that uses a different byte order.

Chapter 5

Include Files

5.1	Introduction	75
5.2	assert.h	76
5.3	conio.h	76
5.4	ctype.h	76
5.5	direct.h	77
5.6	dos.h	77
5.7	errno.h	78
5.8	fcntl.h	79
5.9	float.h	79
5.10	io.h	79
5.11	limits.h	80
5.12	malloc.h	80
5.13	math.h	80
5.14	memory.h	81
5.15	process.h	81
5.16	search.h	82
5.17	setjmp.h	82
5.18	share.h	82
5.19	signal.h	82
5.20	stdarg.h	83
5.21	stddef.h	83
5.22	stdio.h	83
5.23	stdlib.h	85
5.24	string.h	85

5.25 sys\locking.h 86
5.26 sys\stat.h 86
5.27 sys\timeb.h 86
5.28 sys\types.h 86
5.29 sys\utime.h 87
5.30 time.h 87
5.31 varargs.h 87
5.32 v2tov3.h 87

5.1 Introduction

The include files provided with the run-time library contain macro and constant definitions, type definitions, and function declarations. Some routines require definitions and declarations from include files to work properly; for other routines, the inclusion of a file is optional. The description of each include file in this chapter explains the contents of each include file and lists the routines that use it.

A number of routines are declared in more than one include file. For example, the buffer-manipulation functions **memccpy**, **memchr**, **memcmp**, **memcpy**, **memicmp**, **memset**, and **movedata** are declared in both **memory.h** and **string.h**. These multiple declarations ensure agreement with the names of XENIX and UNIX include files, as well as the names of include files under the proposed ANSI standard for C. This preserves compatibility with programs written in earlier versions of C, and further increases the portability of the programs you write in Microsoft C.

Two sets of function declarations are provided in each include file. The first set declares both the return type and the argument-type list for the function. This set is included only when you enable argument type checking by defining **LINT_ARGS**, as described in Section 2.5, "Argument Type Checking," of Chapter 2, "Using C Library Routines." The second set of declarations declares only the return type. This set is included when argument type checking is *not* enabled.

The include files were named and organized to meet the following objectives:

- To maintain compatibility with the names of include files on XENIX and UNIX systems, and with the developing ANSI standard for C
- To reflect the logical categories of run-time routines (for example, placing declarations for all memory-allocation functions in one file, **malloc.h**)
- To require the inclusion of the minimum number of files to use a given routine

Occasionally these goals conflict. For example, the **ftime** function uses the structure type **timeb**. The **timeb** structure type is defined in the include file **sys\timeb.h** on XENIX systems; to maintain compatibility, the same include file is used on MS-DOS. To minimize the number of required include files when using **ftime**, the **ftime** function is declared in **sys\timeb.h**, even though most of the other time functions are declared in **time.h**.

5.2 assert.h

The include file **assert.h** defines the **assert** macro. The **assert.h** file must be included when **assert** is used.

The definition of **assert** is enclosed in an **#ifndef** preprocessor block. If the identifier **NDEBUG** has not been defined (through a **#define** directive or on the compiler command line), the **assert** macro is defined to test a given expression (the “assertion”); if the assertion is false, a message is printed and the program is terminated.

If **NDEBUG** is defined, however, **assert** is defined as empty text. This disables all program assertions by removing all occurrences of **assert** from the source file. Therefore, you can suppress program assertions by defining **NDEBUG**.

5.3 conio.h

The **conio.h** include file contains function declarations for all of the console and port I/O routines, as listed below:

cgets	cscanf	inp	putch
cprintf	getch	kbhit	ungetch
cputs	getche	outp	

5.4 ctype.h

The **ctype.h** include file defines macros and constants and declares a global array used in character classification. The macros defined in **ctype.h** are listed below:

isalnum	iscntrl	islower	isspace	toascii	_tolower
isalpha	isdigit	isprint	isupper	tolower	_toupper
isascii	isgraph	ispunct	isxdigit	toupper	

You must include **ctype.h** when using these macros or the macros will be undefined.

The **toupper** and **tolower** macros are defined as conditional operations. These macros evaluate their argument twice, and so produce unexpected results for arguments with side effects. To overcome this problem, you can remove the macro definitions of **toupper** and **tolower** and use the functions by the same names; see Section 4.3, "Character Classification and Conversion," in Chapter 4, "Run-Time Routines by Category," for details. Declarations for the function versions of **tolower** and **toupper** are given in **stdlib.h**.

In addition to macro definitions, the **ctype.h** include file contains the following:

1. A set of manifest constants defined as bit masks. The bit masks correspond to specific classification tests. For example, the constants **_UPPER** and **_LOWER** are defined to test for an uppercase or lowercase letter, respectively.
2. A declaration of a global array, **_ctype**. The **_ctype** array is a table of character-classification codes based on ASCII character codes.

5.5 direct.h

The **direct.h** include file contains function declarations for the four directory control functions (**chdir**, **getcwd**, **mkdir**, and **rmdir**).

5.6 dos.h

The **dos.h** include file contains macro definitions, function declarations, and type definitions for the MS-DOS interface functions.

The **FP_SEG** and **FP_OFF** macros are defined to get or set the segment and offset portions of a **far** pointer. You must include **dos.h** when using these macros or they will be undefined.

The following functions are declared in **dos.h**:

```
bdos  
dosexterr  
int86  
int86x  
intdos  
intdosx  
segread
```

The **dos.h** file also defines the **WORDREGS** and **BYTEREGS** structure types, used to define sets of word registers and byte registers, respectively. These structure types are combined in the **REGS** union type. The **REGS** union serves as a general-purpose register type, holding both register structures at one time. The **SREGS** structure type defines four members to hold the **ES**, **CS**, **SS**, and **DS** segment register values.

The **DOSERROR** structure is defined to hold error values returned by MS-DOS system call 59H (available under MS-DOS versions 3.0 and later).

Note that **WORDREGS**, **BYTEREGS**, **REGS**, **SREGS**, and **DOSERROR** are tags, not **typedef** names. (See the *Microsoft C Compiler Language Reference* for a discussion of type definitions, tags, and **typedef** names.)

5.7 errno.h

The **errno.h** include file defines the values used by system-level calls to set the **errno** variable. The constants defined in **errno.h** are used by the **perror** function to index the corresponding error message in the global variable **sys_errlist**.

The constants defined in **errno.h** are listed with the corresponding error messages in Appendix A, "Error Messages."

5.8 fcntl.h

The include file **fcntl.h** defines flags used in the **open** and **sopen** calls to specify the type of operations for which the file is opened and to control whether the file is interpreted in text or binary mode. This file should always be included when **open** or **sopen** is used.

The function declarations for **open** and **sopen** are not in **fcntl.h**; instead, they are given in the include file **io.h**.

5.9 float.h

The include file **float.h** contains definitions of constants that specify the ranges of floating-point data types; for example, the maximum number of digits for objects of type **double** (**DBL_DIG** = 15), or the minimum exponent for objects of type **float** (**FLT_MIN_EXP** = -38).

The **float.h** file also contains function declarations for the math functions **_clear87**, **_control87**, **_fpreset**, and **_status87**, as well as definitions of constants used by these functions.

In addition, **float.h** defines floating-point-exception subcodes used with **SIGFPE** to trap floating-point errors (see **signal.h** in Part 2, “Reference”).

5.10 io.h

The include file **io.h** contains function declarations for most of the file-handling and low-level-I/O functions, as listed below:

access	dup2	mktemp	tell
chmod	eof	open	umask
chsize	filelength	read	unlink
close	isatty	rename	write
creat	locking	setmode	
dup	lseek	sopen	

The exceptions are **fstat** and **stat**, which are declared in **sys\stat.h**.

5.11 limits.h

The include file **limits.h** contains definitions of constants that specify the ranges of integer and character data types; for example, the maximum value for an object of type **char** (**CHAR_MAX** = 127).

5.12 malloc.h

The include file **malloc.h** contains function declarations for the memory-allocation functions listed below:

alloca	_fmalloc	alloc	_msize	realloc
calloc	_fmsize	hfree	_nfree	sbrk
_expand	free	malloc	_nmalloc	stackavail
_ffree	_freet	_memavl	_nmsize	

5.13 math.h

The include file **math.h** contains function declarations for all floating-point math routines, plus the **atof** routine, as listed below:

abs	bessel*	fabs	ldexp	sin
acos	cabs	floor	log	sinh
asin	ceil	fmod	log10	sqrt
atan	cos	frexp	matherr	tan
atan2	cosh	hypot	modf	tanh
atof	exp	labs	pow	

* The **bessel** routine does not correspond to a single function but to six functions named **j0**, **j1**, **jn**, **y0**, **y1**, and **yn**.

The **math.h** include file also defines two structures, **exception** and **complex**. The **exception** structure is used with the **matherr** function, and the **complex** structure is used to declare the argument to the **cabs** function.

The **HUGE** value and **HUGE_VAL**, its equivalent in the ANSI C standard, which are returned on error from some math routines, are both defined in **math.h**. **HUGE** and **HUGE_VAL** can be implemented either as manifest constants or as global variables with **double** type, and can be used interchangeably. The value of **HUGE** or **HUGE_VAL** must not be changed in a **#define** directive. Throughout Part 2, “Reference,” references to **HUGE** are understood to mean either **HUGE** or **HUGE_VAL**.

The **math.h** file also defines manifest constants passed in the **exception** structure when a math routine generates an error (for example, **DOMAIN**, **SING**, **EDOM**, and **ERANGE**).

5.14 memory.h

The include file **memory.h** contains function declarations for the seven buffer-manipulation routines listed below:

memccpy
memchr
memcmp
memcpy
memicmp
memset
moveData

5.15 process.h

The include file **process.h** declares all process-control functions (listed below) except for the **signal** function, which is declared in **signal.h**:

abort	execvp	spawnlp
execl	execvpe	spawnlpe
execle	exit	spawnv
execlp	_exit	spawnve
execlpe	getpid	spawnvp
execv	spawnl	spawnvpe
execve	spawnle	system

The **process.h** include file also defines flags used in calls to **spawn** functions to control execution of the child process. Whenever you use one of the eight **spawn** functions, you must include **process.h** so the flags are defined.

5.16 search.h

The include file **search.h** declares the functions **bsearch**, **lsearch**, **lfind**, and **qsort**.

5.17 setjmp.h

The include file **setjmp.h** contains function declarations for the **setjmp** and **longjmp** functions. It also defines the machine-dependent buffer, **jmp_buf**, used by the **setjmp** and **longjmp** functions to save and restore the program state.

5.18 share.h

The include file **share.h** defines flags used in the **sopen** function to set the sharing mode of a file. This file should be included whenever **sopen** is used. The function declaration for **sopen** is given in the file **io.h**. Note that the **sopen** function should only be used under MS-DOS version 3.0 and later.

5.19 signal.h

The include file **signal.h** defines the values for signals. Only the **SIGINT** **SIGFPE** (floating-point exceptions) signals are recognized on MS-DOS. The **signal** function is also declared in **signal.h**.

5.20 stdarg.h

The include file **stdarg.h** defines macros that allow you to access arguments in functions with variable-length argument lists, such as **vprintf**. These macros are defined to be machine independent, portable, and compatible with the developing ANSI standard for C. (See also **varargs.h**.)

5.21 stddef.h

The include file **stddef.h** contains definitions of the commonly used variables and types listed below:

Item	Description
NULL	The null pointer (also defined in stdio.h)
errno	A global variable containing an error message number (also defined in errno.h)
ptrdiff_t	Synonym for the type (int) of the difference of two pointers
size_t	Synonym for the type (int) of the value returned by sizeof

5.22 stdio.h

The include file **stdio.h** contains definitions of constants, macros, and types, along with function declarations for stream I/O functions. The stream I/O functions are listed below:

clearerr	fileno *	fseek	putchar *	sprintf
fclose	flushall	ftell	puts	sscanf
fcloseall	fopen	fwrite	putw	tempnam
fdopen	fprintf	getc *	remove	tmpfile
feof *	fputc	getchar *	rename	tmpnam
ferror *	fputchar	gets	rewind	ungetc
fflush	fputs	getw	rmtmp	vfprintf

fgetc	fread	perror	scanf	vprintf
fgetchar	freopen	printf	setbuf	vsprintf
fgets	fscanf	putc*	setvbuf	

* Implemented as a macro

The **stdio.h** file defines a number of constants; some of the more common ones are listed below:

Item	Description
BUFSIZ	Buffers used in stream I/O are required to have a constant size, which is defined by the BUFSIZ constant. This value is used to establish the size of system-allocated buffers, and must also be used when calling setbuf to allocate your own buffers.
_NFILE	The _NFILE constant defines the number of open files allowed at one time. The five files stdin , stdout , stderr , stdaux , and stdprn are always open, so you should include them when calculating the number of files your program opens.
EOF	The EOF value is defined to be the value returned by an I/O routine when the end of the file (or in some cases, an error) is encountered.
NULL	The NULL value is the null-pointer value. It is defined as 0 in small- and medium-model programs and as 0L in large-model programs.

You can use the above constants in your programs, but you should not alter their values.

The **stdio.h** file also defines a number of flags used internally to control stream operations.

The **FILE** structure type is defined in **stdio.h**. Stream routines use a pointer to the **FILE** type to access a given stream. The system uses the information in the **FILE** structure to maintain the stream.

The **FILE** structures are stored as an array called **_iob**, with one entry per file. Therefore, each element of **_iob** is a **FILE** structure corresponding to a stream. When a stream is opened, it is assigned the address of an entry in the **_iob** array (a **FILE** pointer). Thereafter, the pointer is used for references to the stream.

5.23 stdlib.h

The **stdlib.h** include file contains function declarations for the following functions:

abort	ecvt	itoa	putenv	swab
abs	exit	labs	rand	system
atof	fcvt	ltoa	realloc	tolower
atoi	free	malloc	srand	toupper
atol	gcvt	onexit	strtod	ultoa
calloc	getenv	perror	strtol	

The **tolower** and **toupper** routines are functions in the run-time library, but they are also implemented as macros in the include file **ctype.h**. The declarations for **tolower** and **toupper** are enclosed in an `#ifndef` block; they take effect only if the corresponding macro definitions in **ctype.h** have been suppressed by removing the definitions of **tolower** and **toupper**. For instructions on using these routines as macros or as functions, see Section 4.3, “Character Classification and Conversion,” in Chapter 4, “Run-Time Routines by Category.”

The **stdlib.h** file also includes the definition of the type **onexit_t**, as well as declarations of the following global variables:

_doserrno	_fmode	-psp
environ	_osmajor	sys_errlist
errno	_osminor	sys_nerr

5.24 string.h

The **string.h** include file declares the string manipulation functions, as listed below:

memccpy	strcat	strerror	strnicmp	strrstr
memchr	strchr	strcmp	strnset	strtok
memcmp	strcmp	strlen	strpbrk	strupr
memcpy	strcmp	strlwr	strrchr	
memicmp	strcpy	strncat	strrev	
memset	strcspn	strncmp	strset	
movepdata	strdup	strncpy	strspn	

5.25 sys\locking.h

The **locking.h** include file (conventionally stored in a subdirectory named SYS) contains definitions of flags used in calls to **locking**. Whenever you use the **locking** routine, you must include this file so that the locking flags are defined.

The function declaration for **locking** is given in the file **io.h**. Note that the **locking** function should be used only under MS-DOS versions 3.0 and later.

5.26 sys\stat.h

The **stat.h** include file (conventionally stored in a subdirectory named SYS) defines the structure type returned by the **fstat** and **stat** functions and defines flags used to maintain file-status information. It also contains function declarations for the **fstat** and **stat** functions. Whenever you use the **fstat** or **stat** functions, you must include this file so that the appropriate structure type (named **stat**) is defined.

5.27 sys\timeb.h

The include file **timeb.h** (conventionally stored in a subdirectory named SYS) defines the **timeb** structure type and declares the **ftime** function, which uses the **timeb** structure type. Whenever you use the **ftime** function you must include **timeb.h** so that the structure type is defined.

5.28 sys\types.h

The include file **types.h** (conventionally stored in a subdirectory named SYS) defines types used by system-level calls to return file-status and time information. You must include this file whenever the **sys\stat.h**, **sys\utime.h**, or **sys\timeb.h** file is included.

5.29 sys\utime.h

The include file **utime.h** (conventionally stored in a subdirectory named **SYS**) defines the **utimbuf** structure type and declares the **utime** function, which uses the **utimbuf** type. Whenever you use the **utime** function you must include **utime.h** so that the structure type is defined.

5.30 time.h

The **time.h** include file declares the time functions **asctime**, **ctime**, **difftime**, **gmtime**, **localtime**, **time**, and **tzset**. (The **ftime** and **utime** functions are declared in **sys\timeb.h** and **sys\utime.h**, respectively.)

The **time.h** file also defines both the **tm** structure, used by the **asctime**, **gmtime**, and **localtime** functions, and the **time_t** type, used by the **difftime** function.

5.31 varargs.h

The include file **varargs.h** defines macros for accessing arguments in functions with variable-length argument lists, such as **vprintf**. These macros are defined to be machine independent, portable, and compatible with UNIX System V. (See also **stdarg.h**.)

5.32 v2tov3.h

The include file **v2tov3.h** is provided for users who are converting from versions 2.03 and earlier of the Microsoft C Compiler. Some of the routines provided in the Version 2.03 run-time library are supported in a slightly different form under Version 3.0 of the compiler. Including **v2tov3.h** allows those routines to be used in their original form without altering the source code.

The **v2tov3.h** file, as well as other differences between Version 3.0 of the Microsoft C Compiler and other versions, is discussed in detail in Appendix F, "Converting from Previous Versions of the Compiler," in the *Microsoft C Compiler User's Guide*.

The **v2tov3.h** file contains three macro definitions that can be useful. The **abs** macro produces the absolute value of its argument. The **min** and **max** macros calculate the minimum and maximum, respectively, of two numbers. See the **v2tov3.h** include file for details.

Part 2

Reference

()

.....

()

.....

()

.....

■ Summary

```
# include <process.h>
# include <stdlib.h>
```

Required only for function declarations
Use either **process.h** or **stdlib.h**

```
void abort( );
```

■ Description

The **abort** function prints the message

Abnormal program termination

to **stderr**, then terminates the calling process, returning control to the process that initiated the calling process (usually the operating system). The **abort** function does not flush stream buffers.

■ Return Value

An exit status of 3 is returned to the parent process or operating system.

■ See Also

execl, execle, execlp, execlepe, execv, execve, execvp, execvpe, exit, _exit, signal, spawnl, spawnle, spawnlp, spawnlpe, spawnnv, spawnnv, spawnv, spawnvp, spawnvpe

abort

■ Example

```
#include <stdio.h>

main(argc, argv)
int argc;
char *argv[ ];
{
FILE *stream;
if ((stream = fopen(argv[argc-1],"r")) == NULL) {
    fprintf(stderr,
            "%s couldn't open file %s\n", argv[0], argv[argc-1]);
    abort( );
}
/* Note: the program name is stored in argv[0] only in
** MS-DOS versions 3.0 and later; in versions prior to
** 3.0, argv[0] contains the string "C"
*/
}
```

Sample command line:

```
update employ.dat
```

Output:

```
C:\BIN\UPDATE.EXE couldn't open file employ.dat
```

```
Abnormal program termination
```

■ Summary

include <stdlib.h> Required only for function declarations

int abs(*n*);
int *n*; Integer value

■ Description

The **abs** function returns the absolute value of its integer argument *n*.

■ Return Value

The **abs** function returns the absolute value of its argument. There is no error return.

■ See Also

cabs, fabs, labs

■ Example

```
#include <stdlib.h>

int x = -4, y;

y = abs(x);
printf("%d\t%d\n", x, y);
```

Output:

-4 4

access

■ Summary

include <io.h> Required only for function declarations

```
int access(pathname, mode);  
char *pathname; File or directory path name  
int mode; Permission setting
```

■ Description

With files, the **access** function determines whether or not the specified file exists and can be accessed in the given *mode*. The possible values for *mode* and their meanings in the **access** call are as follows:

Value	Meaning
06	Check for read and write permission
04	Check for read permission
02	Check for write permission
00	Check for existence only

Under MS-DOS, all existing files have read access; thus the modes 00 and 04 produce the same result. Similarly, the modes 06 and 02 are equivalent, since write access implies read access on MS-DOS.

With directories, **access** determines only whether or not the specified directory exists; under MS-DOS, all directories have read and write access.

■ Return Value

The **access** function returns the value 0 if the file has the given *mode*. A return value of -1 indicates that the named file does not exist or is not accessible in the given *mode*, and **errno** is set to one of the following values:

Value	Meaning
EACCES	Access denied: the file's permission setting does not allow the specified access.
ENOENT	File or path name not found.

■ See Also**chmod, fstat, open, stat****■ Example**

```
#include <io.h>
#include <fcntl.h>

int fh;
.
.
.

/* check for write permission */
if ((access("data",2)) == -1) {
    perror("data file not writable");
    exit(1);
}
else
    fh = open("data",O_WRONLY);
```

acos

■ Summary

```
# include <math.h>
```

```
double acos(x);
double x;
```

■ Description

The **acos** function returns the arc cosine of x in the range 0 to π . The value of x must be between -1 and 1.

■ Return Value

The **acos** function returns the arc cosine result. If x is less than -1 or greater than 1, **acos** sets **errno** to **EDOM**, prints a **DOMAIN** error message to **stderr**, and returns 0.

Error handling can be modified by using the **matherr** routine.

■ See Also

asin, **atan**, **atan2**, **cos**, **matherr**, **sin**, **tan**

■ Example

In the following example, the program continues prompting for input as long as the value entered is not in the domain -1 to 1:

```
#include <math.h>

int errno;

main( )
{
    float x, y;

    for (errno = EDOM; errno == EDOM; y = acos(x)) {
        printf("Cosine = ");
        scanf("%f",&x);
        errno = 0;
    }
    printf("Arc cosine of %f = %f\n",x,y);
}
```

Sample output:

```
Cosine = 3
acos: DOMAIN error
Cosine = -1.0
Arc cosine of -1.000000 = 3.141593
```

alloca

■ Summary

`# include <malloc.h>` Required only for function declarations

`char *alloca(size);`
`unsigned size;` Bytes to be allocated from stack

■ Description

The **alloca** routine allocates *size* bytes from the program's stack. The allocated space is automatically freed when the function that called **alloca** is exited.

■ Return Value

The **alloca** routine returns a **char** pointer to the allocated space. The storage space pointed to by the return value is guaranteed to be suitably aligned for storage of any type of object. To get a pointer to a type other than **char**, use a type cast on the return value. The return value is **NULL** if the space cannot be allocated.

■ See Also

calloc, **malloc**, **realloc**

Warning

The pointer value returned by **alloca** should never be passed as an argument to **free**. Also, because **alloca** manipulates the stack, it should be used only in simple assignment statements and never in an expression that is an argument to a function.

■ Example

```
#include <malloc.h>  
  
int *intarray;  
  
/* Allocate space on the stack for 10 integers */  
intarray = (int *)alloca(10*sizeof(int));
```

asctime

■ Summary

```
#include <time.h>

char *asctime(time);
struct tm *time;           Pointer to structure defined in time.h
```

■ Description

The **asctime** function converts a time stored as a structure to a character string. The *time* value is usually obtained from a call to **gmtime** or **localtime**, both of which return a pointer to a **tm** structure, defined in **time.h**. (See **gmtime** for a description of the **tm** structure fields).

The string result produced by **asctime** contains exactly 26 characters and has the form of the following example:

```
Mon Jan 02 02:03:55 1980\n\0
```

A 24-hour clock is used. All fields have a constant width. The new-line character ('\n') and the null character ('\0') occupy the last two positions of the string.

■ Return Value

The **asctime** function returns a pointer to the character string result. There is no error return.

■ See Also

ctime, **ftime**, **gmtime**, **localtime**, **time**, **tzset**

Note

The **asctime** and **ctime** functions use a single statically allocated buffer to hold the return string. Each call to one of these routines destroys the result of the previous call.

■ Example

```
#include <time.h>
#include <stdio.h>

struct tm *newtime;
long ltime;
.

.

.

time(&ltime);           /* get time in seconds */
newtime = localtime(&ltime);    /* convert to struct tm */
/* print local time
   ** as string
*/
printf("the current date and time are %s\n",
       asctime(newtime));
```

asin

■ Summary

```
# include <math.h>
```

```
double asin(z);
double z;
```

■ Description

The **asin** function calculates the arc sine of x in the range $-\pi/2$ to $\pi/2$. The value of x must be between -1 and 1 .

■ Return Value

The **asin** function returns the arc sine result. If x is less than -1 or greater than 1 , **asin** sets **errno** to **EDOM**, prints a **DOMAIN** error message to **stderr**, and returns 0 .

Error handling can be modified by using the **matherr** routine.

■ See Also

acos, **atan**, **atan2**, **cos**, **matherr**, **sin**, **tan**

■ Example

```
#include <math.h>

int errno;

main( )
{
    float x, y;

    for (errno = EDOM; errno == EDOM; y = asin(x)) {
        printf("Sine = ");
        scanf("%f", &x);
        errno = 0;
    }
    printf("Arc sine of %f = %f\n", x, y);
}
```

Output:

```
Sine = -1.001
asin: DOMAIN error
Sine = -1
Arc sine of -1.000000 = -1.570796
```

assert

■ Summary

```
# include <assert.h>  
  
void assert(expression);
```

■ Description

The **assert** routine prints a diagnostic message and terminates the calling process if *expression* is false (0). The diagnostic message has the form

Assertion failed: file *filename*, line *linenumber*

where *filename* is the name of the source file and *linenumber* is the line number of the assertion that failed in the source file. No action is taken if *expression* is true (nonzero).

The **assert** routine is typically used to identify program logic errors. The given *expression* should be chosen so that it holds true only if the program is operating as intended. After a program has been debugged, the special “no debug” identifier **NDEBUG** can be used to remove **assert** calls from the program. If **NDEBUG** is defined (by any value) with a /D command-line option or with a #define directive, the C preprocessor removes all **assert** calls from the program source.

■ Return Value

There is no return value.

Note

The **assert** routine is implemented as a macro.

■ Example

```
#include <stdio.h>
#include <assert.h>

analyze_string (string)
char *string;
{
    /* Test string before processing. */

    assert(string != NULL);           /* can't be NULL
                                         ** (there must
                                         ** be a string)
                                         */
    assert(*string != '\0');          /* can't be empty */
    .
    .
    .
}
```

atan – atan2

■ Summary

```
#include <math.h>

double atan(x);           Calculate arc tangent of x
double x;

double atan2(y, x);       Calculate arc tangent of y/x
double x;
double y;
```

■ Description

The **atan** and **atan2** functions calculate the arc tangent of x and y/x , respectively: **atan** returns a value in the range $-\pi/2$ to $\pi/2$; **atan2** returns a value in the range $-\pi$ to π .

■ Return Value

Both **atan** and **atan2** return the arc tangent result. If both arguments of **atan2** are 0, the function sets **errno** to **EDOM**, prints a **DOMAIN** error message to **stderr**, and returns 0.

Error handling can be modified by using the **matherr** routine.

■ See Also

acos, asin, cos, matherr, sin, tan

■ Example

```
#include <math.h>

printf("%.7f\n", atan(1.0));          /* π/4 */
printf("%.7f\n", atan2(-1.0,1.0));    /* -π/4 */
```

Output:

```
0.7853982
-0.7853982
```

■ Summary

```
# include <math.h>
# include <stdlib.h>
```

Use either math.h or stdlib.h

```
double atof(string);
char *string;
```

Convert *string* to double
String to be converted

```
# include <stdlib.h>
```

Required only for function declarations

```
int atoi(string);
long atol(string);
char *string;
```

Convert *string* to int
Convert *string* to long
String to be converted

■ Description

These functions convert a character string to a double-precision floating-point value (**atof**), an integer value (**atoi**), or a long integer value (**atol**). The input *string* is a sequence of characters that can be interpreted as a numerical value of the specified type. The function stops reading the input string at the first character it cannot recognize as part of a number (which may be the null character terminating the string).

The **atof** function expects *string* to have the following form:

`[[whitespace]][[sign]][[digits]][[.digits]][{{d | D | e | E} [[sign]]digits}]`

A *whitespace* consists of space and/or tab characters, which are ignored; *sign* is either “+” or “-”; and *digits* are one or more decimal digits. If no digits appear before the decimal point, at least one must appear after the decimal point. The decimal digits may be followed by an exponent, which consists of an introductory letter (d, D, e, or E) and an optionally signed decimal integer.

The **atoi** and **atol** functions do not recognize decimal points or exponents. The *string* argument for these functions has the form

`[[whitespace]][[sign]]digits`

where *whitespace*, *sign*, and *digits* are exactly as described above for **atof**.

atof – atol

■ Return Value

Each function returns the **double**, **int**, or **long** value produced by interpreting the input characters as a number. The return value is 0 (0L for **atol**) if the input cannot be converted to a value of that type. The return value is undefined in case of overflow.

■ See Also

ecvt, **fcvt**, **gcvt**

■ Example

The following examples show how numbers stored as strings can be converted to numerical values using the **atof**, **atoi**, and **atol** functions:

```
#include <math.h>

extern long atol(\ );
main(\ )
{
    char *s;
    double x;
    int i;
    long l;

    s = " -2309.12E-15";
    x = atof(s);
    printf("%e\t",x);

    s = "7.8912654773d210";
    x = atof(s);
    printf("%e\t",x);

    s = " -9885";
    i = atoi(s);
    printf("%d\t",i);

    s = "98854 dollars";
    l = atol(s);
    printf("%ld\n",l);
}
```

Output:

-2.309120e-012 7.891265e+210 -9885 98854

■ Summary

```
# include <dos.h>
```

<code>int bdos(dosfn, dosdx, dosal);</code>	
<code>int dosfn;</code>	Function number
<code>unsigned int dosdx;</code>	DX register value
<code>unsigned int dosal;</code>	AL register value

■ Description

The **bdos** function invokes the MS-DOS system call specified by *dosfn*, after placing the values specified by *dosdx* and *dosal* in the **DX** and **AL** registers, respectively. The **bdos** function executes an INT 21H instruction to invoke the system call. When the system call returns, **bdos** returns the content of the **AX** register.

The **bdos** function is intended to be used to invoke DOS system calls that either take no arguments or only take arguments in the **DX(DH,DL)** and/or **AL** registers.

■ Return Value

The **bdos** function returns the value of the **AX** register after the system call has completed.

■ See Also

intdos, **intdosx**

Warning

This call should *not* be used to invoke system calls that indicate errors by setting the carry flag. Since C programs do not have access to this flag, the status of the return value cannot be determined. The **intdos** function should be used in these cases.

bdos

■ **Example**

The following example makes MS-DOS function call 9 (display string) to display a prompt. Since the **AL** register value is not needed, 0 is used. This example works correctly only in small- and medium-model programs.

```
#include <dos.h>

char *buffer = "Enter file name:$";
/* AL is not needed, so 0 is used */
bdos(9, (unsigned)buffer, 0);
```

■ Summary

```
# include <math.h>

double j0(x);
double j1(x);
double jn(n, x);
double y0(x);
double y1(x);
double yn(n, x);

double x;           Floating-point value
int n;             Integer order
```

■ Description

The **j0**, **j1**, and **jn** routines return Bessel functions of the first kind of orders–0, 1, and *n*, respectively.

The **y0**, **y1**, and **yn** routines return Bessel functions of the second kind of orders–0, 1, and *n*, respectively. The argument *x* must be positive.

■ Return Value

These functions return the result of a Bessel function of *x*.

For **y0**, **y1**, or **yn**, if *x* is negative, the routine sets **errno** to **EDOM**, prints a **DOMAIN** error message to **stderr**, and returns the value negative **HUGE**.

Error handling can be modified by using the **matherr** routine.

bessel

■ See Also

matherr

■ Example

```
#include <math.h>

double x, y, z;
.
.
.
y = j0(x);
z = yn(3,x);
```

■ Summary

`# include <search.h>` Required only for function declarations

<code>char *bsearch(key, base, num, width, compare);</code>	
<code>char *key;</code>	Search key
<code>char *base;</code>	Pointer to base of search data
<code>unsigned num, width;</code>	Number and width of elements
<code>int (*compare)();</code>	Pointer to compare function

■ Description

The **bsearch** function performs a binary search of a sorted array of *num* elements, each of *width* bytes in size. *Base* is a pointer to the base of the array to be searched, and *key* is the value being sought.

The *compare* argument is a pointer to a user-supplied routine that compares two array elements and returns a value specifying their relationship. The **bsearch** function will call the *compare* routine one or more times during the search, passing pointers to two array elements on each call. The routine must compare the elements, then return one of the following values:

Value	Meaning
Less than 0	<i>element1</i> less than <i>element2</i>
0	<i>element1</i> identical to <i>element2</i>
Greater than 0	<i>element1</i> greater than <i>element2</i>

■ Return Value

The **bsearch** function returns a pointer to the first occurrence of *key* in the array pointed to by *base*. If *key* is not found, the function returns **NULL**.

■ See Also

lfind, **lsearch**, **qsort**

bsearch

■ Example

```
/* The bsearch function performs a binary search on a
** sorted array for a 'key' element and returns a pointer
** to the structure that matches the key, or NULL if
** there is no match.
*/
#include <search.h>
#include <string.h>
#include <stdio.h>

int compare( ); /* must declare as a function */

main (argc, argv)
    int argc;
    char **argv;
{

    char **result;
    char *key = "PATH";

/* The following statement finds the argument that
** starts with "PATH", assuming the arguments have been
** lexically sorted (see the example with the qsort
** reference entry for a way to sort them).
*/
    result = (char **)bsearch((char *)&key, (char *)argv,
                               argc, sizeof(char *), compare);
    if (result)
        printf("%s found\n", *result);
    else
        printf("PATH not found!\n");
}

int compare (arg1, arg2)
    char **arg1, **arg2;

{
    return (strcmp(*arg1, *arg2, strlen(*arg1)));
}
```

■ Summary

```
# include <math.h>
```

```
double cabs(z);
```

```
struct complex z;
```

Contains real and imaginary parts

■ Description

The **cabs** function calculates the absolute value of a complex number. The complex number must be a structure with type **complex**, defined in **math.h** as follows:

```
struct complex {  
    double x,y;  
};
```

A call to **cabs** is equivalent to the following:

```
sqrt(z.x*z.x + z.y*z.y)
```

■ Return Value

The **cabs** function returns the absolute value as described above. On overflow, the function calls the **matherr** routine, returns the value **HUGE**, and sets **errno** to **ERANGE**.

■ See Also

abs, **fabs**, **labs**

■ Example

```
#include <math.h>  
  
struct complex value;  
double d;  
  
value.x = 3.0;  
value.y = 4.0;  
  
d = cabs(value);
```

calloc

■ Summary

```
# include <malloc.h>
```

Required only for function declarations

```
char *calloc(n, size);
```

```
unsigned n;
```

Number of elements

```
unsigned size;
```

Length in bytes of each element

■ Description

The **calloc** function allocates storage space for an array of *n* elements, each of length *size* bytes. Each element is initialized to 0.

■ Return Value

The **calloc** function returns a **char** pointer to the allocated space. The storage space pointed to by the return value is guaranteed to be suitably aligned for storage of any type of object. To get a pointer to a type other than **char**, use a type cast on the return value. The return value is **NULL** if there is insufficient memory available.

■ See Also

free, **malloc**, **realloc**

■ Example

```
#include <malloc.h>

long *lalloc;
.

.

/* Allocate enough space for 40 long integers and
** initialize it to 0.
*/
lalloc = (long *)calloc(40,sizeof(long));
```

■ Summary

```
#include <math.h>

double ceil(x);
double x;           Floating-point value
```

■ Description

The **ceil** function returns a **double** value representing the smallest integer that is greater than or equal to *x*.

■ Return Value

The **ceil** function returns the **double** result. There is no error return.

■ See Also

floor, **fmod**

■ Example

```
#include <math.h>

double y;
.
.
.
y = ceil(1.05);          /* y = 2.0 */
y = ceil(-1.05);         /* y = -1.0 */
```

cgets

■ Summary

include <conio.h> Required only for function declarations

char *cgets(str);
char *str; Storage location for data

■ Description

The **cgets** function reads a string of characters directly from the console and stores the string and its length in the location pointed to by *str*. The *str* must be a pointer to a character array. The first element of the array, *str[0]*, must contain the maximum length (in characters) of the string to be read. The array must have enough elements to hold the string, a terminating null character ('\'0'), and two additional bytes.

The **cgets** function continues to read characters until a carriage-return-line-feed combination (CR-LF) is read, or the specified number of characters have been read. The string is stored starting at *str[2]*. If a CR-LF combination is read, it is replaced with a null character ('\'0') before being stored. The **cgets** function then stores the actual length of the string in the second array element, *str[1]*.

■ Return Value

The **cgets** function returns a pointer to the start of the string, which is at *str[2]*. There is no error return.

■ See Also

getch, **getche**

■ Example

```
#include <conio.h>

char buffer[82];
char *result;
int numread;
.

.

*buffer = 80;      /* maximum number of characters */
/* note that *buffer is equivalent
** to *buffer[0]
*/
/* The following statements input a string from the
** keyboard and find its length:
*/
result = cgets(buffer);
numread = buffer[1];

/* Result points to the string, and numread is its
** length (not counting the carriage return, which has
** been replaced by a null character).
*/

```

chdir

■ Summary

include <direct.h> Required only for function declarations

int chdir(*pathname*);
char **pathname*; Pathname of new working directory

■ Description

The **chdir** function causes the current working directory to be changed to the directory specified by *pathname*; *pathname* must refer to an existing directory.

■ Return Value

The **chdir** function returns a value of 0 if the working directory is successfully changed. A return value of -1 indicates an error; in this case **errno** is set to **ENOENT**, indicating that the specified path name could not be found. No error occurs if *pathname* specifies the current working directory.

■ See Also

mkdir, rmdir, system

■ Example

```
#include <direct.h>

/* The following statement changes the current working
** directory to the root directory:
*/
chdir("/"); /* Note: equivalent to chdir("\\") */
```

■ Summary

```
# include <sys\ types.h>
# include <sys\ stat.h>
# include <io.h>
```

Required only for function declarations

```
int chmod(pathname, pmode);
char *pathname;
int pmode;
```

Path name of existing file
Permission setting for file

■ Description

The **chmod** function changes the permission setting of the file specified by *pathname*. The permission setting controls read and write access to the file. The constant expression *pmode* contains one or both of the manifest constants **S_IWRITE** and **S_IREAD**, defined in **sys\stat.h**. Any other values for *pmode* are ignored. When both constants are given, they are joined with the bitwise OR operator (**|**). The meaning of the *pmode* argument is as follows:

Value	Meaning
S_IWRITE	Writing permitted
S_IREAD	Reading permitted
S_IREAD S_IWRITE	Reading and writing permitted

If write permission is not given, the file is made read only. Under MS-DOS, all files are readable; it is not possible to give write-only permission. Thus the modes **S_IWRITE** and **S_IREAD | S_IWRITE** are equivalent.

■ Return Value

The **chmod** function returns the value 0 if the permission setting is successfully changed. A return value of -1 indicates an error; in this case, **errno** is set to **ENOENT**, indicating that the specified file could not be found.

chmod

■ See Also

access, creat, fstat, open, stat

■ Example

```
#include <sys\types.h>
#include <sys\stat.h>
#include <io.h>

int result;
.
.
.
result = chmod("data",S_IREAD); /* make file read only */
if (result == -1)
    perror("can't change file mode");
```

■ Summary

`# include <io.h>` Required only for function declarations

```
int chsize(handle, size);
int handle;           Handle referring to open file
long size;            New length of file in bytes
```

■ Description

The **chsize** function extends or truncates the file associated with *handle* to the length specified by *size*. The file must be open in a mode that permits writing. Null characters ('\'0') are appended if the file is extended. If the file is truncated, all data from the end of the shortened file to the original length of the file are lost.

■ Return Value

The **chsize** function returns the value 0 if the file size is successfully changed. A return value of -1 indicates an error, and **errno** is set to one of the following values:

Value	Meaning
EACCES	The specified file is read only. Under MS-DOS 3.0 and later, EACCES may indicate a locking violation (the specified file is locked against access).
EBADF	Invalid file handle.
ENOSPC	No space left on device.

■ See Also

close, **creat**, **open**

chsize

■ Example

```
#include <io.h>
#include <fcntl.h>
#include <sys\types.h>
#include <sys\stat.h>

#define MAXSIZE 32768L

int fh, result;
.

.

fh = open ("data", O_RDWR|O_CREAT, S_IREAD|S_IWRITE);

.

.

/* Make sure the file is no longer than 32K before
** closing it.
*/

if (lseek(fh,0L,2) > MAXSIZE)
    result = chsize(fh,MAXSIZE);
```

■ Summary

```
# include <float.h>
```

```
unsigned int _clear87( );           Get and clear floating-point status word
```

■ Description

The **_clear87** function gets and clears the floating-point status word. The floating-point status word is a combination of the 8087/80287 status word and other conditions detected by the 8087/80287 exception handler, such as floating-point stack overflow and underflow.

■ Return Value

The bits in the value returned indicate the floating-point status. See the **float.h** include file for a complete definition of the bits returned by **_clear87**.

Note

Many of the math library functions modify the 8087/80287 status word, with unpredictable results. Return values from **_clear87** and **_status87** become more reliable as fewer floating-point operations are performed between known states of the floating-point status word.

■ See Also

_control87, **_status87**

_clear87

■ Example

```
#include <stdio.h>
#include <float.h>

double a = 1e-40,b;
float x,y;

main ( )
{
    printf("status = %.4x - clear\n",_clear87( ));
    y = a; /* store into y is inexact and underflows */
    printf("status = %.4x - inexact, underflow\n",_clear87( ));
    b = y; /* y is denormal */
    printf("status = %.4x - denormal\n",_clear87( ));
}
```

■ Summary

```
#include <stdio.h>

void clearerr(stream);
FILE *stream;           Pointer to file structure
```

■ Description

The **clearerr** function resets the error indicator and end-of-file indicator for the specified *stream* to 0. Error indicators are not automatically cleared; once the error indicator for a specified stream is set, operations on that stream continue to return an error value until **clearerr** or **rewind** is called.

■ See Also

eof, feof, ferror, perror

■ Example

```
#include <stdio.h>
#include <stdlib.h>

FILE *stream;
int c;

/* The following statements output data to a
** stream and then check to make sure a write error has
** not occurred. The stream must have been previously
** opened for writing.
*/
if ((c=getc(stream)) == EOF) {
    if (ferror(stream)) {
        fprintf(stderr, "write error\n");
        clearerr(stream);
    }
}
```

close

■ Summary

include <io.h> Required only for function declarations

int close(*handle*);
int *handle*; Handle referring to open file

■ Description

The **close** function closes the file associated with *handle*.

■ Return Value

The **close** function returns 0 if the file was successfully closed. A return value of -1 indicates an error, and **errno** is set to **EBADF**, indicating an invalid file-handle argument.

■ See Also

chsize, **creat**, **dup**, **dup2**, **open**, **unlink**

■ Example

```
#include <io.h>
#include <fcntl.h>

int fh;

fh = open("data", O_RDONLY) ;
.
.
.
close(fh) ;
```

■ Summary

```
# include <float.h>

unsigned int _control87(new, mask);      Get floating-point control word
unsigned int new;                      New control-word bit values
unsigned int mask;                     Mask for new control-word bits to set
```

■ Description

The **_control87** function gets and sets the floating-point control word. The floating-point control word allows the program to change the precision, rounding, and infinity modes in the floating-point math package. Floating-point exceptions can also be masked or unmasked using the **_control87** function.

If the value for *mask* is equal to 0, then **_control87** gets the floating-point control word. If *mask* is nonzero, then a new value for the control word is set in the following manner: for any bit that is on (equal to 1) in *mask*, the corresponding bit in *new* is used to update the control word. In other words,

```
fpcntrl = ((fpcntrl & ~mask) | (new & mask))
```

where *fpcntrl* is the floating-point control word.

■ Return Value

The bits in the value returned indicate the floating-point control state. See the **float.h** include file for a complete definition of the bits returned by **_control87**.

■ See Also

_clear87, **_status87**

_control87

■ Example

```
#include <stdio.h>
#include <float.h>

double a = .1;

main( )
{
    /* get control word */
    printf("control = %.4x\n", _control87(0,0));
    printf("a*a = .01 = %.15e\n", a*a);

    /* set precision to 24 bits */
    _control87(PC_24, MCW_PC);
    printf("a*a = .01 (rounded to 24 bits) = %.15e\n", a*a);

    /* restore to initial default */
    _control87(CW_DEFAULT, 0xffff);
    printf("a*a = .01 = %.15e\n", a*a);
}
```

■ Summary

```
# include <math.h>

double cos(x);           Calculate cosine of x
double cosh(x);          Calculate hyperbolic cosine of x
double x;                 Radians
```

■ Description

The **cos** and **cosh** functions return the cosine and hyperbolic cosine of *x*, respectively.

■ Return Value

The **cos** function returns the cosine of *x*. If *x* is large, a partial loss of significance in the result may occur. In such cases, **cos** generates a **PLOSS** error, but no message is printed. If *x* is so large that a total loss of significance results, **cos** prints a **TLOSS** error message to **stderr** and returns 0. In both cases, **errno** is set to **ERANGE**.

The **cosh** function returns the hyperbolic cosine of *x*. If the result is too large, **cosh** returns the value **HUGE** and sets **errno** to **ERANGE**. Error handling can be modified by using the **matherr** routine.

■ See Also

acos, asin, atan, atan2, matherr, sin, sinh, tan, tanh

■ Example

```
#include <math.h>

double x, y;
.
.
.
y = cos(x);
y = cosh(x);
```

cprintf

■ Summary

```
# include <conio.h> Required only for function declarations
```

```
int cprintf(format-string[], argument...]);
char *format-string; Format control string
```

■ Description

The **cprintf** function formats and prints a series of characters and values directly to the console, using the **putch** function to output characters. Each *argument* (if any) is converted and output according to the corresponding format specification in the *format-string*. The *format-string* has the same form and function as the *format-string* argument for the **printf** function; see the **printf** reference page for a description of the *format-string* and arguments.

■ Return Value

The **cprintf** function returns the number of characters printed.

■ See Also

fprintf, **printf**, **sprintf**, **vprintf**

Note

Unlike the **fprintf**, **printf**, and **sprintf** functions, **cprintf** does not translate line-feed (LF) characters into carriage-return-line-feed combinations (CR-LF) on output.

■ Example

```
#include <conio.h>

int i = -16, j = 29;
unsigned int k = 511;

/* The following statement prints i=-16, j=0x1d, k=511 */
cprintf("i=%d, j=%#x, k=%u\n", i, j, k);
```

cputs

■ Summary

include <conio.h> Required only for function declarations

void cputs(*str*);
char **str*; Pointer to output string

■ Description

The **cputs** function writes the null-terminated string pointed to by *str* directly to the console. Note that a carriage-return–line-feed combination (CR-LF) is not automatically appended to the string after writing.

■ Return Value

There is no return value.

■ See Also

putch

■ Example

```
#include <conio.h>  
  
char *buffer = "Insert data disk in drive a: \r\n";  
  
/* The following statement outputs a prompt to the  
** console.  
*/  
  
cputs(buffer);
```

■ Summary

```
# include <sys\ types.h>
# include <sys\ stat.h>
# include <io.h>
```

Required only for function declarations

```
int creat(pathname, pmode);
char * pathname;
int pmode;
```

Path name of new file
Permission setting

■ Description

The **creat** function either creates a new file or opens and truncates an existing file. If the file specified by *pathname* does not exist, a new file is created with the given permission setting and opened for writing. If the file already exists and its permission setting allows writing, **creat** truncates the file to length 0, destroying the previous contents, and opens it for writing.

The permission setting, *pmode*, applies to newly created files only. The new file receives the specified permission setting after it is closed for the first time. The integer expression *pmode* contains one or both of the manifest constants **S_IWRITE** and **S_IREAD**, defined in **sys\stat.h**. When both constants are given, they are joined with the bitwise OR operator (`|`). The meaning of the *pmode* argument is as follows:

Value	Meaning
S_IWRITE	Writing permitted
S_IREAD	Reading permitted
S_IREAD S_IWRITE	Reading and writing permitted

If write permission is not given, the file is read only. Under MS-DOS it is not possible to give write-only permission. Thus, the modes **S_IWRITE** and **S_IREAD | S_IWRITE** are equivalent. Under MS-DOS Version 3.0 and later, files opened using **creat** are always opened in compatibility mode (see **sopen**).

The **creat** function applies the current file-permission mask to *pmode* before setting the permissions (see **umask**).

creat

■ Return Value

The **creat** function returns a handle for the created file if the call is successful. A return value of -1 indicates an error, and **errno** is set to one of the following values:

Value	Meaning
EACCES	Path name specifies an existing read-only file or specifies a directory instead of a file.
EMFILE	No more file handles available (too many open files).
ENOENT	Path name not found.

■ See Also

chmod, chsize, close, dup, dup2, open, sopen, umask

Note

The **creat** routine is provided primarily for compatibility with previous libraries. A call to **open** with the **O_CREAT** and **O_TRUNC** values specified in the *oflag* argument is equivalent and is preferable for new code.

■ Example

```
#include <sys\types.h>
#include <sys\stat.h>
#include <io.h>
#include <stdlib.h>

int fh;

fh = creat("data", S_IREAD|S_IWRITE);
if (fh == -1)
    perror("couldn't create data file");
```

■ Summary

include <conio.h> Required only for function declarations

int fscanf(format-string[], argument...); Format control string
char *format-string;

■ Description

The **cscanf** function reads data directly from the console into the locations given by the *arguments* (if any), using the **getche** function to read characters. Each *argument* must be a pointer to a variable with a type that corresponds to a type specifier in the *format-string*. The *format-string* controls the interpretation of the input fields and has the same form and function as the *format-string* argument for the **scanf** function; see the **scanf** reference page for a description of the *format-string*.

■ Return Value

The **cscanf** function returns the number of fields that were successfully converted and assigned. The return value does not include fields that were read but not assigned.

The return value is **EOF** for an attempt to read at end-of-file. A return value of 0 means that no fields were assigned.

■ See Also

fscanf, scanf, sscanf

cscanf

■ Example

```
#include <conio.h>

int result;
char buffer[20];
.
.
.
cprintf("Please enter file name: ");

/* The following statement stores string input
** from the keyboard:
*/
result = cscanf("%19s",buffer);

/* Result is the number of correctly matched input
** fields. It is 0 if none could be matched.
*/
```

■ Summary

```
# include <time.h>
```

Required only for function declarations

```
char *ctime(time);
```

```
long *time;
```

Pointer to stored time

■ Description

The **ctime** function converts a time stored as a **long** value to a character string. The *time* value is usually obtained from a call to **time**, which returns the number of seconds elapsed since 00:00:00 Greenwich mean time, January 1, 1970.

The string result produced by **ctime** contains exactly 26 characters and has the form of the following example:

```
Mon Jan 02 02:03:55 1980\n\0
```

A 24-hour clock is used. All fields have a constant width. The new-line character ('\n') and the null character ('\0') occupy the last two positions of the string.

Under MS-DOS, dates prior to 1980 are not understood. If *time* represents a date before January 1, 1980, **ctime** returns the character string representation of 00:00:00 January 1, 1980.

■ Return Value

The **ctime** function returns a pointer to the character string result. There is no error return.

■ See Also

asctime, **ftime**, **gmtime**, **localtime**, **time**

Note

The **asctime** and **ctime** functions use a single statically allocated buffer for holding the return string. Each call to one of these routines destroys the result of the previous call.

■ Example

```
#include <time.h>
#include <stdio.h>

long ltime;

time(&ltime);
printf("the time is %s\n", ctime(&ltime));
```

■ Summary

```
# include <math.h>

int dieetombsin(src8, dst8);           IEEE double to MS binary double
int dmsbintoieee(src8, dst8);          MS binary double to IEEE double
double *src8, *dst8;
```

■ Description

The **dieetombsin** routine converts a double-precision number in IEEE format to Microsoft binary format. The **dmsbintoieee** routine converts a double-precision number in Microsoft binary format to IEEE format.

These routines allow C programs (which store floating-point numbers in the IEEE format) to use numeric data in random access data files created with Microsoft BASIC (which stores floating-point numbers in the Microsoft binary format), and vice versa.

The argument *src8* is a pointer to the **double** value to be converted. The result is stored at the location given by *dst8*.

■ Return Value

These functions return 0 if the conversion is successful and 1 if the conversion caused an overflow.

■ See Also

fieetombsin, **fmsbintoieee**

Note

These routines do not handle IEEE NaNs and infinities. IEEE denormals are treated as 0 in the conversions.

difftime

■ Summary

`# include <time.h>` Required only for function declarations

```
double difftime(time2, time1);
time_t time2;           Type time_t defined in time.h
time_t time1;
```

■ Description

The **difftime** function computes the difference *time2* – *time1*.

■ Return Value

The **difftime** function returns the elapsed time in seconds from *time1* to *time2* as a double-precision number.

■ See Also

time

■ Example

```
#include <time.h>

int mark[10000];

main( )
{
    /* This is an example of a timing application using
     * difftime. It calculates how long it takes to find
     * the prime numbers from 3 to 10000. To print out
     * the primes, delete the outermost loop and the comment
     * delimiters around "printf("%d\t",n);"
    */

    time_t start, finish;
    register int i, loop, n, num, step;

    time(&start);
    for (loop = 0; loop < 1000; ++loop)
        for (num = 0, n = 3; n < 10000; n += 2)
            if (!mark[n]) {
                /* printf("%d\t",n); */
                step = 2*n;
                for (i = 3*n; i < 10000; i += step)
                    mark[i] = -1;
                ++num;
            }
    time(&finish);

    /* Prints average of 1000 loops through "sieve": */
    printf("\nProgram takes %f seconds to find %d primes.\n",
           difftime(finish,start)/1000, num);
}
```

Output:

Program takes 0.482000 seconds to find 1228 primes.

dosexterr

■ Summary

```
# include <dos.h>

int dosexterr (buffer);
struct DOSERROR *buffer;
```

■ Description

The **dosexterr** function obtains the register values returned by the MS-DOS system call 59H and stores the values in the structure pointed to by *buffer*. This function is useful when making system calls under MS-DOS Version 3.0 or later, which offers extended error handling. See your *Microsoft MS-DOS Programmer's Reference Manual* for details on MS-DOS system calls.

The structure type **DOSERROR** is defined in **dos.h** as follows:

```
struct DOSERROR {
    int exterror;
    char class;
    char action;
    char locus;
};
```

Giving a **NULL** pointer argument causes **dosexterr** to return the value in **AX** without filling in the structure fields.

■ Return Value

The **dosexterr** function returns the value in the **AX** register (identical to the value in the **exterror** structure field).

■ See Also

perror

Note

The **dosexterr** function should be used only under MS-DOS Version 3.0 or later.

■ Example

```
#include <dos.h>
#include <fcntl.h>
#include <stdio.h>

struct DOSERROR doserror;
int fd;

if ((fd = open("test.dat", O_RDONLY)) == -1) {
    dosexterr(&doserror);
    printf("error=%d, class=%d, action=%d, locus=%d\n",
           doserror.exterror, doserror.class,
           doserror.action, doserror.locus);
}
```

dup – dup2

■ Summary

include <io.h> Required only for function declarations

int dup(handle); Create second handle for open file
int handle; Handle referring to open file

int dup2(handle1, handle2); Force *handle2* to refer to *handle1* file

int handle1; Handle referring to open file
int handle2; Any handle value

■ Description

The **dup** and **dup2** functions cause a second file handle to be associated with a currently open file. Operations on the file can be carried out using either file handle, since all handles associated with a given file use the same file pointer. The type of access allowed for the file is unaffected by the creation of a new handle.

The **dup** function returns the next available file handle for the given file. The **dup2** function forces the given handle, *handle2*, to refer to the same file as *handle1*. If *handle2* is associated with an open file at the time of the call, that file is closed.

■ Return Value

The **dup** function returns a new file handle. The **dup2** function returns 0 to indicate success. Both functions return -1 if an error occurs, and set **errno** to one of the following values:

Value	Meaning
EBADF	Invalid file handle
EMFILE	No more file handles available (too many open files)

■ **See Also**

close, creat, open

■ **Example**

```
#include <io.h>
#include <stdlib.h>

int fh;
.
.

/* Get another file handle to refer to the same file as
** file handle 1 (stdout).
*/
fh = dup(1);

if (fh == -1)
    perror("dup(1) failure");

/* Now make file handle 3 refer to the same file as file
** handle 1 (stdout). If file handle 3 is already open,
** it is closed first.
*/
fh = dup2(1,3);

if (fh != 0)
    perror("dup2(1,3) failure");
```

ecvt

■ Summary

include <stdlib.h> Required only for function declarations

```
char *ecvt(value, ndigits, decptr, signptr);
double value;                    Number to be converted
int ndigits;                    Number of digits stored
int *decptr;                    Pointer to stored decimal point position
int *signptr;                   Pointer to stored sign indicator
```

■ Description

The **ecvt** function converts a floating-point number to a character string. The *value* is the floating-point number to be converted. **Ecvt** stores *ndigits* digits of *value* as a string and appends a null character ('\0'). If the number of digits in *value* exceeds *ndigits*, the low-order digit is rounded. If there are fewer than *ndigits* digits, the string is padded with zeros.

Only digits are stored in the string. The position of the decimal point and the sign of *value* may be obtained after the call from *decptr* and *signptr*. The argument *decptr* points to an integer value giving the position of the decimal point with respect to the beginning of the string. A 0 or negative integer value indicates that the decimal point lies to the left of the first digit. The argument *signptr* points to an integer indicating the sign of the converted number. If the integer value is 0, the number is positive. Otherwise, the number is negative.

■ Return Value

The **ecvt** function returns a pointer to the string of digits. There is no error return.

■ See Also

atof, atoi, atol, fcvt, gcvt

Note

The **ecvt** and **fcvt** functions use a single statically allocated buffer for the conversion. Each call to one of these routines destroys the result of the previous call.

■ Example

```
#include <stdlib.h>

int decimal, sign;
char *buffer;
int precision = 10;

buffer = ecvt(3.1415926535, precision, &decimal, &sign);
/* buffer contains "3141592654", decimal = 1, sign = 0 */
```

eof

■ Summary

include <io.h> Required only for function declarations

int eof(*handle*);
int *handle*; Handle referring to open file

■ Description

The **eof** function determines whether end-of-file has been reached for the file associated with *handle*.

■ Return Value

The **eof** function returns the value 1 if the current position is end-of-file, 0 if it is not. A return value of -1 indicates an error; in this case, **errno** is set to **EBADF**, indicating an invalid file handle.

■ See Also

clearerr, **feof**, **ferror**, **perror**

■ Example

```
#include <io.h>
#include <fcntl.h>

int fh, count;
char buf[10];

fh = open("data", O_RDONLY);

/* The following statement tests for an end-of-file condition
** before reading. */

while (!eof(fh)) {
    count = read(fh, buf, 10);
    .
    .
    .
}
```

■ Summary

```
# include <process.h>           Required only for function declarations

int execl(pathname, arg0, arg1..., argn, NULL);
int execl(pathname, arg0, arg1..., argn, NULL, envp);
int execlp(pathname, arg0, arg1..., argn, NULL);
int execle(pathname, arg0, arg1..., argn, NULL, envp);
int execv(pathname, argv);
int execve(pathname, argv, envp);
int execvp(pathname, argv);
int execvpe(pathname, argv, envp);

char *pathname;                 Path name of file to be executed
char *arg0,*arg1,...,*argn;     List of pointers to arguments
char *argv[ ];                  Array of pointers to arguments
char *envp[ ];                  Array of pointers to environment
                                settings
```

■ Description

The **exec** functions load and execute new child processes. When the call is successful, the child process is placed in the memory previously occupied by the calling process. Sufficient memory must be available for loading and executing the child process.

The *pathname* argument specifies the file to be executed as the child process. The *pathname* can specify a full path (from the root), a partial path (from the current working directory), or just a file name. If *pathname* does not have a file-name extension or does not end with a period (.), the **exec** functions for the file; if unsuccessful, the extension .EXE is attempted. If *pathname* has an extension, only that extension is used. If *pathname* ends with a period, the **exec** calls search for *pathname* with no extension. The **execlp**, **execle**, **execvp**, and **execvpe** routines search for *pathname* (using the same procedures) in the directories specified by the PATH environment variable.

exec – execvpe

Arguments are passed to the new process by giving one or more pointers to character strings as arguments in the **exec** call. These character strings form the argument list for the child process. The combined length of the strings forming the argument list for the new process must not exceed 128 bytes. The terminating null character ('\0') for each string is not included in the count, but space characters (automatically inserted to separate arguments) are counted.

The argument pointers may be passed as separate arguments (**exec1**, **execle**, **execlp**, and **execlepe**) or as an array of pointers (**execv**, **execve**, **execvp**, and **execvpe**). At least one argument, *arg0* or *argv[0]*, must be passed to the child process. By convention, this argument is a copy of the *pathname* argument. (A different value will not produce an error.) Under versions of MS-DOS earlier than 3.0, the passed value of *arg0* or *argv[0]* is not available for use in the child process. However, under MS-DOS 3.0 and later, the *pathname* is available as *arg0* or *argv[0]*.

The **exec1**, **execle**, **execlp**, and **execlepe** calls are typically used in cases where the number of arguments is known in advance. The argument *arg0* is usually a pointer to *pathname*. The arguments *arg1* through *argn* point to the character strings forming the new argument list. A NULL pointer must follow *argn* to mark the end of the argument list.

The **execv**, **execve**, **execvp**, and **execvpe** calls are useful when the number of arguments to the new process is variable. Pointers to the arguments are passed as an array, *argv*. The argument *argv[0]* is usually a pointer to *pathname*. The arguments *argv[1]* through *argv[n]* point to the character strings forming the new argument list. The argument *argv[n+1]* must be a NULL pointer to mark the end of the argument list.

Files that are open when an **exec** call is made remain open in the new process. In the **exec1**, **execlp**, **execv**, and **execvp** calls, the child process inherits the environment of the parent. The **execle**, **execlepe**, **execve**, and **execvpe** calls allow the user to alter the environment for the child process by passing a list of environment settings through the *envp* argument. The argument *envp* is an array of character pointers, each element of which (except for the final element) points to a null-terminated string defining an environment variable. Such a string usually has the form

NAME=*value*

where **NAME** is the name of an environment variable and *value* is the string value to which that variable is set. (Notice that *value* is not enclosed in double quotes.) The final element of the *envp* array should be **NULL**. When *envp* itself is **NULL**, the child process inherits the environment settings of the parent process.

■ Return Value

The **exec** functions do not normally return to the calling process. If an **exec** function returns, an error has occurred and the return value is -1. The **errno** variable is set to one of the following values:

Value	Meaning
E2BIG	The argument list exceeds 128 bytes or the space required for the environment information exceeds 32K.
EACCES	Locking or sharing violation on the specified file (MS-DOS Version 3.0 or later).
EMFILE	Too many files open (the specified file must be opened to determine whether it is executable).
ENOENT	File or path name not found.
ENOEXEC	The specified file is not executable or has an invalid executable file format.
ENOMEM	Not enough memory is available to execute the child process; or the available memory has been corrupted; or an invalid block exists, indicating that the parent process was not allocated properly.

■ See Also

abort, exit, _exit, onexit, spawnl, spawnle, spawnlp, spawnlpe, spawnnv, spawnve, spawnvp, spawnvpe, system

Note

The **exec** calls do not preserve the translation modes of open files. If the child process must use files inherited from the parent, the **setmode** routine should be used to set the translation mode of these files to the desired mode.

Signal settings are not preserved in child processes created by calls to **exec** routines. The signal settings are reset to the default in the child process.

exec – execvpe

■ Example

```
#include <process.h>
#include <stdio.h>

extern char **environ;

char *args[4];
int result;

args[0] = "child";
args[1] = "one";
args[2] = "two";
args[3] = NULL;

/* All of the following statements attempt to execute a
** process called "child.exe" and pass it three arguments.
*/
result = execl("child.exe", "child", "one", "two", NULL);
result = execle("child.exe", "child", "one", "two", NULL,
                environ);
result = execlp("child.exe", "child", "one", "two", NULL);
result = execv("child.exe", args);
result = execve("child.exe", args, environ);
result = execvp("child.exe", args);
```

■ Summary

# include <process.h>	Required only for function declarations
# include <stdlib.h>	Use either process.h or stdlib.h
void exit(<i>status</i>);	Terminate after closing files
void _exit(<i>status</i>);	Terminate without flushing stream buffers
int <i>status</i>;	Exit status

■ Description

The **exit** and **_exit** functions terminate the calling process. The **exit** function flushes all buffers and closes all open files before terminating the process. The **_exit** function terminates the process without flushing stream buffers. The *status* value is typically set to 0 to indicate a normal exit and set to some other value to indicate an error.

Although the **exit** and **_exit** calls do not return a value, the low-order byte of *status* is made available to the waiting parent process, if there is one, after the calling process exits. If there is no parent process waiting on the exiting process, the *status* value is lost.

■ Return Value

There is no return value.

■ See Also

abort, execl, execle, execlp, execv, execve, execvp, onexit, spawnl, spawnle, spawnlp, spawnv, spawnve, spawnvp, system

exit – _exit

■ Example

```
#include <process.h>
#include <stdio.h>

FILE *stream;
.

.

/*
The following statements cause the process to
** terminate, after flushing buffers and closing
** open files, if another file cannot be opened:
*/
if ((stream = fopen("data","r")) == NULL) {
    fprintf(stderr,"couldn't open data file\n");
    exit(1);
}

/*
The following statements cause the process to
** terminate immediately if a file cannot be opened:
*/
if ((stream = fopen("data","r")) == NULL) {
    fprintf(stderr,"couldn't open data file\n");
    _exit(1);
}
```

■ Summary

```
#include <math.h>

double exp(x);
double x;                                Floating-point value
```

■ Description

The **exp** function returns the exponential function of its floating-point argument *x*.

■ Return Value

The **exp** function returns e^x . On overflow, the function returns **HUGE** and sets **errno** to **ERANGE**; on underflow, **exp** returns 0, but does not set **errno**.

■ See Also

log

■ Example

```
#include <math.h>

double x, y;
.
.
.
y = exp(x);
```

_expand

■ Summary

# include <malloc.h>	Required only for function declarations
char *_expand(ptr, size);	
char *ptr;	Pointer to previously allocated memory block
unsigned size;	New size in bytes

■ Description

The **_expand** function changes the size of a previously allocated memory block by attempting to expand or contract the block without moving its location in the heap. The *ptr* argument points to the beginning of the block. The *size* argument gives the new size of the block, in bytes. The contents of the block are unchanged up to the shorter of the new and old sizes.

The *ptr* argument can also point to a block that has been freed, as long as there has been no intervening call to **calloc**, **_expand**, **malloc**, or **realloc** since the block was freed. If *ptr* points to a freed block, the block will remain free after the call to **_expand**.

■ Return Value

The **_expand** function returns a **char** pointer to the reallocated memory block. Unlike **realloc**, **_expand** cannot move a block to change its size. This means the *ptr* argument to **_expand** is the same as the return value if there is sufficient memory available to expand the block without moving it.

The return value is **NULL** if there is insufficient memory available to expand the block to the given size without moving it. In this case, the item pointed to by *ptr* will have been expanded as much as possible in its current location.

The storage space pointed to by the return value is guaranteed to be suitably aligned for storage of any type of object. The new size of the item can be checked with the **_msize** function. To get a pointer to a type other than **char**, use a type cast on the return value.

■ See Also

calloc, free, malloc, _msize, realloc

■ Example

```
#include <stdio.h>
#include <malloc.h>

main( )
{
    long *oldptr;
    unsigned int newsize = 64000;

    oldptr = (long *)malloc(10000*sizeof(long));
    printf("Size of memory block pointed to by oldptr = %u\n",
           _msize(oldptr));

    if (_expand(oldptr,newsize) != NULL)
        printf("expand was able to increase block to %u\n",
               _msize(oldptr));
    else
        printf("expand was able to increase block to only %u\n",
               _msize(oldptr));
}
```

Sample output:

```
Size of memory block pointed to by oldptr = 40000
expand was able to increase block to only 44718
```

fabs

■ Summary

```
#include <math.h>

double fabs(x);
double x;           Floating-point value
```

■ Description

The **fabs** function returns the absolute value of its floating-point argument.

■ Return Value

The **fabs** function returns the absolute value of its argument. There is no error return.

■ See Also

abs, cabs, labs

■ Example

```
#include <math.h>

double x, y;
.
.
y = fabs(x);
```

■ Summary

```
# include <stdio.h>
```

```
int fclose(stream);  
FILE *stream;
```

Close an open stream
Pointer to file structure

```
int fcloseall( );
```

Close all open streams

■ Description

The **fclose** and **fcloseall** functions close a stream or streams. All buffers associated with the stream(s) are flushed prior to closing. System-allocated buffers are released when the stream is closed. Buffers assigned using **setbuf** are not automatically released.

The **fclose** function closes the given *stream*. The **fcloseall** function closes all open streams except **stdin**, **stdout**, **stderr**, **stdaux**, and **stdprn**.

■ Return Value

The **fclose** function returns 0 if the stream is successfully closed. The **fcloseall** function returns the total number of streams closed. Both functions return **EOF** to indicate an error.

■ See Also

close, **fdopen**, **fflush**, **fopen**, **freopen**

fclose – fcloseall

■ **Example**

```
#include <stdio.h>

FILE *stream;
int numclosed;

stream = fopen("data", "r");
.
.
.

/* The following statement closes the stream: */
fclose(stream);

/* The following statement closes all streams except
** stdin, stdout, stderr, stdaux, and stdprn:
*/
numclosed = fcloseall( );
```

■ Summary

include <stdlib.h> Required only for function declarations

```
char *fcvt(value, ndec, decptr, signptr);
double value;                        Number to be converted
int ndec;                          Number of digits after decimal point
int *decptr;                        Pointer to stored decimal-point position
int *signptr;                      Pointer to stored sign indicator
```

■ Description

The **fcvt** function converts a floating-point number to a character string. The *value* is the floating-point number to be converted. The **fcvt** function stores the digits of *value* as a string and appends a null character ('\0'). The argument *ndec* specifies the number of digits to be stored after the decimal point.

If the number of digits after the decimal point in *value* exceeds *ndec*, the correct digit is rounded according to the FORTRAN F format. If there are fewer than *ndec* digits of precision, the string is padded with zeros.

Only digits are stored in the string. The position of the decimal point and the sign of *value* may be obtained after the call from *decptr* and *signptr*. The argument *decptr* points to an integer value giving the position of the decimal point with respect to the beginning of the string. A 0 or negative integer value indicates that the decimal point lies to the left of the first digit. The argument *signptr* points to an integer indicating the sign of *value*. The integer is set to 0 if *value* is positive, and is set to a nonzero number if *value* is negative.

■ Return Value

The **fcvt** function returns a pointer to the string of digits. There is no error return.

■ See Also

atof, **atoi**, **atol**, **ecvt**, **gcvt**

Note

The **ecvt** and **fcvt** functions use a single statically allocated buffer for the conversion. Each call to one of these routines destroys the result of the previous call.

■ **Example**

```
#include <stdlib.h>

int decimal, sign;
char *buffer;
int precision = 10;

buffer = fcvt(3.1415926535,precision,&decimal,&sign);

/* buffer = "31415926535", decimal = 1, sign = 0 */
```

■ Summary

```
# include <stdio.h>
```

```
FILE *fdopen(handle, type);
```

```
int handle;
```

Handle referring to open file

```
char *type;
```

Type of access permitted

■ Description

The **fdopen** function associates an input/output stream with the file identified by *handle*, thus allowing a file opened for “low-level” I/O to be buffered and formatted. (See Section 4.7, “Input and Output,” in Chapter 4, “Run-Time Routines by Category,” for an explanation of stream I/O versus low-level I/O.) The *type* character string specifies the type of access requested for the file, as follows:

Type	Description
"r"	Open for reading (the file must exist).
"w"	Open an empty file for writing; if the given file exists, its contents are destroyed.
"a"	Open for writing at the end of the file (appending); create the file first if it doesn't exist.
"r+"	Open for both reading and writing (the file must exist).
"w+"	Open an empty file for both reading and writing; if the given file exists, its contents are destroyed.
"a+"	Open for reading and appending; create the file first if it doesn't exist.

Note

Use the "w" and "w+" modes with care, as they can destroy existing files.

fdopen

The specified *type* must be compatible with the access mode and/or sharing modes with which the file was opened. It is the user's responsibility to ensure that this compatibility is maintained.

When a file is opened with "a" or "a+" type, all write operations take place at the end of the file. Although the file pointer can be repositioned using **fseek** or **rewind**, the file pointer is always moved back to the end of the file before any write operation is carried out. Thus, existing data cannot be overwritten.

When the "r+", "w+", or "a+" type is specified, both reading and writing are allowed (the file is said to be open for "update"). However, when switching from reading to writing or vice versa, there must be an intervening **fseek** or **rewind** operation. The current position can be specified for the **fseek** operation, if desired.

In addition to the values listed above, one of the following characters may be appended to the *type* string to specify the translation mode for new lines.

Character	Meaning
t	Open in text (translated) mode; carriage-return-line-feed combinations (CR-LF) are translated into a single line feed (LF) on input; line-feed characters are translated to carriage-return-line-feed combinations on output.
b	Open in binary (untranslated) mode; the above translations are suppressed.

If **t** or **b** is not given in the *type* string, the translation mode is defined by the default mode variable **_fmode**.

■ **Return Value**

The **fdopen** function returns a pointer to the open stream. A NULL pointer value indicates an error.

■ See Also

dup, dup2, fclose, fcloseall, fopen, freopen, open

■ Example

```
#include <stdio.h>
#include <fcntl.h>

FILE *stream;
int fh;

fh = open("data", O_RDONLY);

/* The following statement associates a stream with the
** open file handle:
*/
stream = fdopen(fh, "r");
```

feof

■ Summary

```
#include <stdio.h>

int feof(stream);
FILE *stream;           Pointer to file structure
```

■ Description

The **feof** function determines whether the end of the given *stream* has been reached. Once end-of-file is reached, read operations return an end-of-file indicator until the stream is closed or **rewind** is called.

■ Return Value

The **feof** function returns a nonzero value when the current position is end-of-file. The value 0 is returned if the current position is not end-of-file. There is no error return.

■ See Also

clearerr, eof, ferror, perror

Note

The **feof** function is implemented as a macro.

■ Example

```
#include <stdio.h>

char string[100];
FILE *stream;
/* The following statements process lines of input
** until eof occurs:
*/
while (!feof(stream))
    if (fscanf(stream, "%s", string))
        process(string);
```

■ Summary

```
# include <stdio.h>
```

```
int ferror(stream);
```

```
FILE *stream; Pointer to file structure
```

■ Description

The **ferror** function tests for a reading or writing error on the given *stream*. If an error has occurred, the error indicator for the *stream* remains set until the stream is closed or rewound or until **clearerr** is called.

■ Return Value

The **ferror** function returns a nonzero value to indicate an error on the given *stream*. The return value 0 means no error has occurred.

■ See Also

clearerr, eof, feof, fopen, perror

Note

The **ferror** function is implemented as a macro.

ferror

■ Example

```
#include <stdio.h>

FILE *stream;
char *string;
.

.

/*
 * The following statements output data to a
 * stream and then check to make sure a write error has
 * not occurred. The stream must have been previously
 * opened for writing.
 */

fprintf(stream,"%s\n",string);
if (ferror(stream)) {
    fprintf(stderr,"write error\n");
    clearerr(stream);
}
```

■ Summary

```
#include <stdio.h>

int fflush(stream);
FILE *stream;                                Pointer to file structure
```

■ Description

If the specified *stream* is open for output, the **fflush** function causes the contents of the buffer associated with the *stream* to be written to the associated file. If the *stream* is open for input, the **fflush** function clears the contents of the buffer.

The *stream* remains open after the call. The **fflush** function has no effect on an unbuffered stream.

■ Return Value

The **fflush** function returns the value 0 if the buffer was successfully flushed. The value 0 is also returned in cases where the specified stream has no buffer or is open for reading only. A return value of **EOF** indicates an error.

■ See Also

fclose, **flushall**, **setbuf**

Note

Buffers are automatically flushed when they are full, when the stream is closed, or when a program terminates normally without closing the stream.

fflush

■ Example

```
#include <stdio.h>

FILE *stream;
char buffer[BUFSIZ];
.
.
.

/* The following two statements flush a stream's buffer and
** set up a new buffer for that stream: */

fflush(stream);
setbuf(stream,buffer);
```

■ Summary

`# include <malloc.h>` Required only for function declarations

`void _ffree(ptr);`
`char far *ptr;` Pointer to allocated memory block

■ Description

The **_ffree** function deallocates a memory block outside the default data segment. The argument *ptr* points to a memory block previously allocated through a call to **_fmalloc**. The number of bytes freed is the number of bytes specified when the block was allocated. After the call, the freed block is again available for allocation.

■ Return Value

There is no return value.

■ See Also

_fmalloc, free, malloc

Note

Attempting to free an invalid *ptr* (a pointer not allocated with **_fmalloc**) may affect subsequent allocation and cause errors.

_ffree

■ Example

```
#include <malloc.h>
#include <stdio.h>

char far *alloc;

/* Allocate 100 bytes and then free them.
 */

if ((alloc = _fmalloc(100)) == NULL)      /* test for
                                           ** valid pointer */

    printf("unable to allocate memory\n");
else
{
    .
    .
    .
    _ffree(alloc);                      /* free memory for
                                           ** the heap
                                           */
}
}
```

■ Summary

```
# include <stdio.h>
int fgetc(stream);
FILE *stream;
```

Read a character from *stream*
Pointer to file structure

```
int fgetchar();
```

Read a character from **stdin**

■ Description

The **fgetc** function reads a single character from the input *stream* at the current position and increases the associated file pointer (if any) to point to the next character. The **fgetchar** function is equivalent to **fgetc(stdin)**.

■ Return Value

The **fgetc** and **fgetchar** functions return the character read. A return value of **EOF** may indicate an error or end-of-file; however, the **EOF** value is also a legitimate integer value, so **feof** or **ferror** should be used to verify an error or end-of-file condition.

■ See Also

fputc, **fputchar**, **getc**, **getchar**

Note

The **fgetc** and **fgetchar** routines are identical to **getc** and **getchar**, but are functions, not macros.

fgetc – fgetchar

■ Example

```
#include <stdio.h>

FILE *stream;
char buffer[81];
int i;
int ch;
.

.

.

/* The following statements gather a line of input from
** a stream:
*/
for (i = 0; (i < 80) && ((ch = fgetc(stream)) != EOF) &&
     (ch != '\n'); i++)
    buffer[i] = ch;

buffer[i] = '\0';

/* "fgetchar( )" could be used instead of "fgetc(stream)" in
** the for statement above to gather a line of input from
** stdin (equivalent to "fgetc(stdin)").
*/
```

■ Summary

```
# include <stdio.h>
```

```
char *fgets(string, n, stream);  
char *string;  
int n;  
FILE *stream;
```

Read a string from *stream*
Storage location for data
Number of characters stored
Pointer to file structure

■ Description

The **fgets** function reads a string from the input *stream* and stores it in *string*. Characters are read from the current *stream* position up to and including the first new-line character ('\n'), up to the end of the stream, or until the number of characters read is equal to *n* - 1, whichever comes first. The result is stored in *string*, and a null character ('\0') is appended. The new line, if read, is included in the *string*. If *n* is equal to 1, *string* is empty ("").

The **fgets** function is similar to the library function **gets**; however, **gets** replaces the new-line character with the null character.

■ Return Value

The **fgets** function returns *string*. A NULL return value indicates an error or end-of-file condition. Use **feof** or **ferror** to determine whether the NULL value represents an error or end-of-file.

■ See Also

fputs, **gets**, **puts**

fgets

■ Example

```
#include <stdio.h>

FILE *stream;
char line[100], *result;

/* The following statement gets a line of input from a stream.
** No more than 99 characters, or up to \n, are read. */

result = fgets(line,100,stream);
```

■ Summary

```
# include <math.h>

int fieetomsbin(src4, dst4);      IEEE floating-point to MS binary floating-point
int fmsbintoieee(src4, dst4);     MS binary floating-point to IEEE floating-point
float *src4, *dst4;
```

■ Description

The **fieetomsbin** routine converts a single-precision floating-point number in IEEE format to Microsoft binary format. The **fmsbintoieee** routine converts a floating-point number in Microsoft binary format to IEEE format.

These routines allow C programs (which store floating-point numbers in the IEEE format) to use numeric data in random access data files created with Microsoft BASIC (which store floating-point numbers in the Microsoft binary format), and vice versa.

The argument *src4* points to the **float** value to be converted. The result is stored at the location given by *dst4*.

■ Return Value

These functions return 0 if the conversion is successful, and 1 if the conversion caused an overflow.

■ See Also

dieeeetomsbin, **dmsbintoieee**

Note

These routines do not handle IEEE NaNs and infinities. IEEE denormals are treated as 0 in the conversions.

filelength

■ Summary

```
# include <io.h>      Required only for function declarations
```

```
long filelength(handle);  
int handle;          Handle referring to open file
```

■ Description

The **filelength** function returns the length, in bytes, of the file associated with the given *handle*.

■ Return Value

The **filelength** function returns the file length in bytes. A return value of -1L indicates an error, and **errno** is set to **EBADF** to indicate an invalid file handle.

■ See Also

chsize, **fileno**, **fstat**, **stat**

■ Example

```
#include <io.h>  
#include <stdio.h>  
#include <stdlib.h>  
  
FILE *stream;  
long length;  
  
stream = fopen("data", "r");  
.  
.  
.  
/* The following statements attempt to determine the  
** length of a file associated with a stream:  
*/  
  
length = filelength(fileno(stream));  
  
if (length == -1L)  
    perror("filelength failed");
```

■ Summary

```
# include <stdio.h>

int fileno(stream);
FILE *stream;           Pointer to file structure
```

■ Description

The **fileno** function returns the file handle currently associated with the given *stream*. If more than one handle is associated with the stream, the return value is the handle assigned when the stream was initially opened.

■ Return Value

The **fileno** function returns the file handle. There is no error return. The result is undefined if *stream* does not specify an open file.

■ See Also

fdopen, **filelength**, **fopen**, **freopen**

Note

Fileno is implemented as a macro.

■ Example

```
#include <stdio.h>

int result;

/* The following statement determines the file handle
** of the stderr stream:
*/
result = fileno(stderr); /* result is 2 */
```

floor

■ Summary

```
# include <math.h>

double floor(x);
double x;           Floating-point value
```

■ Description

The **floor** function returns a floating-point value representing the largest integer that is less than or equal to *x*.

■ Return Value

The **floor** function returns the floating-point result. There is no error return.

■ See Also

ceil, fmod

■ Example

```
#include <math.h>

double y;
.
.
.
y = floor(2.8);          /* y = 2.0 */
y = floor(-2.8);         /* y = -3.0 */
```

■ Summary

```
# include <stdio.h>  
  
int flushall();
```

■ Description

The **flushall** function causes the contents of all buffers associated with open **output** streams to be written to the associated files. All buffers associated with open **input** streams are cleared of their current contents; the next read operation (if there is one) then reads new data from the input files into the buffers.

All streams remain open after the call to **flushall**.

■ Return Value

The **flushall** function returns the number of open streams (input and output). There is no error return.

■ See Also

fflush

Note

Buffers are automatically flushed when they are full, when streams are closed, or when a program terminates normally without closing streams.

flushall

■ Example

```
#include <stdio.h>

int numopen;
.
.
.

/* The following statement resolves any pending I/O on
** all streams: */

numopen = flushall( );
```

■ Summary

include <malloc.h> Required only for function declarations

char far *_fmalloc(size);
unsigned size; Bytes in allocated block

■ Description

The **_fmalloc** function allocates a memory block of at least *size* bytes outside the default data segment. (The block may be larger than *size* bytes, due to space required for alignment.)

■ Return Value

The **_fmalloc** function returns a far pointer to a **char**. The storage space pointed to by the return value is guaranteed to be suitably aligned for storage of any type of object. To get a pointer to a type other than **char**, use a type cast on the return value.

If sufficient memory is not available outside the default data segment, the allocation will be retried using the default data segment. If there is still insufficient memory available, the return value is **NULL**.

■ See Also

_ffree, _fmsize, malloc, realloc

■ Example

```
#include <malloc.h>

int *intarray;

/* Allocate space for 20 integers */

intarray = (int *)_fmalloc(20*sizeof(int));
```

fmod

■ Summary

```
# include <math.h>

double fmod(x, y);
double x;           Floating-point values
double y;
```

■ Description

The **fmod** function calculates the floating-point remainder of x/y , such that $x = iy + f$, where i is an integer, f has the same sign as x , and the absolute value of x is less than the absolute value of y .

■ Return Value

The **fmod** function returns the floating-point remainder. If y is 0, the function returns 0.

■ See Also

ceil, **fabs**, **floor**

■ Example

```
#include <math.h>

double x, y, z;
x = -10.0;
y = 3.0;
z = fmod(x,y);      /* z = -1.0 */
```

■ Summary

include <malloc.h> Required only for function declarations

unsigned _fmsize(*ptr*);
char far **ptr*; Pointer to memory block

■ Description

The **_fmsize** function returns the size in bytes of the memory block allocated by a call to **_fmalloc**.

■ Return Value

The **_fmsize** function returns the size in bytes as an unsigned integer.

■ See Also

_ffree, _fmalloc, malloc, _msize, _nfree, _nmalloc, _nmsize

■ Example

```
#include <malloc.h>
#include <stdio.h>

main( )
{
    char far *stringarray;

    stringarray = _fmalloc(200*sizeof(char));
    if (stringarray != NULL)
        printf("%u bytes allocated\n", _fmsize(stringarray));
    else
        printf("Allocation request failed.\n");
}
```

fopen

■ Summary

```
# include <stdio.h>
```

```
FILE *fopen(pathname, type);
```

```
char *pathname;
```

Path name of file

```
char *type;
```

Type of access permitted

■ Description

The **fopen** function opens the file specified by *pathname*. The character string *type* specifies the type of access requested for the file, as follows:

Type	Description
"r"	Open for reading (the file must exist).
"w"	Open an empty file for writing; if the given file exists, its contents are destroyed.
"a"	Open for writing at the end of the file (appending); create the file first if it doesn't exist.
"r+"	Open for both reading and writing (the file must exist).
"w+"	Open an empty file for both reading and writing; if the given file exists, its contents are destroyed.
"a+"	Open for reading and appending; create the file first if it doesn't exist.

Note

Use the "w" and "w+" modes with care, as they can destroy existing files.

When a file is opened with the "a" or "a+" type, all write operations occur at the end of the file. Although the file pointer can be repositioned using **fseek** or **rewind**, the file pointer is always moved back to the end of the file before any write operation is carried out. Thus, existing data cannot be overwritten.

When the "r+", "w+", or "a+" type is specified, both reading and writing are allowed (the file is said to be open for "update"). However, when switching between reading and writing, there must be an intervening **fseek** or **rewind** operation. The current position may be specified for the **fseek** operation, if desired.

In addition to the values listed above, one of the following characters may be appended to the *type* string to specify the translation mode for newlines:

Character	Meaning
t	Open in text (translated) mode; carriage-return-line-feed combinations (CR-LF) are translated into a single line feed (LF) on input; line-feed characters are translated to carriage-return-line-feed combinations on output.
b	Open in binary (untranslated) mode; the above translations are suppressed.

If **t** or **b** is not given in the *type* string, the translation mode is defined by the default mode variable **_fmode**.

■ Return Value

The **fopen** function returns a pointer to the open file. A NULL pointer value indicates an error.

■ See Also

fclose, **fcloseall**, **fdopen**, **ferror**, **fileno**, **freopen**, **open**, **setmode**

fopen

■ Example

```
#include <stdio.h>

main(argc, argv)
int argc;
char *argv[ ];

{
FILE *stream;

/* The following fopen attempts to open the file whose name
** is stored in the pointer argv[argc-1]; if it is not
** successful, the program prints an error message to stderr:
*/
if ((stream = fopen(argv[argc-1],"r")) == NULL) {
    fprintf(stderr,
            "%s couldn't open file %s\n", argv[0], argv[argc-1]);
    exit(1);
}
/* Note: the program name is stored in argv[0] only in
** MS-DOS versions 3.0 and later; in versions prior to
** 3.0, argv[0] contains the string "C"
*/
}
```

Sample command line:

update employ.dat

Output:

C:\BIN\UPDATE.EXE couldn't open file employ.dat

■ Summary

```
#include <dos.h>

unsigned FP_OFF(longptr);
unsigned FP_SEG(longptr);
char far *longptr Long pointer to memory address
```

■ Description

The **FP_OFF** and **FP_SEG** macros can be used to set or get the offset and segment, respectively, of the long pointer *longptr*.

■ Return Value

The **FP_OFF** macro returns an unsigned integer value representing an offset. The **FP_SEG** macro returns an unsigned integer value representing a segment address.

■ See Also

segread

■ Example

```
#include <dos.h>

char far *p;
unsigned int seg_val;
unsigned int off_val;
.
.
.
seg_val = FP_SEG(p);
off_val = FP_OFF(p);
```

_fpreset

■ Summary

```
# include <float.h>
```

```
void _fpreset( );
```

Reinitialize floating-point math package

■ Description

The **_fpreset** function reinitializes the floating-point math package. This function is usually used in conjunction with **signal**, **system**, or the **exec** or **spawn** family of routines.

If a program traps floating-point error signals (**SIGFPE**) with **signal**, it can safely recover from floating-point errors by invoking **_fpreset** and doing a **longjmp**.

Note

On MS-DOS versions prior to 4.0, a child process executed by **exec**, **spawn**, or **system** might affect the floating-point state of the parent process if an 8087 or 80287 coprocessor is used. Therefore, if you are using either an 8087 or an 80287, the following precautions are recommended:

- **exec**, **spawn**, or **system** should not be called during the evaluation of a floating-point expression.
 - **_fpreset** should be called after these routines if there is a possibility of the child process performing any floating-point operations using an 8087 or 80287.
-

■ Return Value

There is no return value.

■ See Also

execl, execle, execlp, execlepe, execv, execve, execvp, execvpe, signal, spawnl, spawnle, spawnlp, spawnlpe, spawnnv, spawnve, spawnvp, spawnvpe

■ Example

```
#include <stdio.h>
#include <signal.h>
#include <setjmp.h>
#include <float.h>

int fphandler( );
jmp_buf mark;
double a = 1.0, b = 0.0, c;

main ( )
{
    if (signal(SIGFPE,fphandler) == (int(*)())-1)
        abort( );
    if (setjmp(mark) == 0) {
        c = a/b;           /* generate f.p. error */
        printf("Should never get here\n");
    }
    printf("Recovered from floating-point error\n");
}

int fphandler(sig,num)
    int sig,num;

{
printf("signal = %d  subcode = %d\n",sig,num);
_fpreset();          /* reinitialize floating-point package */
longjmp(mark,-1);
}
```

fprintf

■ Summary

```
# include <stdio.h>
```

```
int fprintf(stream, format-string[], argument...);
```

```
FILE *stream;
```

Pointer to file structure

```
char *format-string;
```

Format control string

■ Description

The **fprintf** function formats and prints a series of characters and values to the output *stream*. Each *argument* (if any) is converted and output according to the corresponding format specification in the *format-string*.

The *format-string* has the same form and function as the *format-string* argument for the **printf** function; see the **printf** reference page for a description of the *format-string* and *arguments*.

■ Return Value

The **fprintf** function returns the number of characters printed.

■ See Also

cprintf, fscanf, printf, sprintf

■ Example

```
#include <stdio.h>

FILE *stream;
int i = 10;
double fp = 1.5;
char *s = "this is a string";
char c = '\n';

stream = fopen("results", "w");

/* Format and print various data. */

fprintf(stream, "%s%c", s, c);      /* prints "this is a string"
                                         ** followed by a new line
                                         */
fprintf(stream, "%d\n", i);          /* prints 10 followed by
                                         ** a new line
                                         */
fprintf(stream, "%f", fp);          /* prints 1.500000 */
```

fputc – fputchar

■ Summary

```
# include <stdio.h>
```

```
int fputc(c, stream);
int c;
FILE *stream;
```

Write a character to *stream*
Character to be written
Pointer to file structure

```
int fputchar(c);
int c;
```

Write a character to **stdout**
Character to be written

■ Description

The **fputc** function writes the single character *c* to the output *stream* at the current position. The **fputchar** function is equivalent to **fputc(c, stdout)**.

■ Return Value

The **fputc** and **fputchar** functions return the character written. A return value of **EOF** may indicate an error; however, since the **EOF** value is also a legitimate integer value, use **ferror** to verify an error condition.

Note

The **fputc** and **fputchar** routines are identical to **putc** and **putchar**, but are functions, not macros.

■ See Also

fgetc, **fgetchar**, **putc**, **putchar**

■ Example

```
#include <stdio.h>

FILE *stream;
char buffer[81];
int i;
int ch;
.

.

/* The following statements write the contents of a buffer to
** a stream. Note that the output occurs as a side effect
** within the for statement's second expression, so the
** statement body is null.
*/
for (i = 0; (i < 81) &&
      ((ch = fputc(buffer[i], stream)) != EOF); i++)
;

/*
*fputchar( ) could be used instead of "fputc(stream)"
** in the for statement above to write the buffer to stdout
** (equivalent to "fputc(stdout)").
*/
```

fputs

■ Summary

```
# include <stdio.h>
```

```
int fputs(string, stream);  
char *string;  
FILE *stream;
```

Write a string to *stream*
String to be output
Pointer to file structure

■ Description

The **fputs** function copies *string* to the output *stream* at the current position. The terminating null character ('\0') is not copied.

■ Return Value

The **fputs** function returns the last character output. If the input *string* is empty, the return value is 0. The return value EOF indicates an error.

■ See Also

fgets, gets, puts

■ Example

```
#include <stdio.h>  
  
FILE *stream;  
int result;  
. . .  
  
/* The following statement writes a string to a stream:  
 */  
  
result = fputs("data files have been updated\n", stream);
```

■ Summary

```
# include <stdio.h>
```

```
int fread(buffer, size, count, stream);
char *buffer;                                Storage location for data
int size;                                     Item size in bytes
int count;                                    Maximum number of items to be read
FILE *stream;                                 Pointer to file structure
```

■ Description

The **fread** function reads as many as *count* items of length *size* from the input *stream* and stores them in the given *buffer*. The file pointer associated with *stream* (if there is one) is increased by the number of bytes actually read.

If the given *stream* was opened in text mode, carriage-return–line-feed pairs (CR-LF) are replaced with single line-feed characters (LF). The replacement has no effect on the file pointer or the return value.

■ Return Value

The **fread** function returns the number of full items actually read, which may be less than *count* if an error occurs or the file end is encountered before reaching *count*.

■ See Also

fwrite, read

fread

■ Example

```
#include <stdio.h>

FILE *stream;
long list[100];
int numread;

stream = fopen("data", "r+b");

/* The following statement reads 100 binary long integers
** from the stream:
*/
numread = fread((char *)list,sizeof(long),100,stream);
```

■ Summary

`# include <malloc.h>` Required only for function declarations

`void free(ptr);` Pointer to allocated memory block
`char *ptr;`

■ Description

The **free** function deallocates a memory block. The argument *ptr* points to a memory block previously allocated through a call to **calloc**, **malloc**, or **realloc**. The number of bytes freed is the number of bytes specified when the block was allocated (or reallocated, in the case of **realloc**). After the call, the freed block is available for allocation.

■ Return Value

There is no return value.

■ See Also

calloc, **malloc**, **realloc**

Note

Attempting to free an invalid *ptr* (a pointer not allocated with **calloc**, **malloc**, or **realloc**) may affect subsequent allocation and cause errors.

free

■ Example

```
#include <malloc.h>
#include <stdio.h>

char *alloc;

/* Allocate 100 bytes and then free them.
 */

if ((alloc = malloc(100)) == NULL)      /* test for valid
                                           ** pointer
                                           */
{
    printf("unable to allocate memory\n");
}
else
{
    .
    .
    .
    free(alloc);                      /* free memory for
                                           ** the heap
                                           */
}
```

■ **Summary**

`# include <malloc.h>` Required only for function declarations

`unsigned int _freeect(size);`
`unsigned int size;` Item size in bytes

■ **Description**

The **_freeect** function tells you how much memory is available for dynamic memory allocation by returning the approximate number of times your program can call **malloc** to allocate an item of a given size in the default data segment.

■ **Return Value**

The **_freeect** function returns the number of calls as an unsigned integer.

■ **See Also**

calloc, **_expand**, **malloc**, **_memavl**, **_msize**, **realloc**

_freeect

■ Example

```
main( )
{
    int i;

    printf("Approximate # of times program can call malloc\n");
    printf("to allocate a single integer = %u\n\n",
          _freeect(sizeof(int)));

    /* Now, call malloc 1000 times, allocating a single int
     * each time:
     */

    for (i = 0; i < 1000; ++i)
        malloc(sizeof(int));

    printf("Approximate # of times program can call malloc\n");
    printf("to allocate a single integer = %u\n",
          _freeect(sizeof(int)));
}
```

Sample output:

```
Approximate # of times program can call malloc
to allocate a single integer = 15268
```

```
Approximate # of times program can call malloc
to allocate a single integer = 14266
```

■ Summary

```
# include <stdio.h>
```

```
FILE *freopen(pathname, type, stream);
char *pathname; Path name of new file
char *type; Type of access permitted
FILE *stream; Pointer to file structure
```

■ Description

The **freopen** function closes the file currently associated with *stream* and reassigns *stream* to the file specified by *pathname*. The **freopen** function is typically used to redirect the preopened files **stdin**, **stdout**, **stderr**, **stdaux**, and **stdprn** to files specified by the user. The new file associated with *stream* is opened with the given *type*, which is a character string specifying the type of access requested for the file, as follows:

Type	Description
"r"	Open for reading (the file must exist).
"w"	Open an empty file for writing; if the given file exists, its contents are destroyed.
"a"	Open for writing at the end of the file (appending); create the file first if it doesn't exist.
"r+"	Open for both reading and writing (the file must exist).
"w+"	Open an empty file for both reading and writing; if the given file exists, its contents are destroyed.
"a+"	Open for reading and appending; create the file first if it doesn't exist.

Note

Use the "w" and "w+" modes with care, as they can destroy existing files.

freopen

When a file is opened with the "**a**" or "**a+**" types, all write operations take place at the end of the file. Although the file pointer can be repositioned using **fseek** or **rewind**, the file pointer is always moved back to the end of the file before any write operation is carried out. Thus, existing data cannot be overwritten.

When the "**r+**", "**w+**", or "**a+**" types are specified, both reading and writing are allowed (the file is said to be open for "update"). However, when switching between reading and writing, there must be an intervening **fseek** or **rewind** operation. The current position may be specified for the **fseek** operation, if desired.

In addition to the values listed above, one of the following characters may be appended to the *type* string to specify the translation mode for new lines:

Character	Meaning
t	Open in text (translated) mode; carriage-return-line-feed combinations (CR-LF) are translated into a single line feed (LF) on input; line-feed characters are translated to carriage-return-line-feed combinations on output.
b	Open in binary (untranslated) mode; the above translations are suppressed.

If **t** or **b** is not given in the *type* string, the translation mode is defined by the default mode variable **_fmode**.

■ **Return Value**

The **freopen** function returns a pointer to the newly opened file. If an error occurs, the original file is closed and the function returns a **NULL** pointer value.

■ **See Also**

fclose, fcloseall, fdopen, fileno, fopen, open, setmode

■ Example

```
#include <stdio.h>

FILE *stream;
.

.

/* The following statement closes the stdout stream and
** reassigns its stream pointer: */
stream = freopen("data2", "w+", stdout);
```

frexp

■ Summary

```
# include <math.h>

double frexp(x, exptr);
double x;           Floating-point value
int *exptr;         Pointer to stored integer exponent
```

■ Description

The **frexp** function breaks down the floating-point value x into a mantissa m and an exponent n such that the absolute value of m is greater than or equal to 0.5 and less than 1.0 and $x = m \cdot 2^n$. The integer exponent n is stored at the location pointed to by *exptr*.

■ Return Value

The **frexp** function returns the mantissa m . If x is 0, the function returns 0 for both the mantissa and exponent. There is no error return.

■ See Also

ldexp, modf

■ Example

```
#include <math.h>

double x, y;
int n;
.

.

x = 16.4;
/* y will be .5125, n will be 5 */
y = frexp(x,&n);
```

■ Summary

```
# include <stdio.h>
```

```
int fscanf(stream, format-string[], argument...));
FILE *stream;           Pointer to file structure
char *format-string;   Format-control string
```

■ Description

The **fscanf** function reads data from the current position of the specified *stream* into the locations given by *arguments* (if any). Each *argument* must be a pointer to a variable with a type that corresponds to a type specifier in the *format-string*. The *format-string* controls the interpretation of the input fields and has the same form and function as the *format-string* argument for the **scanf** function; see the **scanf** reference page for a description of the *format-string*.

■ Return Value

The **fscanf** function returns the number of fields that were successfully converted and assigned. The return value does not include fields that were read but not assigned.

The return value is **EOF** for an attempt to read at end-of-file. A return value of 0 means that no fields were assigned.

■ See Also

cscanf, **fprintf**, **scanf**, **sscanf**

fscanf

■ Example

```
#include <stdio.h>

FILE *stream;
long l;
float fp;
char s[81];
char c;

stream = fopen("data", "r");
.
.
.

/* Input various data. */

fscanf(stream, "%s", s);
fscanf(stream, "%c", &c);
fscanf(stream, "%ld", &l);
fscanf(stream, "%f", &fp);
```

■ Summary

```
#include <stdio.h>

int fseek(stream, offset, origin);
FILE *stream;           Pointer to file structure
long offset;            Number of bytes from origin
int origin;             Initial position
```

■ Description

The **fseek** function moves the file pointer (if any) associated with *stream* to a new location that is *offset* bytes from the *origin*. The next operation on the stream takes place at the new location. On a stream open for update, the next operation can be either a read or a write.

The argument *origin* must be one of the following constants defined in **stdio.h**:

Origin	Definition
SEEK_SET	Beginning of file
SEEK_CUR	Current position of file pointer
SEEK_END	End of file

The **fseek** function can be used to reposition the pointer anywhere in a file. The pointer can also be positioned beyond the end of the file. However, an attempt to position the pointer in front of the beginning of the file causes an error.

■ Return Value

The **fseek** function returns the value 0 if the pointer was successfully moved. A nonzero return value indicates an error. On devices incapable of seeking (such as terminals and printers), the return value is undefined.

fseek

■ See Also

ftell, lseek, rewind

Note

For streams opened in text mode, **fseek** has limited use because carriage-return-line-feed translations can cause **fseek** to produce unexpected results. The only **fseek** operations guaranteed to work on streams opened in text mode are the following:

- seeking with an offset of 0 relative to any of the origin values
 - seeking from the beginning of the file with an offset value returned from a call to **ftell**
-

■ Example

```
#include <stdio.h>

FILE *stream;
int result;

stream = fopen("data", "r");
.
.
.

/* The following statement returns the file pointer to the
** beginning of the file:
*/
result = fseek(stream, 0L, SEEK_SET);
```

■ Summary

```
# include <sys\ types.h>
# include <sys\ stat.h>

int fstat(handle, buffer);
int handle;           Handle referring to open file
struct stat *buffer; Pointer to structure to store results
```

■ Description

The **fstat** function obtains information about the open file associated with the given *handle* and stores it in the structure pointed to by *buffer*. The structure, whose type **stat** is defined in **sys\stat.h**, contains the following fields:

Field	Value
st_mode	Bit mask for file-mode information. S_IFCHR bit set if <i>handle</i> refers to a device. S_IFREG bit set if <i>handle</i> refers to an ordinary file. User read/write bits set according to the file's permission mode.
st_dev	Either drive number of the disk containing the file, or <i>handle</i> in the case of a device.
st_rdev	Either drive number of the disk containing the file, or <i>handle</i> in the case of a device (same as st_dev).
st_nlink	Always 1.
st_size	Size of the file in bytes.
st_atime	Time of last modification of file.
st_mtime	Time of last modification of file (same as st_atime).
st_ctime	Time of last modification of file (same as st_atime and st_mtime).

There are three additional fields in the **stat** structure type that do not contain meaningful values under MS-DOS.

fstat

■ Return Value

The **fstat** function returns the value 0 if the file-status information is obtained. A return value of -1 indicates an error; in this case, **errno** is set to **EBADF**, indicating an invalid file handle.

■ See Also

access, **chmod**, **filelength**, **stat**

Note

If the given *handle* refers to a device, the size and time fields in the **stat** structure are not meaningful.

■ Example

```
#include <fcntl.h>
#include <sys\types.h>
#include <sys\stat.h>
#include <stdio.h>

struct stat buf;
int fh, result;

fh = open("tmp/data", O_RDONLY);
.
.
.
result = fstat(fh,&buf);

if (result == 0)
    printf("file size is %ld\n",buf.st_size);
```

■ Summary

```
# include <stdio.h>

long ftell(stream);
FILE *stream;           Pointer to file structure
```

■ Description

The **ftell** function gets the current position of the file pointer (if any) associated with *stream*. The position is expressed as an offset relative to the beginning of the *stream*.

■ Return Value

The **ftell** function returns the current position. A return value of -1L indicates an error. On devices incapable of seeking (such as terminals and printers), or when *stream* does not refer to an open file, the return value is undefined.

■ See Also

fseek, **lseek**, **tell**

Note

The value returned by **ftell** may not reflect the physical byte offset for streams opened in text mode, since text mode causes carriage-return line-feed translation. Use **ftell** in conjunction with the **fseek** function to remember and return to file locations correctly.

f_{tell}

■ **Example**

```
#include <stdio.h>

FILE *stream;
long position;

stream = fopen("data","rb");
.

.

position = ftell(stream);
```

■ Summary

```
# include <sys\ types.h>
# include <sys\ timeb.h>
```

```
void ftime(timeptr);
struct timeb *timeptr;
```

Pointer to structure defined in **sys\ timeb.h**

■ Description

The **ftime** function gets the current time and stores it in the structure pointed to by *timeptr*. The **timeb** structure is defined in **sys\ timeb.h**. It contains four fields, **time**, **millitm**, **timezone**, and **dstflag**, which have the following values:

Field	Value
time	The time in seconds since 00:00:00 Greenwich mean time, January 1, 1970.
millitm	Fraction of a second in milliseconds.
timezone	The difference in minutes, moving westward, between Greenwich mean time and local time. The value of timezone is set from the value of the global variable timezone (see tzset).
dstflag	Nonzero if daylight saving time is currently in effect for the local time zone, as determined from the value of the global variable daylight (see tzset).

■ Return Value

The **ftime** function gives values to the fields in the structure pointed to by *timeptr*. It does not return a value.

■ See Also

asctime, **ctime**, **gmtime**, **localtime**, **time**, **tzset**

ftime

■ Example

```
#include <sys/types.h>
#include <sys/timeb.h>
#include <stdio.h>
#include <time.h>

main( )
{
    struct timeb timebuffer;
    char *timeline;

    ftime(&timebuffer);

    timeline = ctime(&(timebuffer.time));

    printf("The time is %.19s.%hu %s",
           timeline, timebuffer.millitm, &timeline[20]);
}
```

Sample output:

The time is Wed Dec 04 17:58:29.420 1985

■ Summary

```
# include <stdio.h>

int fwrite(buffer, size, count, stream);
char *buffer;
int size;
int count;
FILE *stream;
```

Pointer to data to be written
Item size in bytes
Maximum number of items to be written
Pointer to file structure

■ Description

The **fwrite** function writes as many as *count* items of length *size* from *buffer* to the output *stream*. The file pointer associated with *stream* (if there is one) is incremented by the number of bytes actually written.

If the given *stream* was opened in text mode, each carriage return is replaced with a carriage-return–line-feed pair. The replacement has no effect on the return value.

■ Return Value

The **fwrite** function returns the number of full items actually written, which may be less than *count* if an error occurs.

■ See Also

fread, write

fwrite

■ Example

```
#include <stdio.h>

FILE *stream;
long list[100];
int numwritten;

stream = fopen("data", "r+b");
.

.

/* The following statement writes 100 long integers to
** a stream in binary format:
*/
numwritten = fwrite((char *)list,sizeof(long),100,stream);
```

■ Summary

<code># include <stdlib.h></code>	Required only for function declarations
<code>char gcvt(value, ndec, buffer);</code>	
<code>double value;</code>	Value to be converted
<code>int ndec;</code>	Number of significant digits stored
<code>char *buffer;</code>	Storage location for result

■ Description

The **gcvt** function converts a floating-point *value* to a character string and stores the string in *buffer*. The *buffer* should be large enough to accommodate the converted value plus a terminating null character ('\0'), which is automatically appended. There is no provision for overflow.

The **gcvt** function attempts to produce *ndec* significant digits in FORTRAN F format. Failing that, it produces *ndec* significant digits in FORTRAN E format. Trailing zeros may be suppressed in the conversion.

■ Return Value

The **gcvt** function returns a pointer to the string of digits. There is no error return.

■ See Also

atof, atoi, atol, ecvt, fcvt

■ Example

```
#include <stdlib.h>

char buffer[50];
int precision = 7;
/* buffer contains "-314150.0" */
gcvt(-3.1415e5,precision,buffer);
```

getc – getchar

■ Summary

```
# include <stdio.h>

int getc(stream);
FILE *stream;                                Read a character from stream
                                                Pointer to file structure

int getchar( );                               Read a character from stdin
```

■ Description

The **getc** macro reads a single character from the current *stream* position and increases the associated file pointer (if there is one) to point to the next character. The **getchar** macro is identical to **getc(stdin)**.

■ Return Value

The **getc** and **getchar** macros return the character read. A return value of **EOF** indicates an error or end-of-file condition. Use **ferror** or **feof** to determine whether an error or end-of-file occurred.

■ See Also

fgetc, **fgetchar**, **getch**, **getche**, **putc**, **putchar**, **ungetc**

Note

The **getc** and **getchar** routines are identical to **fgetc** and **fgetchar**, but are macros, not functions.

■ Example

```
#include <stdio.h>

FILE *stream;
char buffer[81];
int i, ch;
.

.

/*
 * The following statements gather a line of input from
 ** stdin:
 */

for (i = 0; (i < 80) && ((ch = getchar( )) != EOF) &&
     (ch != '\n'); i++)
    buffer[i] = ch;

buffer[i] = '\0';

/*
 * "getc(stdin)" could be used instead of "getchar( )" in the
 ** for statement above to gather a line of input from stdin.
 */
```

getch

■ Summary

#include <conio.h> Required only for function declarations

```
int getch();
```

■ Description

The **getch** function reads, without echoing, a single character directly from the console. Characters typed are not echoed. If a is typed, the system executes an INT 23H

■ Return Value

The **getch** function returns the character read. There is no error return.

■ See Also

cgets, getche, getchchar

■ Example

```
#include <conio.h>
#include <ctype.h>

int ch;

/* This loop gets characters from the keyboard until a
** nonblank character is seen. Preceding blank
** characters are discarded.
*/
do  {
    ch = getch();
}
while (isspace(ch));
```

■ Summary

```
# include <conio.h>          Required only for function declarations
```

```
int getche( );
```

■ Description

The **getche** function reads a single character from the console and echoes the character read. If a CONTROL-C is typed, the system executes an INT 23H (CONTROL-C exit).

■ Return Value

The **getche** function returns the character read. There is no error return.

■ See Also

cgets, getch, getchar

■ Example

```
#include <conio.h>
#include <ctype.h>

int ch;

/* Get a character from the keyboard and echo it to the
** console. If it is an uppercase letter, convert it
** to lowercase and write over the old character.
*/
ch = getche( );
if (isupper(ch))
    cprintf("\b%c", _tolower(ch));
```

getcwd

■ Summary

```
# include <direct.h>
```

Required only for function declarations

```
char *getcwd(pathbuf, n);  
char *pathbuf;  
int n;
```

Storage location for path name
Maximum length of path name

■ Description

The **getcwd** function gets the full path name of the current working directory and stores it at *pathbuf*. The integer argument *n* specifies the maximum length for the path name. An error occurs if the length of the path name (including the terminating null character) exceeds *n*.

The *pathbuf* argument can be **NULL**; a buffer of size *n* will automatically be allocated (with **malloc**) and used to store the path name. This buffer can later be freed by using the **getcwd** return value (a pointer to the allocated buffer) with the **free** function.

■ Return Value

The **getcwd** function returns *pathbuf*. A **NULL** return value indicates an error, and **errno** is set to one of the following values:

Value	Meaning
ENOMEM	Insufficient memory to allocate <i>n</i> bytes (when NULL argument given as <i>pathbuf</i>)
ERANGE	Path name longer than <i>n</i> characters

■ See Also

chdir, **mkdir**, **rmdir**

■ Example

```
#include <direct.h>
#include <stdlib.h>

char buffer[51];

/* The following statement stores the name of the current
** working directory (up to 50 characters long) in buffer:
*/

if (getcwd(buffer,50) == NULL)
    perror("getcwd error");
```

getenv

■ Summary

```
# include <stdlib.h>
```

Required only for function declarations

```
char *getenv(varname);
```

```
char *varname;
```

Name of environment variable

■ Description

The **getenv** function searches the list of environment variables for an entry corresponding to *varname*. Environment variables define the environment in which a process executes (for example, the default search path for libraries to be linked with a program).

■ Return Value

The **getenv** function returns a pointer to the environment table entry containing the current string value of *varname*. The return value is **NULL** if the given variable is not currently defined.

■ See Also

putenv

Note

Environment table entries must not be changed directly. If an entry must be changed, use the **putenv** function. To modify the returned value without affecting the environment table, use **strdup** or **strcpy** to make a copy of the string.

The **getenv** and **putenv** functions use the global variable **environ** to access the environment table. The **putenv** function may change the value of **environ**, thus invalidating the “*envp*” argument to the “*main*” function.

■ Example

```
#include <stdlib.h>

char *pathvar;

/* The following statement gets the value of the PATH
** environment variable:
*/

pathvar = getenv("PATH");

/* If an entry such as "PATH=A:\BIN;B:\BIN" is in the
** environment, pathvar will point to "A:\BIN;B:\BIN". If
** there is no PATH environment variable, pathvar will
** be NULL.
*/
```

getpid

■ Summary

```
# include <process.h>      Required only for function declarations  
int getpid();
```

■ Description

The **getpid** function returns an integer, the process ID, that uniquely identifies the calling process.

■ Return Value

The **getpid** function returns the process ID. There is no error return.

■ See Also

mktemp

■ Example

```
#include <process.h>  
#include <string.h>  
#include <stdio.h>  
  
char filename[9], pid[5];  
. . .  
strcpy(filename, "FILE");  
strcat(filename, itoa(getpid(), pid, 10));  
/* prints "FILExxxxx", where xxxxx is the process id */  
printf("File name is %s\n", filename);
```

■ Summary

```
# include <stdio.h>
```

```
char *gets(buffer);  
char *buffer;
```

Storage location for input string

■ Description

The **gets** function reads a line from the standard input stream **stdin** and stores it in *buffer*. The line consists of all characters up to and including the first new-line character ('\n'). The **gets** function then replaces the new-line character with a null character ('\0') before returning the line, unlike **fgets**, which retains the new-line character.

■ Return Value

The **gets** function returns its argument. A NULL pointer indicates an error or end-of-file condition. Use **ferror** or **feof** to determine whether an error or end-of-file occurred.

■ See Also

fgets, **fputs**, **puts**

■ Example

```
#include <stdio.h>  
  
char line[100];  
char *result;  
  
/* The following statement gets a line of input from  
** stdin:  
*/  
  
result = gets(line);
```

getw

■ Summary

```
# include <stdio.h>
```

```
int getw(stream);
```

```
FILE *stream; Pointer to file structure
```

■ Description

The **getw** function reads the next binary value of type **int** from the specified input *stream* and increases the associated file pointer (if there is one) to point to the next unread character. The **getw** function does not assume any special alignment of items in the stream.

■ Return Value

The **getw** function returns the integer value read. A return value of **EOF** may indicate an error or end-of-file; however, the **EOF** value is also a legitimate integer value, so **feof** or **ferror** should be used to verify an end-of-file or error condition.

■ See Also

putw

Note

The **getw** function is provided primarily for compatibility with previous libraries. Note that portability problems may occur with **getw** since the size of an **int** and ordering of bytes within an **int** differ across systems.

■ Example

```
#include <stdio.h>
#include <stdlib.h>

FILE *stream;
int i;
.

.

/*
 * The following statement reads a word from a stream
 * and checks for an error:
 */
i = getw(stream);

if (ferror(stream)) {
    fprintf(stderr,"getw failed\n");
    clearerr(stream);
}
```

gmtime

■ Summary

```
# include <time.h>
```

```
struct tm *gmtime(time);
```

```
long *time; Pointer to stored time
```

■ Description

The **gmtime** function converts a time stored as a **long** value to a structure. The **long** value *time* represents the seconds elapsed since 00:00:00, January 1, 1970, Greenwich mean time; this value is usually obtained from a call to **time**.

The **gmtime** function breaks down the *time* value and stores it in a structure of type **tm**, defined in **time.h**. The structure result reflects Greenwich mean time, not local time.

The fields of the structure type **tm** store the following values:

Field	Value Stored
tm_sec	Seconds
tm_min	Minutes
tm_hour	Hours (0-24)
tm_mday	Day of month (1-31)
tm_mon	Month (0-11; January = 0)
tm_year	Year (current year minus 1900)
tm_wday	Day of week (0-6; Sunday = 0)
tm_yday	Day of year (0-365; January 1 = 0)
tm_isdst	Nonzero if daylight saving time is in effect, otherwise 0

Under MS-DOS, dates prior to 1980 are not understood. If *time* represents a date before January 1, 1980, **gmtime** returns the structure representation of 00:00:00, January 1, 1980.

■ Return Value

The **gmtime** function returns a pointer to the structure result. There is no error return.

■ See Also

asctime, ctime, ftime, localtime, time

Note

The **gmtime** and **localtime** functions use a single statically allocated structure to hold the result. Each call to one of these routines destroys the result of the previous call.

■ Example

```
#include <time.h>

struct tm *newtime;
long ltime;

time(&ltime);
newtime = gmtime(&ltime);
printf("Greenwich mean time is %s\n", asctime(newtime));
```

malloc

■ Summary

```
# include <malloc.h>
```

Required only for function declarations

```
char huge *malloc(n, size);
```

long *n*;

Number of elements

unsigned *size*;

Length in bytes of each element

■ Description

The **malloc** function allocates storage space for a huge array of *n* elements, each of length *size* bytes. Each element is initialized to 0.

If the size of the array is greater than 128K, then the size of an array element must be a power of 2.

■ Return Value

The **malloc** function returns a **char huge** pointer to the allocated space. The storage space pointed to by the return value is guaranteed to be suitably aligned for storage of any type of object. To get a pointer to a type other than **char huge**, use a type cast on the return value. The return value is **NULL** if there is insufficient memory available.

■ See Also

calloc, free, hfree, malloc, realloc

■ Example

```
#include <malloc.h>

long huge *lalloc;
.
.
.
/* Allocate enough space for 80000 long integers and
** initialize it to 0.
*/
lalloc = (long huge *)malloc(80000L,sizeof(long));
```

■ Summary

```
# include <malloc.h>
```

Required only for function declarations

```
void hfree(ptr);
```

char huge **ptr*;

Pointer to allocated memory block

■ Description

The **hfree** function deallocates a memory block. The *ptr* argument points to a memory block previously allocated through a call to **halloc**. The number of bytes freed is the number of bytes specified when the block was allocated. After the call, the freed block is available for allocation.

■ Return Value

There is no return value.

■ See Also

halloc

Note

Attempting to free an invalid *ptr* (a pointer not allocated with **halloc**) may affect subsequent allocation and cause errors.

hfree

■ Example

```
#include <malloc.h>
#include <stdio.h>

char huge *alloc;

/* Allocate 80000 bytes and then free them.
 */
alloc = halloc(80000L,sizeof(char));
.

.

if (alloc != NULL)      /* test for valid pointer */
    hfree(alloc);      /* free memory for the heap */
```

■ Summary

```
#include <math.h>

double hypot(x,y);
double x, y;           Floating-point values
```

■ Description

The **hypot** function calculates the length of the hypotenuse of a right triangle, given the length of the two sides *x* and *y*. A call to **hypot** is equivalent to the following:

```
sqrt(x*x + y*y);
```

■ Return Value

The **hypot** function returns the length of the hypotenuse. If an overflow results, **hypot** sets **errno** to **ERANGE** and returns the value **HUGE**.

■ See Also

cabs

■ Example

```
#include <math.h>

double x, y, z;

x = 3.0;
y = 4.0;

z = hypot(x,y);
printf("Hypotenuse = %2.1f\n",z);
```

Output:

```
Hypotenuse = 5.0
```

inp

■ Summary

include <conio.h> Required only for function declarations

int inp(*port*);
unsigned *port*; Port number

■ Description

The **inp** function reads 1 byte from the input port specified by *port*. The *port* argument can be any unsigned integer number in the range 0 to 65535.

■ Return Value

The **inp** function returns the byte read from *port*. There is no error return.

■ See Also

outp

■ Example

```
#include <conio.h>

unsigned port;
char result;
.

.

/* The following statement inputs a byte from the port
** that 'port' is currently set to:
*/
result = inp(port);
```

■ Summary

```
#include <dos.h>
```

```
int int86(intno, inregs, outregs);  
int intno;                                Interrupt number  
union REGS *inregs;                      Register values on call  
union REGS *outregs;                     Register values on return
```

■ Description

The **int86** function executes the 8086 software interrupt specified by the interrupt number *intno*. Before executing the interrupt, **int86** copies the contents of *inregs* to the corresponding registers. After the interrupt returns, the function copies the current register values to *outregs*. It also copies the status of the system carry flag to the **cflag** field in *outregs*. The *inregs* and *outregs* arguments are unions of type **REGS**. The union type is defined in the include file **dos.h**.

The **int86** function is intended to be used to invoke DOS interrupts directly.

■ Return Value

The return value is the value in the **AX** register after the interrupt returns. If the **cflag** field in *outregs* is nonzero, an error has occurred and the **_doserrno** variable is also set to the corresponding error code.

■ See Also

bdos, **intdos**, **intdosx**, **int86x**

int86

■ Example

```
#include <signal.h>
#include <dos.h>
#include <stdio.h>
#include <process.h>

/*
 * (interrupt number 0x23), which would be caught by the
 * interrupt handling routine int_handler. Note that the
 * values in the regs struct do not matter for this
 * interrupt.
 */

#define CNTRL_C 0x23
int int_handler(int):
union REGS regs;
.
.
.
signal(SIGINT, int_handler);
.
.
.
int86(CNTRL_C, &regs, &regs);
```

■ Summary

```
# include <dos.h>
```

```
int int86x(intno, inregs, outregs, segreg);
int intno;                                Interrupt number
union REGS *inregs;                      Register values on call
union REGS *outregs;                     Register values on return
struct SREGS **segregs;                  Segment-register values on call
```

■ Description

The **int86x** function executes the 8086 software interrupt specified by the interrupt number *intno*. Unlike the **int86** function, **int86x** accepts segment-register values in *segregs*, letting programs that use long-model data segments or far pointers specify which segment or pointer should be used during the system call.

Before executing the specified interrupt, **int86x** copies the contents of *inregs* and *segregs* to the corresponding registers. Only the **DS** and **ES** register values in *segregs* are used. After the interrupt returns, the function copies the current register values to *outregs* and restores **DS**. It also copies the status of the system carry flag to the **cflag** field in *outregs*. The *inregs* and *outregs* arguments are unions of type **REGS**. The *segregs* argument is a structure of type **SREGS**. These types are defined in the include file **dos.h**.

The **int86x** function is intended to be used to directly invoke DOS interrupts that take an argument in the **ES** register, or take a **DS** register value that is different from the default data segment.

■ Return Value

The return value is the value in the **AX** register after the interrupt returns. If the **flag** field in *outregs* is nonzero, an error has occurred and the **doserrno** variable is also set to the corresponding error code.

int86x

■ See Also

bdos, intdos, intdosx, int86, segread, FP_SEG

Note

Segment values for the *segregs* argument can be obtained by using either the **segread** function or the **FP_SEG** macro.

■ Example

```
#include <signal.h>
#include <dos.h>
#include <stdio.h>
#include <process.h>

/*
 * Use int86x routine to generate an interrupt 0x21 (system
 * call), which invokes the DOS 'Change Attributes' system
 * call. The int86x routine is used because the file name to
 * be referenced may be in a segment other than the default
 * data segment (it is referenced by a far pointer), so the
 * DS register must be explicitly set with the SREGS struct.
 */

#define SYSCALL      0x21          /* INT 21H invokes system
                                    calls */
#define CHANGE_ATTR  0x43          /* system call 43H - change
                                    attributes */

char far *filename;           /* file name in 'far' data
                                segment */

union REGS inregs, outregs;
struct SREGS segregs;
int result;
.

.

inregs.h.ah = CHANGE_ATTR;    /* AH is system call
                                number */
inregs.h.al = 0;              /* AL is function (get
                                attributes) */
inregs.x.dx = FP_OFF(filename); /* DS:DX points to file
                                name */
```

```
segregs.ds = FP_SEG(filename);
result = int86x(SYSCALL, &inregs, &outregs, &segregs);
if (outregs.x.cflag) {
    printf("can't get attributes of file; error number %d\n",
           result);
    exit(1);
}
else {
    printf("Attrs = %#x\n", outregs.x.cx);
}
```

intdos

■ Summary

```
# include <dos.h>
```

```
int intdos(inregs, outregs);  
union REGS *inregs;  
union REGS *outregs;
```

Register values on call
Register values on return

■ Description

The **intdos** function invokes the DOS system call specified by register values defined in *inregs* and returns the effect of the system call in *outregs*. The *inregs* and *outregs* arguments are unions of type **REGS**. The union type is defined in the include file **dos.h**.

To invoke a system call, **intdos** executes an INT 21H instruction. Before executing the instruction, the function copies the contents of *inregs* to the corresponding registers. After the INT instruction returns, **intdos** copies the current register values to *outregs*. It also copies the status of the system carry flag to the **cflag** field in *outregs*. If this field is nonzero, the flag was set by the system call and indicates an error condition.

The **intdos** function is intended to be used to invoke DOS system calls that take arguments in registers other than **DX (DH/DL)** and **AL**, or to invoke system calls that indicate errors by setting the carry flag.

■ Return Value

The **intdos** function returns the value of the **AX** register after the system call is completed. If the **cflag** field in *outregs* is nonzero, an error has occurred and **_doserrno** is also set to the corresponding error code.

■ See Also

bdos, **intdosx**

■ Example

```
#include <dos.h>
#include <stdio.h>

union REGS inregs, outregs;
.

.

/* The following statements get the current date using
** DOS function call 2a hex:
*/
inregs.h.ah = 0x2a;
intdos(&inregs,&outregs);
printf("date is %d/%d/%d\n",outregs.h.dh,outregs.h.dl,
outregs.x.cx);
```

intdosx

■ Summary

```
# include <dos.h>
```

```
int intdosx(inregs, outregs, segregs);  
union REGS *inregs;  
union REGS *outregs;  
struct SREGS *segregs;
```

Register values on call
Register values on return
Segment-register values on call

■ Description

The **intdosx** function invokes the DOS system call specified by register values defined in *inregs* and returns the effect of the system call in *outregs*. Unlike the **intdos** function, **intdosx** accepts segment-register values in *segregs*, letting programs that use long-model data segments or far pointers specify which segment or pointer should be used during the system call. The *inregs* and *outregs* arguments are unions of type **REGS**. The *segregs* argument is a structure of type **SREGS**. These types are defined in the include file **dos.h**.

To invoke a system call, **intdosx** executes an INT 21H instruction. Before executing the instruction, the function copies the contents of *inregs* and *segregs* to the corresponding registers. Only the **DS** and **ES** register values in *segregs* are used. After the INT instruction returns, **intdosx** copies the current register values to *outregs* and restores **DS**. It also copies the status of the system carry flag to the **cflag** field in *outregs*. If this field is nonzero, the flag was set by the system call and indicates an error condition.

The **intdosx** function is intended to be used to invoke DOS system calls that take an argument in the **ES** register, or that take a **DS** register value that is different from the default data segment.

■ Return Value

The **intdosx** function returns the value of the **AX** register after the system call is completed. If the **cflag** field in *outregs* is nonzero, an error has occurred and **_doserrno** is also set to the corresponding error code.

■ See Also**bdos, intdos, segread, FP_SEG****Note**

Segment values for the *segregs* argument can be obtained by using either the **segread** function or the **FP_SEG** macro.

■ Example

```
#include <dos.h>

union REGS inregs, outregs;
struct SREGS segregs;
char far *dir = "/test/bin";

/* The following statements change the current working
** directory with DOS function call 3b hex:
*/
inregs.h.ah = 0x3b;           /* change directory */
inregs.x.dx = FP_OFF(dir);   /* file name offset */
segregs.ds = FP_SEG(dir);    /* file name segment */
intdosx(&inregs,&outregs,&segregs);
```

isalnum – isascii

■ Summary

```
# include <ctype.h>
```

int isalnum(c);	Test for alphanumeric ('A'–'Z', 'a'–'z', or '0'–'9')
-----------------	--

int isalpha(c);	Test for letter ('A'–'Z' or 'a'–'z')
-----------------	--------------------------------------

int isascii(c);	Test for ASCII character (0x00–0x7F)
-----------------	--------------------------------------

int c;	Integer to be tested
--------	----------------------

■ Description

The **ctype** routines listed above test a given integer value, returning a nonzero value if the integer satisfies the test condition and a 0 value if it does not. An ASCII character set environment is assumed.

The **isascii** routine produces meaningful results for all integer values. However, the remaining routines produce a defined result only for integer values corresponding to the ASCII character set (that is, only where **isascii** holds true) or for the non-ASCII value **EOF** (defined in **stdio.h**).

■ See Also

iscntrl, **isdigit**, **isgraph**, **islower**, **isprint**, **ispunct**, **isspace**, **isupper**,
isxdigit, **toascii**, **tolower**, **toupper**

Note

The **ctype** routines are implemented as macros.

■ Example

```
#include <stdio.h>
#include <ctype.h>

int ch;

/* The following statements analyze all characters
** between code 0x0 and code 0x7f, printing "A" for
** alphas, "AN" for alphanumeric, and "AS" for ASCIIIs:
*/
for (ch = 0; ch <= 0x7f; ch++) {
    printf("%#04x", ch);
    printf("%3s", isalnum(ch) ? "AN" : "");
    printf("%2s", isalpha(ch) ? "A" : "");
    printf("%3s", isascii(ch) ? "AS" : "");
    putchar ('\n');
}
```

isatty

■ Summary

include <io.h> Required only for function declarations

int isatty(handle);
int handle; Handle referring to device to be tested

■ Description

The **isatty** function determines whether the given *handle* is associated with a character device (that is, a terminal, console, printer, or serial port).

■ Return Value

The **isatty** function returns a nonzero value if the device is a character device. Otherwise, the return value is 0.

■ Example

```
#include <io.h>

int fh;
long loc;
.

.

if (isatty(fh) == 0)
    loc = tell(fh); /* if not a device, get current
                      ** position
                     */
```

■ Summary

```
# include <ctype.h>
```

<code>iscntrl(c);</code>	Test for control character (0x00–0x1f or 0x7f)
<code>isdigit(c);</code>	Test for digit ('0'–'9')
<code>isgraph(c);</code>	Test for printable character not including the space character (0x21–0x7e)
<code>islower(c);</code>	Test for lowercase ('a'–'z')
<code>isprint(c);</code>	Test for printable character (0x20–0x7e)
<code>ispunct(c);</code>	Test for punctuation character (<code>isalnum(c)</code> , <code>iscntrl(c)</code> , and <code>isspace(c)</code> all false)
<code>isspace(c);</code>	Test for white-space character (0x09–0x0d or 0x20)
<code>isupper(c);</code>	Test for uppercase ('A'–'Z')
<code>isxdigit(c);</code>	Test for hexadecimal digit ('A'–'F', 'a'–'f', or '0'–'9')
<code>int c;</code>	Integer value to be tested

■ Description

The **ctype** routines listed above test a given integer value, returning a nonzero value if the integer satisfies the test condition, and 0 if it does not. An ASCII character set environment is assumed.

These routines produce a defined result only for integer values corresponding to the ASCII character set (that is, only where `isascii` holds true) or for the non-ASCII value **EOF** (defined in **stdio.h**).

iscntrl – isxdigit

■ See Also

isalnum, isalpha, isascii, toascii, tolower, toupper

Note

The **ctype** routines are implemented as macros.

■ Example

```
#include <stdio.h>
#include <ctype.h>

int ch;

/* The following statements analyze all characters
** between code 0x0 and code 0x7f, printing "U" for
** uppercase letters, "L" for lowercase letters, "D"
** for digits, "X" for hex digits, "S" for spaces, "PU"
** for punctuations, "PR" for printables, "G" for graphics,
** and "C" for controls. If the code is printable, it is
** printed.
*/
for (ch = 0; ch <= 0x7f; ch++) {
    printf("%2s", iscntrl(ch) ? "C" : "");
    printf("%2s", isdigit(ch) ? "D" : "");
    printf("%2s", isgraph(ch) ? "G" : "");
    printf("%2s", islower(ch) ? "L" : "");
    printf("%c", isprint(ch) ? ch : '\0');
    printf("%3s", ispunct(ch) ? "PU" : "");
    printf("%2s", isspace(ch) ? "S" : "");
    printf("%3s", isprint(ch) ? "PR" : "");
    printf("%2s", isupper(ch) ? "U" : "");
    printf("%2s", isxdigit(ch) ? "X" : "");
}

putchar ('\n');
```

■ Summary

include <stdlib.h> Required only for function declarations

```
char *itoa(value, string, radix);  
int value;                        Number to be converted  
char *string;                  String result  
int radix;                     Base of value
```

■ Description

The **itoa** function converts the digits of the given *value* to a null terminated character string and stores the result in *string*. The *radix* argument specifies the base of *value*; it must be in the range 2–36. If *radix* equals 10 and *value* is negative, the first character of the stored string is the minus sign (-).

■ Return Value

The **itoa** function returns a pointer to *string*. There is no error return.

■ See Also

ltoa, ultoa

Note

The space allocated for *string* must be large enough to hold the returned string. The function can return up to 17 bytes.

■ Example

```
#include <stdlib.h>  
  
int radix = 8;  
char buffer[20];  
char *p;  
  
p = itoa(-3445,buffer,radix); /* p = "171213" */
```

kbhit

■ Summary

include <conio.h> Required only for function declarations

```
int kbhit();
```

■ Description

The **kbhit** function checks the console for a recent keystroke.

■ Return Value

The **kbhit** function returns a nonzero value if a key has been pressed. Otherwise, it returns 0.

■ Example

```
#include <conio.h>

int result;

/* The following statement tests to see if a key has
** been pressed:
*/
result = kbhit();

/* If result is nonzero, a keystroke is waiting in the
** buffer. It can be fetched with getch or getche.
** If getch or getche were called without first checking
** kbhit, the program might pause while waiting for
** input.
*/
```

■ Summary

include <stdlib.h> Required only for function declarations

long labs(*n*);
long *n*; Long integer value

■ Description

The **labs** function produces the absolute value of its long-integer argument *n*.

■ Return Value

The **labs** function returns the absolute value of its argument. There is no error return.

■ See Also

abs, cabs, fabs

■ Example

```
#include <stdlib.h>

long x, y;
x = -41567L;
y = labs(x); /* y = 41567L */
```

ldexp

■ Summary

```
#include <math.h>

double ldexp(x, exp);
double x;                                Floating-point value
int exp;                                 Integer exponent
```

■ Description

The **ldexp** function calculates the value of $x * 2^{exp}$.

■ Return Value

The **ldexp** function returns $x * 2^{exp}$. If an overflow results, the function returns $\pm \text{HUGE}$ (depending on the sign of x) and sets **errno** to **ERANGE**.

■ See Also

frexp, modf

■ Example

```
#include <math.h>

double x, y;
int p;

x = 1.5;
p = 5;
y = ldexp(x,p);           /* y = 48.0 */
```

■ Summary

`# include <search.h>` Required only for function declarations

`char *lsearch(key, base, num, width, compare);`

`char *lfind(key, base, num, width, compare);`

`char *key;`

Search key

`char *base;`

Pointer to base of search data

`unsigned *num, width;`

Number and width of elements

`int (*compare)();`

Pointer to compare function

■ Description

The **lsearch** and **lfind** functions perform a linear search for the value *key* in an array of *num* elements, each of *width* bytes in size. (Unlike **bsearch**, **lsearch** and **lfind** do not require the array to be sorted.) The argument *base* is a pointer to the base of the array to be searched.

If the *key* is not found, **lsearch** adds it to the end. The **lfind** function does not.

The argument *compare* is a pointer to a user-supplied routine that compares two array elements and returns a value specifying their relationship. Both **lsearch** and **lfind** call the *compare* routine one or more times during the search, passing pointers to two array elements on each call. This routine must compare the elements, then return one of the following values:

Value	Meaning
Not equal to 0	<i>element1</i> and <i>element2</i> different
0	<i>element1</i> identical to <i>element2</i>

■ Return Value

Both **lsearch** and **lfind** return a pointer to the first occurrence of *key* in the array pointed to by *base*. If *key* is not found, these functions return **NULL**.

lfind – lsearch

■ See Also

bsearch

■ Example

```
/* The lsearch function performs a linear search on an array
** for a 'key' element; lsearch returns a pointer to the
** structure that matches the key, or NULL if there is no
** match.
*/
#include <search.h>
#include <string.h>
#include <stdio.h>

int compare( ); /* must declare as a function */

main (argc, argv)
    int argc;
    char **argv;
{

    char **result;
    char *key = "PATH";

/* The following statement finds the argument that
** starts with "PATH":
*/
    result = (char **)lsearch((char *)&key, (char *)argv,
                               &argc, sizeof(char *), compare);
    if (result)
        printf("%s found\n", *result);
    else
        printf("PATH not found!\n");
}

int compare (arg1, arg2)
    char **arg1, **arg2;

{
    return(strncmp(*arg1,*arg2,strlen(*arg1)));
}
```

■ Summary

```
# include <time.h>

struct tm *localtime(time);
long *time;                                Pointer to stored time
```

■ Description

The **localtime** function converts a time stored as a **long** value to a structure. The **long** value *time* represents the seconds elapsed since 00:00:00, January 1, 1970, Greenwich mean time; this value is usually obtained from the *time* function.

The **localtime** function breaks down the *time* value, corrects for the local time zone and daylight saving time if appropriate, and stores the corrected time in a structure of type *tm*. (See **gmtime** for a description of the *tm* structure fields.)

Under MS-DOS, dates prior to 1980 are not understood. If *time* represents a date before January 1, 1980, **localtime** returns the structure representation of 00:00:00 January 1, 1980.

The **localtime** function makes corrections for the local time zone if the user first sets the environment variable **TZ**. The value of **TZ** must be a three-letter time zone name (such as PST), followed by a possibly signed number giving the difference between Greenwich mean time and the local time zone. The number may be followed by a three-letter daylight saving time zone (such as PDT). The **localtime** function uses the difference between Greenwich mean time and local time to adjust the stored time value. If a daylight saving time zone is present in the **TZ** setting, **localtime** also corrects for daylight saving time. If **TZ** currently has no value, the default value PST8PDT is used.

When **TZ** is set, three other environment variables, **timezone**, **daylight**, and **tzname**, are automatically set as well. See the **tzset** function for a description of these variables.

localtime

■ Return Value

The **localtime** function returns a pointer to the structure result. There is no error return.

■ See Also

asctime, ctime, ftime, gmtime, time, tzset

Note

The **gmtime** and **localtime** functions use a single statically allocated buffer for the conversion. Each call to one of these routines destroys the result of the previous call.

■ Example

```
#include <stdio.h>
#include <time.h>

main( )
{
    struct tm *newtime;
    char *am_pm = "PM";
    time_t long_time;

    time(&long_time);
    newtime = localtime(&long_time);

    if (newtime->tm_hour < 12)
        am_pm = "AM";
    if (newtime->tm_hour > 12)
        newtime->tm_hour -= 12;

    printf("%.19s %s\n", asctime(newtime), am_pm);
}
```

Sample output:

Tue Dec 10 11:30:12 AM

■ Summary

```
# include <sys\locking.h>
# include <i.o.h>
```

Required only for function declarations

```
int locking(handle, mode, nbytes);
int handle;           File handle
int mode;             File locking mode
long nbytes;          Number of bytes to lock
```

■ Description

The **locking** function locks or unlocks *nbyte* bytes of the file specified by *handle*. Locking bytes in a file prevents subsequent reading and writing of those bytes by other processes. Unlocking a file permits other processes to read or write to previously locked bytes. All locking or unlocking begins at the current position of the file pointer and proceeds for the next *nbyte* bytes, or to the end of the file.

The argument *mode* specifies the locking action to be performed. It must be one of the following manifest constants:

Manifest Constant	Meaning
LK_LOCK	Lock the specified bytes. If the bytes cannot be locked, try again after 1 second. If, after 10 attempts, the bytes cannot be locked, return an error.
LK_RLCK	Same as LK_LOCK .
LK_NBLCK	Lock the specified bytes. If bytes cannot be locked, return an error.
LK_NBRLCK	Same as LK_NBLCK .
LK_UNLCK	Unlock the specified bytes. The bytes must have been previously locked.

More than one region of a file can be locked, but no overlapping regions are allowed. Furthermore, no more than one region can be unlocked at a time.

locking

When unlocking a file, the region of the file being unlocked must correspond to a region that was previously locked. The **locking** function does not coalesce adjacent regions, so if two locked regions are adjacent, each region must be unlocked separately.

All locks should be removed before closing a file or exiting the program.

■ **Return Value**

The **locking** function returns 0 if it is successful. A return value of -1 indicates failure, and **errno** is set to one of the following values:

Value	Meaning
EACCES	Locking violation (file already locked or unlocked).
EBADF	Invalid file handle.
EDEADLOCK	Locking violation. This is returned when the LK_LOCK or LK_RLCK flag is specified and the file cannot be locked after 10 attempts.
EINVAL	

■ **See Also**

creat, **open**

Note

The **locking** function should be used only under MS-DOS 3.0 and later; it has no effect under earlier versions of MS-DOS.

■ Example

```
#include <io.h>
#include <sys\locking.h>
#include <stdlib.h>

extern unsigned char _osmajor;
int fh;
long pos;
.

.

/* Save the current file pointer position, then lock a
** region from the beginning of the file to the saved
** file pointer position:
*/
if (_osmajor >= 3) {
    pos = tell(fh);
    lseek(fh, OL, 0);
    if ((locking(fh, LK_NBLCK, pos)) != -1) {
        .
        .
        lseek(fh, OL, 0);
        locking(fh, LK_UNLCK, pos);
    }
}
```

log – log10

■ Summary

```
#include <math.h>

double log(x);           Calculate natural logarithm of x

double log10(x);         Calculate logarithm base 10 of x

double x;                Floating-point value
```

■ Description

The **log** and **log10** functions calculate the natural logarithm and base 10 logarithm of *x*, respectively.

■ Return Value

The **log** and **log10** functions return the logarithm result. If *x* is negative, both functions print a **DOMAIN** error message to **stderr** and return the value negative **HUGE**. If *x* is 0, both functions print a **SING** error message and return the value negative **HUGE**. In either case, **errno** is set to **EDOM**.

Error handling can be modified by using the **matherr** routine.

■ See Also

exp, matherr, pow

■ Example

```
#include <math.h>

double x = 1000.0, y;
y = log(x);      /* y = 6.907755 */
/* The log10 function calculates the base 10 logarithm of the
** given value.
*/
y = log10(x);    /* y = 3.0 */
```

■ Summary

```
# include <setjmp.h>
```

```
void longjmp(env, value);
jmp_buf env;
int value;
```

Variable in which environment is stored
Value to be returned to **setjmp** call

■ Description

The **longjmp** function restores a stack environment previously saved in *env* by **setjmp**. The **setjmp** and **longjmp** functions provide a way to execute a nonlocal goto and are typically used to pass execution control to error-handling or recovery code in a previously called routine without using the normal calling or return conventions.

A call to **setjmp** causes the current stack environment to be saved in *env*. A subsequent call to **longjmp** restores the saved environment and returns control to the point immediately following the corresponding **setjmp** call. Execution resumes as if the given *value* had just been returned by the **setjmp** call. The values of all variables (except register variables) accessible to the routine receiving control contain the values they had when **longjmp** was called. The values of register variables are unpredictable.

The **longjmp** function must be called before the function that called **setjmp** returns. If **longjmp** is called after the function calling **setjmp** returns, unpredictable program behavior will result.

The *value* returned by **longjmp** must be nonzero. If a 0 argument is given for *value*, the value 1 is substituted in the actual return.

■ Return Value

There is no return value.

■ See Also

setjmp

longjmp

Warning

The values of register variables in the routine calling **setjmp** may not be restored to the proper values after a **longjmp** is executed.

■ Example

```
#include <stdio.h>
#include <setjmp.h>

jmp_buf mark;

main( )
{
    if (setjmp(mark) != 0) {
        printf("longjmp has been called\n");
        recover( );
        exit(1);
    }
    printf("setjmp has been called\n");
    .
    .
    .
    p( );
    .
    .
    .
}

p( )
{
    int error = 0;
    .
    .
    .
    if (error != 0)
        longjmp(mark, -1);
    .
    .
    .
}
```

longjmp

```
recover( )
{
    /* ensure that data files won't be corrupted by
     * exiting the program */
    .
    .
    .
}
```

lseek

■ Summary

include <io.h> Required only for function declarations

```
long lseek(handle, offset, origin);  
int handle;                                      Handle referring to open file  
long offset;                                      Number of bytes from origin  
int origin;                                      Initial position
```

■ Description

The **lseek** function moves the file pointer (if any) associated with *handle* to a new location that is *offset* bytes from the *origin*. The next operation on the file occurs at the new location. The *origin* must be one of the following constants defined in **stdio.h**:

Origin	Definition
SEEK_SET	Beginning of file
SEEK_CUR	Current position of file pointer
SEEK_END	End of file

The **lseek** function can be used to reposition the pointer anywhere in a file. The pointer can also be positioned beyond the end of the file. However, an attempt to position the pointer before the beginning of the file causes an error.

■ Return Value

The **lseek** function returns the offset, in bytes, of the new position from the beginning of the file. A return value of -1L indicates an error, and **errno** is set to one of the following values:

Value	Meaning
EBADF	Invalid file handle
EINVAL	Invalid value for <i>origin</i> , or position specified by <i>offset</i> is before the beginning of the file

On devices incapable of seeking (such as terminals and printers), the return value is undefined.

■ See Also**fseek, tell****■ Example**

```
#include <io.h>
#include <fcntl.h>
#include <stdlib.h>

int fh;
long position;

fh = open("data", O_RDONLY);
.

.

/* 0 offset from beginning */
position = lseek(fh, 0L, SEEK_SET);
if (position == -1L)
    perror("lseek to beginning failed");
.

.

/* find current position */
position = lseek(fh, 0L, SEEK_CUR);
if (position == -1L)
    perror("lseek to current position failed");
.

.

/* go to end of file */
position = lseek(fh, 0L, SEEK_END);
if (position == -1L)
    perror("lseek to end failed");
```

ltoa

■ Summary

include <stdlib.h> Required only for function declarations

```
char ltoa(value, string, radix);
long value;                    Number to be converted
char *string;                String result
int radix;                    Base of value
```

■ Description

The **ltoa** function converts the digits of the given *value* to a null-terminated character string and stores the result in *string*. The *radix* argument specifies the base of *value*; it must be in the range 2 – 36. If *radix* equals 10 and *value* is negative, the first character of the stored string is the minus sign (-).

■ Return Value

The **ltoa** function returns a pointer to *string*. There is no error return.

■ See Also

itoa, ultoa

Note

The space allocated for *string* must be large enough to hold the returned string. The function can return up to 33 bytes.

■ Example

```
#include <stdlib.h>

int radix = 10;
char buffer[20];
char *p;

p = ltoa(-344115L,buffer,radix);      /* p = "-344115" */
```

■ Summary

include <malloc.h> Required only for function declarations

char *malloc(*size*);
unsigned *size*; Bytes in allocated block

■ Description

The **malloc** function allocates a memory block of at least *size* bytes. (The block may be larger than *size* bytes, due to space required for alignment and for maintenance information.)

■ Return Value

The **malloc** function returns a **char** pointer to the allocated space. The storage space pointed to by the return value is guaranteed to be suitably aligned for storage of any type of object. To get a pointer to a type other than **char**, use a type cast on the return value. The return value is **NULL** if there is insufficient memory available.

■ See Also

calloc, free, realloc

■ Example

```
#include <malloc.h>

int *intarray;

/* Allocate space for 20 integers */

intarray = (int *)malloc(20*sizeof(int));
```

matherr

■ Summary

```
# include <math.h>
```

```
int matherr(x);
```

```
struct exception *x;
```

Math exception information

■ Description

The **matherr** function processes errors generated by the functions of the math library. The math functions call **matherr** whenever an error is detected. The user can provide a different definition of the **matherr** function to carry out special error handling.

When an error occurs in a math routine, **matherr** is called with a pointer to the following structure (defined in **math.h**) as an argument:

```
struct exception {  
    int type;  
    char *name;  
    double arg1, arg2, retval;  
};
```

The **type** specifies the type of math error. It will be one of the following values, defined in **math.h**:

Value	Meaning
DOMAIN	Argument domain error
SING	Argument singularity
OVERFLOW	Overflow range error
UNDERFLOW	Underflow range error
TLOSS	Total loss of significance
PLOSS	Partial loss of significance

The structure member **name** is a pointer to a null-terminated string containing the name of the function that caused the error. The structure members **arg1** and **arg2** specify the values that caused the error. (If only one argument is given, it is stored in **arg1**.)

The default return value for the given error is **retval**. You can change this return value; keep in mind that the return value must specify whether or not an error actually occurred. If **matherr** returns 0, an error message is displayed and **errno** is set to an appropriate error value. If **matherr** returns a nonzero value, no error message is displayed and **errno** remains unchanged.

■ Return Value

The **matherr** function should return 0 to indicate an error, and nonzero to indicate successful corrective action.

■ See Also

acos, asin, atan, atan2, bessel, cabs, cos, cosh, exp, hypot, log, pow, sin, sinh, sqrt, tan

■ Example

```
#include <math.h>
#include <string.h>

/* Catches errors in calls to the log or log10 routines. If
 * the error is the result of a negative argument (DOMAIN
 * error), the log or log10 of the absolute value of the
 * argument is returned (rather than the default value, HUGE).
 * The error message is suppressed. If the error is a 0
 * argument, or the error was generated by some other routine,
 * the default actions are taken. */

int matherr(x)
struct exception *x;
{
    if (x->type == DOMAIN) {
        if (strcmp(x->name, "log") == 0) {
            x->retval = log(-(x->arg1));
            return(1);
        }
        else if (strcmp(x->name, "log10") == 0) {
            x->retval = log10(-(x->arg1));
            return(1);
        }
    }
    return(0);                                /* use default actions */
}
```

_memavl

■ Summary

```
# include <malloc.h>           Required only for function declarations  
unsigned int _memavl();
```

■ Description

The **_memavl** function returns the approximate size, in bytes, of the memory available for dynamic memory allocation in the default data segment. This function can be used with **calloc**, **malloc**, or **realloc** in the small and medium memory models, and with **_nmalloc** in all memory models.

■ Return Value

The **_memavl** function returns the size in bytes as an unsigned integer.

■ See Also

calloc, **malloc**, **_free**, **realloc**, **stackavail**

■ Example

```
main( )  
{  
    long *longptr;  
  
    printf("Memory available before malloc = %u\n", _memavl( ));  
    longptr = (long*)malloc(5000*sizeof(long));  
    printf("Memory available after malloc = %u\n", _memavl( ));  
}
```

Sample output:

```
Memory available before malloc = 61383  
Memory available after malloc = 40959
```

■ Summary

```
# include <memory.h>
# include <string.h>
```

Required only for function declarations
Use either **string.h** or **memory.h**

```
char *memccpy(dest, src, c, cnt);
char *dest;
char *src;
int c;
unsigned cnt;
```

Pointer to destination
Pointer to source
Last character to copy
Number of characters

■ Description

The **memccpy** function copies 0 or more bytes of *src* to *dest*, copying up to and including the first occurrence of the character *c* or until *cnt* bytes have been copied, whichever comes first.

■ Return Value

If the character *c* is copied, **memccpy** returns a pointer to the byte in *dest* that immediately follows the character. If *c* is not copied, **memccpy** returns **NULL**.

■ See Also

memchr, **memcmp**, **memcpy**, **memset**

■ Example

```
#include <memory.h>

char buffer[100], source[100];
char *result;
.

.

/*
 * Copy bytes from source to buffer until '\n' is
 ** copied, but not more than 100 bytes:
 */

result = memccpy(buffer, source, '\n', 100);
```

memchr

■ Summary

```
# include <memory.h>
# include <string.h>
```

Required only for function declarations
Use either `string.h` or `memory.h`

```
char *memchr(buf, c, cnt);
char *buf;
int c;
unsigned cnt;
```

Pointer to buffer
Character to copy
Number of characters

■ Description

The `memchr` function searches the first *count* bytes of *buf* for the first occurrence of the character *c*. The search continues until *c* is found or *cnt* bytes have been examined.

■ Return Value

The `memchr` function returns a pointer to the location of *c* in *buf*. It returns `NULL` if *c* is not within the first *cnt* bytes of *buf*.

■ See Also

`memccpy`, `memcmp`, `memcpy`, `memset`

■ Example

```
#include <memory.h>

char buffer[100];
char *result;
.

.

/*
 * Find the first occurrence of 'a' in buffer. If 'a' is
 ** not in the first 100 bytes, return NULL.
 */

result = memchr(buffer, 'a', 100);
```

■ Summary

<code># include <memory.h></code>	Required only for function declarations
<code># include <string.h></code>	Use either <code>string.h</code> or <code>memory.h</code>
<code>int memcmp (buf1, buf2, cnt);</code>	
<code>char *buf1;</code>	First buffer
<code>char *buf2;</code>	Second buffer
<code>unsigned cnt;</code>	Number of characters

■ Description

The `memcmp` function compares the first `cnt` bytes of `buf1` and `buf2` lexicographically and returns a value indicating their relationship, as follows:

Value	Meaning
Less than 0	<code>buf1</code> less than <code>buf2</code>
0	<code>buf1</code> identical to <code>buf2</code>
Greater than 0	<code>buf1</code> greater than <code>buf2</code>

■ Return Value

The `memcmp` function returns an integer value, as described above.

■ See Also

`memccpy`, `memchr`, `memcpy`, `memset`

■ Example

```
#include <memory.h>

char first[100], second[100];
int result;

/* The following statement compares first[ ] and second[ ] to
** see which, if either, is greater. If they are the same in
** the first 100 bytes, they are considered equal. */

result = memcmp(first, second, 100);
```

memcpy

■ Summary

# include <memory.h>	Required only for function declarations
# include <string.h>	Use either string.h or memory.h
char memcpy(<i>dest</i> , <i>src</i> , <i>cnt</i>);	
char * <i>dest</i> ;	Pointer to destination
char * <i>src</i> ;	Pointer to source
unsigned <i>cnt</i> ;	Number of characters

■ Description

The **memcpy** function copies *cnt* bytes of *src* to *dest*. If some regions of *src* and *dest* overlap, **memcpy** ensures that the original *src* bytes in the overlapping region are copied before being overwritten.

■ Return Value

The **memcpy** function returns a pointer to *dest*.

■ See Also

memccpy, **memchr**, **memcmp**, **memset**

■ Example

```
#include <memory.h>

char source[200], destination[200];
.

.

/* Move 200 bytes from source to destination, and
** return a pointer to destination.
*/
memcpy(destination, source, 200);
```

■ Summary

```
# include <memory.h>
# include <string.h>
```

Required only for function declarations
Use either **string.h** or **memory.h**

```
int memicmp (buf1, buf2, cnt);
char *buf1;
char *buf2;
unsigned cnt;
```

First buffer
Second buffer
Number of characters

■ Description

The **memicmp** function compares the first *cnt* bytes of *buf1* and *buf2* lexicographically, without regard to the case of letters in the two buffers, that is, uppercase (capital) and lowercase letters are considered equivalent. The **memicmp** function returns a value indicating the relationship of *buf1* and *buf2*, as follows:

Value	Meaning
Less than 0	<i>buf1</i> less than <i>buf2</i>
0	<i>buf1</i> identical to <i>buf2</i>
Greater than 0	<i>buf1</i> greater than <i>buf2</i>

■ Return Value

The **memicmp** function returns an integer value, as described above.

■ See Also

memccpy, **memchr**, **memcmp**, **memcpy**, **memset**

memicmp

■ Example

```
#include <memory.h>

char first[100], second[100];
int result;

strcpy(first, "Those Who Will Not Learn from History");
strcpy(second, "THOSE WHO WILL NOT LEARN FROM their mistakes");
result = memicmp(first, second, 29);
printf("%d\n", result);
```

Output:

0

■ Summary

```
# include <memory.h>
# include <string.h>
```

Required only for function declarations
Use either **string.h** or **memory.h**

```
char *memset(dest, c, cnt);
char *dest;
int c;
unsigned cnt;
```

Pointer to destination
Character to set
Number of characters

■ Description

The **memset** function sets the first *cnt* bytes of *dest* to the character *c*.

■ Return Value

The **memset** function returns a pointer to *dest*.

■ See Also

memccpy, **memchr**, **memcmp**, **memcpy**

■ Example

```
#include <memory.h>

char buffer[100];

/* Set the first 100 bytes of buffer to zeros.
 */

memset(buffer, '\0', 100);
```

mkdir

■ Summary

include <direct.h> Required only for function declarations

int mkdir(*pathname*); Path name for new directory
char **pathname*;

■ Description

The **mkdir** function creates a new directory with the specified *pathname*. Only one directory can be created at a time, so only the last component of *pathname* can name a new directory.

■ Return Value

The **mkdir** function returns the value 0 if the new directory was created. A return value of -1 indicates an error, and **errno** is set to one of the following values:

Value	Meaning
EACCES	Directory not created. The given name is the name of an existing file, directory, or device.
ENOENT	Path name not found.

■ **See Also**

chdir, rmdir

■ Example

```
#include <direct.h>

int result;

/* The following two statements create two new directories:
** one at the root on drive b:, and one in the "tmp"
** subdirectory of the current working directory. */

result = mkdir("b:/tmp"); /* "b:\\tmp" could also be used */

result = mkdir("tmp/sub"); /* "tmp\\sub" could also be used */
```

■ Summary

include <io.h> Required only for function declarations

char *mktemp(*template*);
char **template*; File-name pattern

■ Description

The **mktemp** function creates a unique file name by modifying the given *template*. The *template* argument has the form

baseXXXXXX

where *base* is the part of the new file name supplied by the user and the Xs are placeholders for the part supplied by **mktemp**; **mktemp** preserves *base* and replaces the six trailing Xs with an alphanumeric character followed by a five-digit value. The five-digit value is a unique number identifying the calling process. The alphanumeric character is 0 ('0') the first time **mktemp** is called with a given *template*.

In subsequent calls from the same process with the same *template*, **mktemp** checks to see if previously returned names have been used to create files. If no file exists for a given name, **mktemp** returns that name. If files exist for all previously returned names, **mktemp** creates a new name by replacing the alphanumeric character in the name with the next available lowercase letter. For example, if the first name returned is `t012345` and this name is used to create a file, the next name returned will be `ta12345`. When creating new names, **mktemp** uses, in order, '0' and the lowercase letters 'a' to 'z'.

■ Return Value

The **mktemp** function returns a pointer to the modified *template*. The return value is **NULL** if the *template* argument is badly formed or no more unique names can be created from the given *template*.

mktemp

■ See Also

fopen, getpid, open

Note

The **mktemp** function generates unique file names but does not create or open files.

■ Example

```
#include <io.h>

char *template = "fnXXXXXX";
char *result;

/* The following statement calls mktemp to generate a unique
** file name:
*/
result = mktemp(template);
```

■ Summary

```
#include <math.h>

double modf(x, intptr);
double x;           Floating-point value
double *intptr;    Pointer to stored integer portion
```

■ Description

The **modf** function breaks down the floating-point value x into fractional and integer parts. The signed fractional portion of x is returned. The integer portion is stored as a floating-point value at *intptr*.

■ Return Value

The **modf** function returns the signed fractional portion of x . There is no error return.

■ See Also

frexp, ldexp

■ Example

```
#include <math.h>

double x, y, n;

x = -14.87654321;
y = modf(x,&n);      /* y = -0.87654321, n = -14.0 */
```

movedata

■ Summary

```
# include <memory.h>      Required only for function declarations
# include <string.h>       Use either string.h or memory.h
```

```
void movedata(srcseg, srcoff, destseg, destoff, nbytes);
int srcseg;                Segment address of source
int srcoff;                Segment offset of source
int destseg;               Segment address of destination
int destoff;               Segment offset of destination
unsigned nbytes;           Number of bytes
```

■ Description

The **movedata** function copies *nbytes* bytes from the source address specified by *srcseg:srcoff* to the destination address specified by *destseg:destoff*.

The **movedata** function is intended to be used to move far data in small- or medium-model programs where segment addresses of data are not implicitly known. In large model programs, the **memcpy** function can be used since segment addresses are implicitly known.

■ Return Value

There is no return value.

■ See Also

memcpy, **segread**, **FP_SEG**



Note

Segment values for the *srcseg* and *destseg* arguments can be obtained by using either the **segread** function or the **FP_SEG** macro.

The **movedata** function does not handle all cases of overlapping moves correctly (overlapping moves occur when part of the destination is the same memory area as part of the source). Overlapping moves are handled correctly in the **memcpy** function.

■ Example

```
#include <memory.h>
#include <dos.h>

char far *src;
char far *dest;
.

.

/*
 * The following statement moves 512 bytes of data from
 ** src to dest:
 */

movedata(FP_SEG(src), FP_OFF(src), FP_SEG(dest),
         FP_OFF(dest), 512);
```

_msize

■ **Summary**

`#include <malloc.h>` Required only for function declarations

`unsigned _msize(ptr);`
`char *ptr;` Pointer to memory block

■ **Description**

The **_msize** function returns the size, in bytes, of the memory block allocated by a call to **calloc**, **malloc**, or **realloc**.

■ **Return Value**

The size in bytes is returned as an unsigned integer.

■ **See Also**

calloc, **_expand**, **malloc**, **realloc**

■ Example

```
#include <stdio.h>
#include <malloc.h>

main( )
{
    long *oldptr;
    unsigned int newsize = 64000;

    oldptr = (long *)malloc(10000*sizeof(long));
    printf("Size of memory block pointed to by oldptr = %u\n",
          _msize(oldptr));

    if (_expand(oldptr,newsize) != NULL)
        printf("expand was able to increase block to %u\n",
               _msize(oldptr));
    else
        printf("expand was able to increase block to only %u\n",
               _msize(oldptr));
}
```

Sample output:

```
Size of memory block pointed to by oldptr = 40000
expand was able to increase block to only 44718
```

_nfree

■ Summary

`# include <malloc.h>` Required only for function declarations

`void _nfree(ptr);`
`char near *ptr;` Pointer to allocated memory block

■ Description

The **_nfree** function deallocates a memory block. The argument *Ptr* points to a memory block previously allocated through a call to **_nmalloc**. The number of bytes freed is the number of bytes specified when the block was allocated. After the call, the freed block is again available for allocation.

■ Return Value

There is no return value.

■ See Also

_nmalloc, free, malloc

Note

Attempting to free an invalid *ptr* (a pointer not allocated with **_nmalloc**) may affect subsequent allocation and cause errors.

■ Example

```
#include <malloc.h>
#include <stdio.h>

char near *alloc;

/* Allocate 100 bytes and then free them.*/

/* Test for valid pointer:*/

if ((alloc = _nmalloc(100)) == NULL)
    printf("unable to allocate memory\n");
else {
    .
    .
    .
    /*Free memory for the heap:*/
    _nfree(alloc);
}
```

_nmalloc

■ Summary

`# include <malloc.h>` Required only for function declarations

`char near *_nmalloc(size);`
`unsigned size;` Bytes in allocated block

■ Description

The `_nmalloc` function allocates a memory block of at least `size` bytes inside the default data segment. (The block may be larger than `size` bytes due to space required for alignment.)

■ Return Value

The `_nmalloc` function returns a near pointer to a `char`. The storage space pointed to by the return value is guaranteed to be suitably aligned for storage of any type of object. To get a pointer to a type other than `char`, use a type cast on the return value. The return value is `NULL` if there is insufficient memory available.

■ See Also

`_nfree`, `_nmsize`, `malloc`, `realloc`

■ Example

```
#include <malloc.h>

int *intarray;
/* Allocate space for 20 integers */
intarray = (int *)_nmalloc(20*sizeof(int));
```

■ Summary

include <malloc.h> Required only for function declarations

unsigned _nmsize(*ptr*);
char near *ptr*; Pointer to memory block

■ Description

The **_nmsize** function returns the size in bytes of the memory block allocated by a call to **_nmalloc**.

■ Return Value

The **_nmsize** function returns the size in bytes as an unsigned integer.

■ See Also

_ffree, _fmalloc, _fmsize, malloc, _msize, _nfree, _nmalloc

■ Example

```
#include <malloc.h>
#include <stdio.h>

main( )
{
    char near *stringarray;

    stringarray = _nmalloc(200*sizeof(char));
    if (stringarray != NULL)
        printf("%u bytes allocated\n", _nmsize(stringarray));
    else
        printf("Allocation request failed.\n");
}
```

onexit

■ Summary

include <stdlib.h> Required only for function declarations

onexit_t onexit(*func*); Pointer type onexit_t defined in stdlib.h
onexit_t *func*;

■ Description

The **onexit** function is passed the address of a function (*func*) to be called when the program terminates normally. Successive calls to **onexit** create a register of functions that are executed “last-in, first-out.” No more than 32 functions can be registered with **onexit**; **onexit** returns the value **NULL** if the number of functions exceeds 32. The functions passed to **onexit** cannot take parameters.

■ Return Value

The **onexit** function returns a pointer to the function if successful, and returns **NULL** if there is no space left to store the function pointer.

■ See Also

exit

■ Example

```
#include <stdlib.h>

main( )
{
    int fn1( ), fn2( ), fn3( ), fn4( );

    onexit(fn1);
    onexit(fn2);
    onexit(fn3);
    onexit(fn4);
    printf("This is executed first.\n");
}

int fn1( )
{
    printf("next.\n");
}

int fn2( )
{
    printf("executed ");
}

int fn3( )
{
    printf("is ");
}

int fn4( )
{
    printf("This ");
}
```

Output:

```
This is executed first.
This is executed next.
```

open

■ Summary

```
# include <fcntl.h>
# include <sys\ types.h>
# include <sys\ stat.h>
# include <io.h>
```

Required only for function declarations

```
int open(pathname, oflag[], pmode[]);
char *pathname; File path name
int oflag; Type of operations allowed
int pmode; Permission setting
```

■ Description

The **open** function opens the file specified by *pathname* and prepares the file for subsequent reading or writing, as defined by *oflag*. The argument *oflag* is an integer expression formed by combining one or more of the following manifest constants, defined in **fcntl.h**. When more than one manifest constant is given, the constants are joined with the bitwise-OR operator (|).

oflag	Meaning
O_APPEND	Reposition the file pointer to the end of the file before every write operation.
O_CREAT	Create and open a new file for writing; this has no effect if the file specified by <i>pathname</i> exists.
O_EXCL	Return an error value if the file specified by <i>pathname</i> exists. Only applies when used with O_CREAT .
O_RDONLY	Open file for reading only; if this flag is given, neither O_RDWR nor O_WRONLY may be given.
O_RDWR	Open file for both reading and writing; if this flag is given, neither O_RDONLY nor O_WRONLY may be given.
O_TRUNC	Open and truncate an existing file to 0 length; the file must have write permission. The contents of the file are destroyed.

O_WRONLY	Open file for writing only; if this flag is given, neither O_RDONLY nor O_RDWR may be given.
O_BINARY	Open file in binary (untranslated) mode. (See fopen for a description of binary mode.)
O_TEXT	Open file in text (translated) mode. (See fopen for a description of text mode.)

Note

O_TRUNC destroys the complete contents of an existing file. Use with care.

The *pmode* argument is required only when **O_CREAT** is specified. If the file exists, *pmode* is ignored. Otherwise, *pmode* specifies the file's permission settings, which are set when the new file is closed for the first time. The *pmode* is an integer expression containing one or both of the manifest constants **S_IWRITE** and **S_IREAD**, defined in **sys\stat.h**. When both constants are given, they are joined with the bitwise-OR operator (**|**). The meaning of the *pmode* argument is as follows:

Value	Meaning
S_IWRITE	Writing permitted
S_IREAD	Reading permitted
S_IREAD S_IWRITE	Reading and writing permitted

If write permission is not given, the file is read only. Under MS-DOS, all files are readable; it is not possible to give write-only permission. Thus the modes **S_IWRITE** and **S_IREAD | S_IWRITE** are equivalent.

The **open** function applies the current file permission mask to *pmode* before setting the permissions (see **umask**).

open

■ Return Value

The **open** function returns a file handle for the opened file. A return value of -1 indicates an error, and **errno** is set to one of the following values:

Value	Meaning
EACCES	Given path name is a directory; or an attempt was made to open a read-only file for writing; or a sharing violation occurred (the file's sharing mode does not allow the specified operations; MS-DOS Version 3.0 or later only).
EEXIST	The O_CREAT and O_EXCL flags are specified but the named file already exists.
EMFILE	No more file handles available (too many open files).
ENOENT	File or path name not found.

■ See Also

access, **chmod**, **close**, **creat**, **dup**, **dup2**, **fopen**, **sopen**, **umask**

■ Example

```
#include <fcntl.h>
#include <sys\types.h>
#include <sys\stat.h>
#include <io.h>
#include <stdlib.h>

main( )
{
    int fh1, fh2;

    fh1 = open("data1", O_RDONLY);
    if (fh1 == -1)
        perror("open failed on input file");

    fh2 = open("data2", O_WRONLY|O_TRUNC|O_CREAT,
               S_IREAD|S_IWRITE);
    if (fh2 == -1)
        perror("open failed on output file");
.
```

outp

■ Summary

```
# include <conio.h>
```

Required only for function declarations

```
int outp(port, value);
```

```
unsigned port;
```

Port number

```
int value;
```

Output value

■ Description

The **outp** function writes the specified *value* to the output port specified by *port*. The *port* argument can be any unsigned integer in the range 0 to 65535; *value* can be any integer in the range 0 to 255.

■ Return Value

The **outp** function returns *value*. There is no error return.

■ See Also

inp

■ Example

```
#include <conio.h>

int port, byte_val;
.

.

/*
 * The following statement outputs a byte to the port
 ** that 'port' is currently set to:
 */

outp(port,byte_val);
```

■ Summary

# include <stdlib.h>	Required only for function declarations
void perror(<i>string</i>);	User-supplied message
int <i>errno</i>;	Error number
int sys_nerr;	Number of system messages
char sys_errlist[sys_nerr];	Array of error messages

■ Description

The **perror** function prints an error message to **stderr**. The *string* argument is printed first, followed by a colon, the system error message for the last library call that produced an error, and a new line.

The actual error number is stored in the variable **errno**, which should be declared at the external level. The system error messages are accessed through the variable **sys_errlist**, which is an array of messages ordered by error number. The **perror** function prints the appropriate error message by using the **errno** value as an index to **sys_errlist**. The value of the variable **sys_nerr** is defined as the maximum number of elements in the **sys_errlist** array.

To produce accurate results, **perror** should be called immediately after a library routine returns with an error. Otherwise, the **errno** value may be overwritten by subsequent calls.

■ Return Value

The **perror** function returns no value.

■ See Also

clearerr, perror, strerror

Note

Under MS-DOS, some of the **errno** values listed in **errno.h** are not used. See Appendix A, "Error Messages," for a list of **errno** values used on MS-DOS and the corresponding error messages. The **perror** function prints an empty string for any **errno** value not used under MS-DOS.

■ Example

```
#include <fcntl.h>
#include <sys\types.h>
#include <sys\stat.h>
#include <io.h>
#include <stdlib.h>

int fh1, fh2;

fh1 = open("data1", O_RDONLY);
if (fh1 == -1)
    perror("open failed on input file");

fh2 = open("data2", O_WRONLY|O_TRUNC|O_CREAT, S_IREAD|S_IWRITE);
if (fh2 == -1)
    perror("open failed on output file");
```

■ Summary

```
#include <math.h>
```

```
double pow(x, y);
```

```
double x;
```

Number to be raised

```
double y;
```

Power of *x*

■ Description

The **pow** function computes *x* raised to the *y*th power.

■ Return Value

The **pow** function returns the value of x^y . If *y* is 0, **pow** returns the value 1. If *x* is 0 and *y* is negative, **pow** sets **errno** to **ERANGE**, and returns **HUGE**. If *x* is negative and *y* is not an integer, the function prints a **DOMAIN** error message to **stderr**, sets **errno** to **EDOM**, and returns 0. If an overflow results, the function sets **errno** to **ERANGE** and returns either positive or negative **HUGE**. No message is printed for overflow or underflow conditions.

■ See Also

exp, log, sqrt

■ Example

```
#include <math.h>

double x = 2.0, y = 3.0, z;
.
.
.
z = pow(x,y); /* z = 8.0 */
```

printf

■ Summary

```
#include <stdio.h>
```

```
int printf(format-string[], argument...);
```

```
char *format-string;
```

Format control

■ Description

The `printf` function formats and prints a series of characters and values to the standard output stream, `stdout`. The *format-string* consists of ordinary characters, escape sequences, and, if there are arguments following the *format-string*, format specifications. Ordinary characters and escape sequences are simply copied to `stdout` in order of their appearance. For example, the line

```
printf("Line one\n\t\tLine two\n");
```

produces the output

Line one

Line two

(For more information on escape sequences, see Section 2.2.4, “Escape Sequences,” in the *Microsoft C Compiler Language Reference*.)

If there are *arguments* following the *format-string*, then the *format-string* must contain format specifications that determine the output format for these *arguments*. Format specifications always begin with a percent sign (%), and are described in greater detail below.

The *format-string* is read left to right. When the first format specification (if any) is encountered, the value of the first *argument* after the *format-string* is converted and output according to the format specification. The second format specification causes the second *argument* to be converted and output, and this continues through the end of the *format-string*. If there are more arguments than there are format specifications, the extra arguments are ignored. The results are undefined if there are not enough arguments for all the format specifications.

A format specification has the following form:

```
%[flags][width].[precision]{F|N|h|l} type
```

Each field of the format specification is a single character or a number signifying a particular format option. The *type* character, which appears after the last optional format field, determines whether the associated argument is interpreted as a character, a string, or a number (see Table R.1). The simplest format specification contains only the percent sign and a *type* character (for example, %s). The optional fields control other aspects of the formatting, as follows:

Field	Description
<i>flags</i>	Justification of output and printing of signs, blanks, decimal points, octal and hexadecimal prefixes (see Table R.2).
<i>width</i>	Minimum number of characters output.
<i>precision</i>	Maximum number of characters printed for all or part of the output field, or minimum number of digits printed for integer values (see Table R.3).
F, N	Prefixes that allow user to override default addressing conventions of memory model being used: F Used in small model to print value that has been declared far N Used in medium, large and huge models for near value F and N should be used only with the s and p <i>type</i> characters, since they are relevant only with arguments that pass a pointer.
h, l	Size of argument expected: h Used as a prefix with the integer types d , i , o , u , x , and X to specify that the argument is a short int l Used as a prefix with d , i , o , u , x , and X types to specify that the argument is a long int ; also used as a prefix with e , E , f , g , or G types to show that the argument is double , rather than float

If a percent sign (%) is followed by a character that has no meaning as a format field, the character is simply copied to **stdout**. For example, to print a percent-sign character, use %%.

printf

Table R.1
printf Type Characters

Character	Argument Type	Output Format
d	Integer	Signed decimal integer
i	Integer	Signed decimal integer
u	Integer	Unsigned decimal integer
o	Integer	Unsigned octal integer
x	Integer	Unsigned hexadecimal integer, using "abcdef"
X	Integer	Unsigned hexadecimal integer, using "ABCDEF"
f	Floating point	Signed value having the form $[-]ddd.dddd$, where ddd is one or more decimal digits. The number of digits before the decimal point depends on the magnitude of the number, and the number of digits after the decimal point depends on the requested precision.
e	Floating point	Signed value having the form $[-]d.dddd \times [sign]ddd$, where d is a single decimal digit, ddd is one or more decimal digits, ddd is exactly three decimal digits, and $sign$ is + or -
E	Floating point	Identical to the "e" format, except that "E" introduces the exponent instead of "e"
g	Floating point	Signed value printed in "f" or "e" format, whichever is more compact for the given value and <i>precision</i> (see below). The "e" format is used only when the exponent of the value is less than -4 or greater than <i>precision</i> . Trailing zeros are truncated and the decimal point appears only if one or more digits follow it.
G	Floating point	Identical to the "g" format, except that "E" introduces the exponent (where appropriate) instead of "e"
c	Character	Single character
s	String	Characters printed up to the first null character ('\0') or until <i>precision</i> is reached

Table R.1 (*continued*)

Character	Argument Type	Output Format
n	Pointer to integer	Number of characters successfully written so far to the <i>stream</i> or buffer; this value is stored in the integer whose address is given as the argument
p	Far pointer	Prints the address pointed to by the argument in the form <i>xxxx:yyyy</i> , where <i>xxxx</i> is the segment and <i>yyyy</i> is the offset, and the digits <i>x</i> and <i>y</i> are uppercase hexadecimal digits; %Np prints only the offset of the address, <i>yyyy</i> . Since %p expects a pointer to a far value, pointer arguments to p must be cast to far in small-model programs.

Table R.2
printf Flag Characters

Flag ^a	Meaning	Default
-	Left justify the result within the field <i>width</i>	Right justify
+	Prefix the output value with a sign (+ or -) if the output value is of a signed type	Sign appears only for negative signed values (-).
blank (' ')	Prefix the output value with a blank if the output value is signed and positive; the "+" flag overrides the blank flag if both appear, and a positive signed value will be output with a sign.	No blank
#	When used with the o, x, or X format, the "#" flag prefixes any nonzero output value with 0, 0x, or 0X, respectively	No prefix

printf

Table R.2 (continued)

Flag ^a	Meaning	Default
	When used with the e, E, or f format, the “#” flag forces the output value to contain a decimal point in all cases	Decimal point appears only if digits follow it
	When used with the g or G format, the “#” flag forces the output value to contain a decimal point in all cases and prevents the truncation of trailing zeros	Decimal point appears only if digits follow it Trailing zeros are truncated.
	Ignored when used with c, d, i, u, or s	

^a More than one *flag* can appear in a format specification.

The *width* is a non-negative decimal integer controlling the minimum number of characters printed. If the number of characters in the output value is less than the specified *width*, blanks are added on the left or the right (depending on whether the “-” flag is specified) until the minimum width is reached. If *width* is prefixed with a 0, zeros are added until the minimum width is reached (not useful for left-justified numbers).

The *width* specification never causes a value to be truncated; if the number of characters in the output value is greater than the specified *width*, or *width* is not given, all characters of the value are printed (subject to the *precision* specification).

The *width* specification may be an asterisk (*), in which case an argument from the argument list supplies the value. The *width* argument must precede the value being formatted in the argument list.

The *precision* specification is a non-negative decimal integer preceded by a period (.), which specifies the number of characters to be printed, or the number of decimal places. Unlike the *width* specification, the *precision* can cause truncation of the output value, or rounding in the case of a floating-point value.

The *precision* specification may be an asterisk (*), in which case an argument from the argument list supplies the value. The *precision* argument must precede the value being formatted in the argument list.

The interpretation of the *precision* value, and the default when *precision* is omitted, depend on the *type*, as shown in Table R.3.

Table R.3
How printf Precision Values Affect Type

Type	Meaning	Default
d i u o x X	The <i>precision</i> specifies the minimum number of digits to be printed. If the number of digits in the argument is less than <i>precision</i> , the output value is padded on the left with zeros. The value is not truncated when the number of digits exceeds <i>precision</i> .	If <i>precision</i> is 0 or omitted entirely, or if the period (.) appears without a number following it, the <i>precision</i> is set to 1.
e E f	The <i>precision</i> specifies the number of digits to be printed after the decimal point. The last printed digit is rounded.	Default <i>precision</i> is six; if <i>precision</i> is 0 or the period (.) appears without a number following it, no decimal point is printed.
g G c s	The <i>precision</i> specifies the maximum number of significant digits printed. No effect The <i>precision</i> specifies the maximum number of characters to be printed. Characters in excess of <i>precision</i> are not printed.	All significant digits are printed. Character printed Characters are printed until a null character is encountered.

■ Return Value

The **printf** function returns the number of characters printed.

■ See Also

fprintf, **scanf**, **sprintf**, **vfprintf**, **vprintf**, **vsprintf**

printf

■ Example

```
main( )          /* Format and print various data. */
{
    char ch = 'h', *string = "computer";
    int count = 234, *ptr, hex = 0x10, oct = 010, dec = 10;
    double fp = 251.7366;

    printf("%d    %+d    %06d    %X    %x    %o\n\n",
           count, count, count, count, count, count);

    printf("1234567890123%n45678901234567890\n\n", &count);
    printf("Value of count should be 13; count = %d\n\n",
           count);

    printf("%10c%5c\n\n", ch, ch);

    printf("%25s\n%25.4s\n", string, string);

    printf("%f    %.2f    %e    %E\n\n", fp, fp, fp, fp);

    printf("%i    %i    %i\n\n", hex, oct, dec);

    ptr = &count;
    printf("%Np    %p    %Fp\n",
           ptr, (int far *) ptr, (int far *) ptr);
}
```

Output:

```
234      +234      000234      EA      ea      352
123456789012345678901234567890
Value of count should be 13; count = 13
h      h
computer
comp
251.736600      251.74      2.517366e+002      2.517366E+002
16      8      10
127A      1328:127A      1328:127A
```

■ Summary

```
# include <stdio.h>
```

int putc(<i>c</i> , <i>stream</i>);	Write a character to <i>stream</i>
int <i>c</i> ;	Character to be written
FILE * <i>stream</i> ;	Pointer to file structure

int putchar(<i>c</i>);	Write a character to stdout
int <i>c</i> ;	Character to be written

■ Description

The **putc** routine writes the single character *c* to the output *stream* at the current position. The **putchar** routine is identical to **putc(*c*, stdout)**.

■ Return Value

The **putc** and **putchar** routines return the character written. A return value of **EOF** indicates an error. Since the **EOF** value is a legitimate integer value, the **ferror** function should be used to verify that an error occurred.

■ See Also

fputc, fputchar, getc, getchar

Note

The **putc** and **putchar** routines are identical to **fputc** and **fputchar**, but are macros, not functions.

putc – putchar

■ Example

```
#include <stdio.h>

FILE *stream;
char buffer[81];
int i, ch;
.

.

/*
 * The following statements write a buffer to
 * a stream:
 */

for (i = 0; (i < 81) && ((ch = putc(buffer[i], stream)) != EOF);)
    ++i;

/* Note that the body of the for statement is null, since
 * the write operation is carried out in the test expression.
 */
```

■ Summary

```
# include <conio.h>
```

Required only for function declarations

```
void putch(c)
```

```
int c;
```

Character to be output

■ Description

The **putch** function writes the character *c* directly to the console.

■ Return Value

There is no return value.

■ See Also

cprintf, getch, getche

■ Example

```
#include <conio.h>

/* The following example shows how the getche function
** could be defined using putch and getch:
*/

int getche( )
{
    int ch;

    ch = getch( );
    putch(ch);
    return(ch);
}
```

putenv

■ Summary

`# include <stdlib.h>` Required only for function declarations

`int putenv(envstring);`
`char *envstring;` Environment string definition

■ Description

The **putenv** function adds new environment variables or modifies the values of existing environment variables. Environment variables define the environment in which a process executes (for example, the default search path for libraries to be linked with a program).

The *envstring* argument must be a pointer to a string with the form

varname=*string*

where *varname* is the name of the environment variable to be added or modified and *string* is the variable's value. If *varname* is already part of the environment, it is replaced by *string*; otherwise, the new *string* is added to the environment. A variable can be set to an empty value by specifying an empty *string*.

Do not free a pointer to an environment entry while the environment entry is still in use, or the environment variable will point into freed space. A similar problem can occur if you pass a pointer to a local variable to **putenv**, then exit the function in which the variable is declared.

■ Return Value

The **putenv** function returns 0 if it is successful. A return value of -1 indicates an error.

■ See Also

getenv

Note

The **getenv** and **putenv** functions use the global variable **environ** to access the environment table. The **putenv** function may change the value of **environ**, thus invalidating the “envp” argument to the “main” function.

■ Example

```
#include <stdlib.h>
#include <stdio.h>
#include <process.h>

/* Attempt to change an environment variable. */

if (putenv("PATH=a:\\bin;b:\\tmp") == -1) {
    printf("putenv failed -- out of memory");
    exit(1);
}
```

puts

■ Summary

```
#include <stdio.h>

int puts(string);
char *string;           String to be output
```

■ Description

The **puts** function writes the given *string* to the standard output stream **stdout**, replacing the *string*'s terminating null character ('\0') with a new-line character ('\n') in the output stream.

■ Return Value

The **puts** function returns the last character written, which is always the new-line character ('\n'). A return value of **EOF** indicates an error.

■ See Also

fputs, **gets**

■ Example

```
#include <stdio.h>

int result;

/* The following statement writes a prompt to stdout: */
result = puts("insert data disk and strike any key");
```

■ Summary

```
# include <stdio.h>

int putw(binint, stream);
int binint;
FILE *stream;
```

Binary integer to be output
Pointer to file structure

■ Description

The **putw** function writes a binary value of type **int** to the current position of the specified *stream*. The **putw** function does not affect the alignment of items in the stream, nor does it assume any special alignment.

■ Return Value

The **putw** function returns the value written. A return value of **EOF** may indicate an error. Since **EOF** is also a legitimate integer value, **ferror** should be used to verify an error.

■ See Also

getw

Note

The **putw** function is provided primarily for compatibility with previous libraries. Note that portability problems may occur with **putw**, since the size of an **int** and ordering of bytes within an **int** differ across systems.

putw

■ Example

```
#include <stdio.h>
#include <stdlib.h>

FILE *stream;
.

.

/* The following statement writes a word to a stream
** and checks for an error:
*/
putw(0345, stream);

if (ferror(stream)) {
    fprintf(stderr, "putw failed\n");
    clearerr(stream);
}
```

■ Summary

include <search.h> Required only for function declarations

```
void qsort(base, num, width, compare);
char *base;
unsigned num, width;
int (*compare)();
```

■ Description

The **qsort** function implements a quick-sort algorithm to sort an array of *num* elements, each of *width* bytes in size. The argument *base* is a pointer to the base of the array to be sorted. The **qsort** function overwrites this array with the sorted elements.

The argument *compare* is a pointer to a user-supplied routine that compares two array elements and returns a value specifying their relationship. The **qsort** function will call the *compare* routine one or more times during the sort, passing pointers to two array elements on each call. The routine must compare the elements, then return one of the following values:

Value	Meaning
Less than 0	<i>element1</i> less than <i>element2</i>
0	<i>element1</i> equivalent to <i>element2</i>
Greater than 0	<i>element1</i> greater than <i>element2</i>

■ Return Value

There is no return value.

■ See Also

bsearch, **lsearch**

qsort

■ Example

```
#include <search.h>
#include <string.h>
#include <stdio.h>

int compare( ); /* must declare as a function */

main (argc, argv)
    int argc;
    char **argv;

{
    .
    .

    /* The following statement sorts the command line
     * arguments in lexical order:
    */

qsort((char *)argv,argc,sizeof(char *),compare);
for (i = 0; i < argc; ++i)
    printf("%s\n", argv[i]);
.

.

}

int compare (arg1, arg2)
char **arg1, **arg2;

{
    return(strcmp(*arg1,*arg2));
}
```

■ Summary

```
#include <stdlib.h>           Required only for function declarations  
int rand();
```

■ Description

The **rand** function returns a pseudorandom integer in the range 0 to 32767. The **srand** routine can be used before calling **rand** to set a random starting point.

■ Return Value

The **rand** function returns a pseudorandom number as described above. There is no error return.

■ See Also

srand

■ Example

```
#include <stdlib.h>  
#include <stdio.h>  
  
int x;  
  
/* Print the first 20 random numbers generated.  
 */  
  
for (x = 1; x <= 20; x++)  
    printf("iteration %d, rand=%d\n", x, rand());
```

read

■ Summary

include <io.h> Required only for function declarations

```
int read(handle, buffer, count);
int handle; Handle referring to open file
char *buffer; Storage location for data
unsigned int count; Maximum number of bytes
```

■ Description

The **read** function attempts to read *count* bytes from the file associated with *handle* into *buffer*. The read operation begins at the current position of the file pointer (if any) associated with the given file. After the read operation, the file pointer points to the next unread character.

■ Return Value

The **read** function returns the number of bytes actually read, which may be less than *count* if there are fewer than *count* bytes left in the file or if the file was opened in text mode (see below). The return value 0 indicates an attempt to read at end-of-file. The return value -1 indicates an error, and **errno** is set to the following value:

Value	Meaning
EBADF	The given <i>handle</i> is invalid; or the file is not open for reading; or the file is locked (MS-DOS versions 3.0 or later only).

If you are reading more than 32K (the maximum size for type **int**) from a file, the return value should be of type **unsigned int**. (See the example that follows.) However, the maximum number of bytes that can be read from a file is 65534, since 65535 (or 0xFFFF) is indistinguishable from -1, and therefore would return an error.

If the file was opened in text mode, the return value may not correspond to the number of bytes actually read. When text mode is in effect, each carriage-return-line-feed pair (CR-LF) is replaced with a single line-feed character (LF). Only the single line-feed character is counted in the return value. The replacement does not affect the file pointer.

■ See Also**creat, fread, open, write***Note*

Under MS-DOS, when files are opened in text mode, a character is treated as an end-of-file indicator. When the CONTROL-Z is encountered, the read terminates, and the next read returns 0 bytes. The file must be closed to clear the end-of-file indicator.

■ Example

```
#include <io.h>
#include <stdio.h>
#include <fcntl.h>

char buffer[60000];

main( )
{
    int fh;
    unsigned int nbytes = 60000, bytesread;

    if ((fh = open("c:/data/conf.dat", O_RDONLY)) == -1) {
        perror("open failed on input file");
        exit(1);
    }
    if ((bytesread = read(fh,buffer,nbytes)) == -1)
        perror("");
    else
        printf("Read %u bytes from file\n", bytesread);
    .
    .
}
```

realloc

■ Summary

# include <malloc.h>	Required only for function declarations
char *realloc(ptr, size);	
char *ptr;	Pointer to previously allocated memory block
unsigned size;	New size in bytes

■ Description

The **realloc** function changes the size of a previously allocated memory block. The *ptr* argument points to the beginning of the block. The *size* argument gives the new size of the block, in bytes. The contents of the block are unchanged up to the shorter of the new and old sizes.

The *ptr* argument may also point to a block that has been freed, as long as there has been no intervening call to **calloc**, **malloc**, or **realloc** since the block was freed.

■ Return Value

The **realloc** function returns a **char** pointer to the reallocated memory block. The block may be moved when its size is changed; therefore, the *ptr* argument to **realloc** is not necessarily the same as the return value.

The return value is **NULL** if there is insufficient memory available to expand the block to the given size. The original block is freed when this occurs.

The storage space pointed to by the return value is guaranteed to be suitably aligned for storage of any type of object. To get a pointer to a type other than **char**, use a type cast on the return value.

■ See Also

calloc, **free**, **malloc**, **realloc**

■ Example

```
#include <malloc.h>
#include <stdio.h>

char *alloc;

/* Get enough space for 50 characters.
 */

alloc = malloc(50*sizeof(char));
.

.

/* Reallocate block to hold 100 characters */

if (alloc != NULL)
    alloc = realloc(alloc,100*sizeof(char));
```

remove

■ Summary

```
# include <io.h>
# include <stdio.h>
```

Required only for function declarations
Use either **io.h** or **stdio.h**

```
int remove(pathname);
char *pathname;
```

Path name of file to be removed



■ Description

The **remove** function deletes the file specified by *pathname*.

■ Return Value

The **remove** function returns the value 0 if the file is successfully deleted. A return value of -1 indicates an error, and **errno** is set to one of the following values:

Value	Meaning
EACCES	Path name specifies a directory or a read-only file.
ENOENT	File or path name not found.



■ See Also

close, **unlink**

■ Example

```
#include <io.h>
#include <stdlib.h>

int result;

result = remove("tmpfile");
if (result == -1)
    perror("couldn't delete tmpfile");
```



■ Summary

```
# include <io.h>           Required only for function declarations  
# include <stdio.h>         Use either io.h or stdio.h  
  
int rename(oldname, newname);  
char *oldname;             Pointer to old name  
char *newname;             Pointer to new name
```

■ Description

The **rename** function renames the file or directory specified by *oldname* to the name given by *newname*. The *oldname* must specify the path name of an existing file or directory. The *newname* must not specify the name of an existing file or directory.

The **rename** function can be used to move a file from one directory to another by giving a different path name in the *newname* argument. However, files cannot be moved from one device to another (for example, from Drive A to Drive B). Directories can only be renamed, not moved.

■ Return Value

The **rename** function returns 0 if it is successful. On an error, it returns a nonzero value and sets **errno** to one of the following values:

Value	Meaning
EACCES	File or directory specified by <i>newname</i> already exists or could not be created (invalid path); or <i>oldname</i> is a directory and <i>newname</i> specifies a different path.
ENOENT	File or path name specified by <i>oldname</i> not found.
EXDEV	Attempt to move a file to a different device.

rename

■ See Also

creat, fopen, open

Note

Note that the order of the arguments in **rename** in Microsoft C 4.0 is the opposite of their order in earlier versions. This change was made to conform to the developing ANSI C standard.

■ Example

```
#include <io.h>

int result;

/* The following statement changes the file "input" to
** have the name "data":
*/
result = rename("input", "data");
```

■ Summary

```
# include <stdio.h>
```

```
void rewind(stream);
```

```
FILE *stream;                   Pointer to file structure
```

■ Description

The **rewind** function repositions the file pointer associated with *stream* to the beginning of the file. A call to **rewind** is equivalent to

```
fseek(stream, 0L, SEEK_SET);
```

except that **rewind** clears the end-of-file and error indicators for the stream, and **fseek** does not; also, **fseek** returns a value that indicates whether or not the pointer was successfully moved, but **rewind** does not return any value.

■ Return Value

There is no return value.

■ See Also

fseek, **ftell**

■ Example

```
#include <stdio.h>

FILE *stream;
int data1, data2;
.

.

fprintf(stream, "%d %d", data1, data2); /* Place data in file */

rewind(stream);                                   /* Now read data file */
fscanf(stream, "%d", &data1);
```

rmdir

■ Summary

include <direct.h> Required only for function declarations

int rmdir(*pathname*);

char **pathname*;

Path name of directory to be removed

■ Description

The **rmdir** function deletes the directory specified by *pathname*. The directory must be empty, and it must not be the current working directory or the root directory.

■ Return Value

The **rmdir** function returns the value 0 if the directory is successfully deleted. A return value of -1 indicates an error, and **errno** is set to one of the following values:

Value	Meaning
EACCES	The given path name is not a directory; or the directory is not empty; or the directory is the current working directory or root directory.
ENOENT	Path name not found.

■ See Also

chdir, **mkdir**

■ Example

```
#include <direct.h>

int result1, result2;

/* The following statements delete two directories:
** one at the root, and one in the current working
** directory. */
result1 = rmdir("/data1");
result2 = rmdir("data2");
```

■ Summary

```
# include <stdio.h>
int rmtmp( );
```

■ Description

The **rmtmp** function is used to clean up all the temporary files in the current directory; **rmtmp** removes only those files created by **tmpfile**.

The **rmtmp** function should be used only in the same directory in which the temporary files were created.

■ Return Value

The **rmtmp** function returns the number of temporary files closed and deleted.

■ See Also

flushall, **tmpfile**, **tmpnam**

■ Example

```
#include <stdio.h>

main( )
{
    int numdeleted;
    .
    .
    .
    if ((stream = tmpfile( )) == NULL)
        perror("Couldn't open new temporary file");
    .
    .
    .
    numdeleted = rmtmp( );
    printf("Number of files closed and deleted in\
current directory = %d\n", numdeleted);
}
```

sbrk

■ Summary

`# include <malloc.h>` Required only for function declarations

`char *sbrk(incr);` Number of bytes added or subtracted
`int incr;`

■ Description

The **sbrk** function resets the break value for the calling process. The break value is the address of the first byte of unallocated memory. The **sbrk** function adds *incr* bytes to the break value; the size of the process's allocated memory is adjusted accordingly. Note that *incr* may be negative, in which case the amount of allocated space is decreased by *incr* bytes.

■ Return Value

The **sbrk** function returns the old break value. A return value of -1 indicates an error, and **errno** is set to **ENOMEM**, indicating that insufficient memory was available.

■ See Also

calloc, **free**, **malloc**, **realloc**

Important

In compact-, large-, and huge-model programs, **sbrk** fails and returns -1. Use **malloc** for allocation requests in large-model programs.

■ Example

```
#include <malloc.h>
#include <stdio.h>

/* Allocate 100 bytes of memory.
 */

char *alloc;
alloc = sbrk(100);

/*
 */

/* Now reduce allocated memory to 60 bytes.
 */
if (alloc != (char)-1)
    sbrk(-40);
```

scanf

■ Summary

```
# include <stdio.h>
```

```
int scanf(format-string[], argument...));
```

```
char *format-string;
```

Format control

■ Description

The **scanf** function reads data from the standard input stream **stdin** into the locations given by *arguments*. Each *argument* must be a pointer to a variable with a type that corresponds to a type specifier in the *format-string*. The *format-string* controls the interpretation of the input fields. The *format-string* can contain one or more of the following:

- White-space characters (blank (' '), tab ('\t'), or new line ('\n')). A white-space character causes **scanf** to read, but not store, all consecutive white-space characters in the input up to the next non-white-space character. One white-space character in the *format-string* matches any number (including 0) and combination of white-space characters in the input.
- Non-white-space characters, except for the percent-sign character (%). A non-white-space character causes **scanf** to read, but not store, a matching non-white-space character. If the next character in **stdin** does not match, **scanf** terminates.
- Format specifications, introduced by the percent sign (%). A format specification causes **scanf** to read and convert characters in the input into values of a specified type. The value is assigned to an argument in the argument list.

The *format-string* is read from left to right. Characters outside format specifications are expected to match the sequence of characters in **stdin**; the matched characters in **stdin** are scanned but not stored. If a character in **stdin** conflicts with the *format-string*, **scanf** terminates. The conflicting character is left in **stdin** as if it had not been read.

When the first format specification is encountered, the value of the first input field is converted according to the format specification and stored in the location specified by the first *argument*. The second format specification causes the second input field to be converted and stored in the second *argument*, and so on through the end of the *format-string*.

An input field is defined as all characters up to the first white-space character (space, tab, or new line), or up to the first character that cannot be converted according to the format specification, or until the field *width*, if specified, is reached, whichever comes first. If there are too many arguments for the given format specifications, the extra arguments are ignored. The results are undefined if there are not enough arguments for the given format specifications.

A format specification has the following form:

$\%[*][width][\{F|N\}][\{h|l\}]type$

Each field of the format specification is a single character or a number signifying a particular format option. The *type* character, which appears after the last optional format field, determines whether the input field is interpreted as a character, a string, or a number. The simplest format specification contains only the percent sign and a *type* character (for example, `%s`).

Each field of the format specification is discussed in detail below. If a percent sign (`%`) is followed by a character that has no meaning as a format-control character, that character and the following characters (up to the next percent sign) are treated as an ordinary sequence of characters — that is, a sequence of characters that must match the input. For example, to specify that a percent sign character is to be input, use `%%`.

An asterisk (`*`) following the percent sign suppresses assignment of the next input field, which is interpreted as a field of the specified *type*. The field is scanned but not stored.

The *width* is a positive decimal integer controlling the maximum number of characters to be read from `stdin`. No more than *width* characters are converted and stored at the corresponding *argument*. Fewer than *width* characters may be read if a white-space character (space, tab, or new line) or a character that cannot be converted according to the given format occurs before *width* is reached.

The optional **F** and **N** prefixes allow the user to override the default addressing conventions of the memory model being used. **F** should be prefixed to an *argument* pointing to a **far** object, while **N** should be prefixed to an *argument* pointing to a **near** object.

The optional prefix **l** indicates that the **long** version of the following *type* is to be used, while the prefix **h** indicates that the **short** version is to be used. The corresponding *argument* should point to a **long** or **double** object (with the **l** character) or a **short** object (with the **h** character). The **l** and **h** modifiers can be used with the **d**, **i**, **o**, **x**, and **u** *type* characters. The **l**

scanf

modifier can also be used with the **e** and **f** *type* characters. The **l** and **h** modifiers are ignored if specified for any other *type*.

The *type* characters and their meanings are described in Table R.4.

Table R.4
scanf Type Characters

Character	Type of Input Expected	Type of Argument
d	Decimal integer	Pointer to int
D	Decimal integer	Pointer to long
o	Octal integer	Pointer to int
O	Octal integer	Pointer to long
x	Hexadecimal integer	Pointer to int
X	Hexadecimal integer	Pointer to long
i	Decimal, hexadecimal or octal integer	Pointer to int
I	Decimal, hexadecimal or octal integer	Pointer to long
u	Unsigned decimal integer	Pointer to unsigned int
U	Unsigned decimal integer	Pointer to unsigned long
e	Floating-point value consisting of an optional sign (+ or -), a series of one or more decimal digits possibly containing a decimal point, and an optional exponent ("e" or "E") followed by an optionally signed integer value	Pointer to float
f		
c	Character. White-space characters that are ordinarily skipped are read when c is specified; to read the next non-white-space character, use %ls.	Pointer to char
s	String	Pointer to character array large enough for input field plus a terminating null character ('\0'), which is automatically appended

Table R.4 (continued)

Character	Type of Input Expected	Type of Argument
n	No input read from <i>stream</i> or buffer	Pointer to int, into which is stored the number of characters successfully read from the <i>stream</i> or buffer up to that point in the current call to scanf
p	Value in the form xxxx:yyyy, where the digits x and y are uppercase hexadecimal digits	Pointer to far data item

To read strings not delimited by space characters, a set of characters in brackets ([]) can be substituted for the s (string) type character. The corresponding input field is read up to the first character that does not appear in the bracketed character set. If the first character in the set is a caret (^), the effect is reversed: the input field is read up to the first character that *does* appear in the rest of the character set.

To store a string without storing a terminating null character ('\0'), use the specification %nc, where n is a decimal integer. In this case, the c type character indicates that the argument is a pointer to a character array. The next n characters are read from the input stream into the specified location, and no null character ('\0') is appended.

The **scanf** function scans each input field, character by character. It may stop reading a particular input field before it reaches a space character for a variety of reasons: the specified width has been reached; the next character cannot be converted as specified; the next character conflicts with a character in the control string that it is supposed to match; or the next character fails to appear (or does appear) in a given character set. When this occurs, the next input field is considered to begin at the first unread character. The conflicting character, if there was one, is considered unread and is the first character of the next input field or the first character in subsequent read operations on **stdin**.

scanf

■ Return Value

The **scanf** function returns the number of fields that were successfully converted and assigned. The return value does not include fields that were read but not assigned.

The return value is **EOF** for an attempt to read at end-of-file. A return value of 0 means that no fields were assigned.

■ See Also

fscanf, printf, sscanf, vfprintf, vprintf, vsprintf

■ Examples

```
*****Example 1*****
#include <stdio.h>

int i;
float fp;
char c, s[81];

scanf("%d %f %c %s",&i, &fp, &c, s); /* Input various data */
```

```
*****Example 2*****  
#include <stdio.h>  
  
main() /* Convert hexadecimal or octal integer  
** to a decimal integer  
*/  
{  
    int numassigned, val;  
  
    printf("Enter hexadecimal or octal #, or 00 to quit:\n");  
    do {  
        printf("# = ");  
        numassigned = scanf("%i", &val);  
        printf("Decimal # = %i\n", val);  
    }  
    while (val && numassigned); /* Loop ends if input  
** value is 00, or if  
** scanf is unable to  
** assign field  
*/  
}
```

Sample output:

```
Enter hexadecimal or octal #, or 00 to quit:  
# = 0xf  
Decimal # = 15  
# = 0100  
Decimal # = 64  
# = 00  
Decimal # = 0
```

segread

■ Summary

```
# include <dos.h>
```

```
void segread(segregs);  
struct SREGS *segregs;
```

Segment register values

■ Description

The **segread** function fills the structure pointed to by *segregs* with the current contents of the segment registers. This function is intended to be used with the **intdosx** and **int86x** functions to retrieve segment register values for later use.

■ Return Value

There is no return value.

■ See Also

intdosx, **int86x**, **FP_SEG**

■ Example

```
#include <dos.h>  
  
struct SREGS segregs;  
unsigned int cs, ds, es, ss;  
  
/* The following statements get the current values of  
** the segment registers:  
*/  
  
segread(&segregs);  
cs = segregs.cs;  
ds = segregs.ds;  
es = segregs.es;  
ss = segregs.ss;
```

■ Summary

```
# include <stdio.h>
```

```
void setbuf(stream, buffer);
```

```
FILE *stream; Pointer to file structure
```

```
char *buffer; User-allocated buffer
```

■ Description

The **setbuf** function allows the user to control buffering for the specified *stream*. The argument *stream* must refer to an open file. If the *buffer* argument is **NULL**, the *stream* is unbuffered. If not, the *buffer* must point to a character array of length **BUFSIZ**, where **BUFSIZ** is the buffer size as defined in **stdio.h**. The user-specified *buffer* is used for I/O buffering instead of the default system-allocated buffer for the given *stream*.

The **stderr** and **stdataux** streams are unbuffered by default but may be assigned buffers with **setbuf**.

■ Return Value

There is no return value.

■ See Also

fflush, **fopen**, **fclose**

■ Example

```
#include <stdio.h>

char buf[BUFSIZ];
FILE *stream1, *stream2;

stream1 = fopen("data1", "r");
stream2 = fopen("data2", "w");

setbuf(stream1,buf); /* stream1 uses user-assigned buffer */
setbuf(stream2,NULL); /* stream2 is unbuffered */
```

setjmp

■ Summary

```
# include <setjmp.h>
```

```
int setjmp(env);  
jmp_buf env; Variable in which environment is stored
```

■ Description

The **setjmp** function saves a stack environment that can subsequently be restored using **longjmp**. **Setjmp** and **longjmp** provide a way to execute a nonlocal goto and are typically used to pass execution control to error-handling or recovery code in a previously called routine without using the normal calling or return conventions.

A call to **setjmp** causes the current stack environment to be saved in *env*. A subsequent call to **longjmp** restores the saved environment and returns control to the point just after the corresponding **setjmp** call. The values of all variables (except register variables) accessible to the routine receiving control contain the values they had when **longjmp** was called. The values of register variables are unpredictable.

■ Return Value

The **setjmp** function returns the value 0 after saving the stack environment. If **setjmp** returns as a result of a **longjmp** call, it returns the *value* argument of **longjmp**. There is no error return.

■ See Also

longjmp

Warning

The values of register variables in the routine calling **setjmp** may not be restored to the proper values after a **longjmp** call is executed.

■ Example

```
#include <stdio.h>
#include <setjmp.h>

jmp_buf mark;

main( )
{
    if (setjmp(mark) != 0) {
        printf("longjmp has been called\n");
        recover();
        exit(1);
    }
    printf("setjmp has been called\n");
    .
    .
    .
    p();
    .
    .
    .
}

p( )
{
    int error = 0;
    .
    .
    .
    if (error != 0)
        longjmp(mark, -1);
    .
    .
    .
}

recover( )
{
    /* ensure that data files won't be corrupted by
     * exiting the program.
    */
    .
    .
    .
}
```

setmode

■ Summary

```
# include <fcntl.h>
# include <io.h>      Required only for function declarations
```

```
int setmode(handle, mode);
int handle;           File handle
int mode;            New translation mode
```

■ Description

The **setmode** function sets the translation mode of the file given by *handle* to *mode*. The *mode* must be one of the following manifest constants:

Manifest Constant	Meaning
O_TEXT	Set text (translated) mode. Carriage-return–line-feed combinations (CR-LF) are translated into a single line feed (LF) on input. Line-feed characters are translated into carriage-return–line-feed combinations on output.
O_BINARY	Set binary (untranslated) mode. The above translations are suppressed.

The **setmode** function is typically used to modify the default translation mode of **stdin**, **stdout**, **stderr**, **stdaux**, and **stdprn**, but can be used on any file.

■ Return Value

If successful, **setmode** returns the previous translation mode. A return value of -1 indicates an error, and **errno** is set to one of the following values:

Value	Meaning
EBADF	Invalid file handle
EINVAL	Invalid <i>mode</i> argument (neither O_TEXT nor O_BINARY)

■ **See Also**

creat, fopen, open

■ **Example**

```
#include <stdio.h>
#include <fcntl.h>
#include <io.h>

int result;

/* The following statement sets stdin to be binary
** (initially it is text):
*/
result = setmode(fileno(stdin), O_BINARY);
```

setvbuf

■ Summary

```
# include <stdio.h>
```

```
int setvbuf(stream, buf, type, size);
FILE *stream;           Pointer to file structure
char *buf;              User-allocated buffer
int type;               Type of buffer:
                        - _IONBF (no buffer)
                        - _IOFBF (full buffering)
                        - _IOLBF (line buffering)
int size;               Size of buffer
```

■ Description

The **setvbuf** function allows the user to control both buffering and buffer size for the specified *stream*. The *stream* must refer to an open file. The array that *buf* points to is used as the buffer, unless it is **NULL**, in which case the stream is unbuffered. If the stream is buffered, the type specified by *type* is used; the type must be either **_IONBF**, **_IOFBF**, or **_IOLBF**. If *type* is **_IOFBF** or **_IOLBF**, then *size* is used as the size of the buffer. If *type* is **_IONBF**, then the stream is unbuffered, and *size* and *buf* are ignored, as shown by the following:

Type Value	Meaning
_IONBF	No buffer is used, regardless of <i>buf</i> or <i>size</i> .
_IOFBF	Full buffering (unless <i>buf</i> is NULL); that is, use <i>buf</i> as the buffer and <i>size</i> as the size of the buffer.
_IOLBF	Same as _IOFBF .

The legal values for *size* are greater than 0 and less than the maximum integer size.

■ Return value

The return value for **setvbuf** is 0 if successful, and nonzero if an illegal type or buffer size is specified.

■ See Also**setbuf, fflush, fopen, fclose****■ Example**

```
#include <stdio.h>

char buf[1024];
FILE *stream1, *stream2;

main( )
{
    stream1 = fopen("data1", "r");
    stream2 = fopen("data2", "w");
    /* Stream1 will use a user-assigned buffer of 1024 bytes,
     ** while stream2 will be unbuffered.
    */
    if (setvbuf(stream1, buf, _IOFBF, sizeof(buf)) != 0)
        printf("Incorrect type or size of buffer1\n");
    if (setvbuf(stream2, NULL, _IONBF, 0) != 0)
        printf("Incorrect type or size of buffer2\n");
}
```

signal

■ Summary

```
#include <signal.h>
```

```
int (*signal(sig, func)( );
```

```
int sig;
```

Signal value

```
int (*func)( );
```

Function to be executed

■ Description

The **signal** function allows a process to choose one of three ways to handle an interrupt signal from the operating system. The *sig* argument must be one of the manifest constants **SIGINT** or **SIGFPE** defined in **signal.h**. The **SIGINT** manifest constant corresponds to the MS-DOS interrupt signal, INT 23H. **SIGFPE** corresponds to floating-point exceptions that are not masked, such as overflow, division by zero, and invalid operation. The *func* argument must be one of the manifest constants **SIG_DFL** or **SIG_IGN** (also defined in **signal.h**), or a function address. The action taken when the interrupt signal is received depends on the value of *func*, as follows:

Value	Meaning
SIG_IGN	The interrupt signal is ignored. This value should never be given for SIGFPE , since the floating-point state of the process is left undefined.
SIG_DFL	The calling process is terminated and control returns to the MS-DOS command level. All files opened by the process are closed, but buffers are not flushed.
Function address	For SIGINT signals, the function pointed to by <i>func</i> is passed the single argument SIGINT and executed. If the function returns, the calling process resumes execution immediately following the point where it received the interrupt signal. Before the specified function is executed, the value of <i>func</i> is set to SIG_DFL ; the next interrupt signal is treated as described above for SIG_DFL , unless an intervening call to

signal specifies otherwise. This allows the user to reset signals in the called function if desired.

For **SIGFPE**, the function pointed to by *func* is passed two arguments, **SIGFPE** and an integer error subcode, **FPE_xxx**, then executed. (See the include file **float.h** for definitions of the **FPE_xxx** subcodes.) The value of *func* is not reset upon receiving the signal; to recover from floating-point exceptions, use **setjmp** in conjunction with **longjmp**. (See the example under **_fpreset** in this Reference.) If the function returns, the calling process resumes execution with the floating-point state of the process left in an undefined state.

■ Return Value

The **signal** function returns the previous value of *func*. A return value of **-1** indicates an error, and **errno** is set to **EINVAL**, indicating an invalid *sig* value.

■ See Also

abort, **exit**, **_exit**, **_fpreset**, **spawnl**, **spawnle**, **spawnlp**, **spawnrv**,
spawnve, **spawnvp**

Note

Signal settings are not preserved in child processes created by calls to **exec** or **spawn** routines. The signal settings are reset to the default in the child process.

signal

■ Example

```
#include <stdio.h>
#include <signal.h>
#include <stdlib.h>
#include <process.h>

int handler( );

main( )
{
    if (signal(SIGINT,handler) == (int(*)())-1) {
        fprintf(stderr,"couldn't set SIGINT\n");
        abort();
    }
    .
    .
}

int handler( )
{
    char ch;

    printf("terminate processing? ");
    scanf("%1c",&ch);
    if (ch == 'y' || ch == 'Y')
        exit(0);
    signal(SIGINT,handler); /* signal called here so
                           ** next interrupt signal
                           ** sends control to
                           ** handler(), not to OS
                           */
}
```

■ Summary

```
#include <math.h>
```

double sin(<i>x</i>);	Calculate sine of <i>x</i>
double sinh(<i>x</i>);	Calculate hyperbolic sine of <i>x</i>
double <i>x</i> ;	Radians

■ Description

The **sin** and **sinh** functions return the sine and hyperbolic sine of *x*, respectively.

■ Return Value

The **sin** function returns the sine of *x*. If *x* is large, a partial loss of significance in the result may occur. In such cases, **sin** generates a **PLOSS** error, but no message is printed. If *x* is so large that a total loss of significance results, **sin** prints a **TLOSS** error message to **stderr** and returns 0. In both cases, **errno** is set to **ERANGE**.

The **sinh** function returns the hyperbolic sine of *x*. If the result is too large, **sinh** sets **errno** to **ERANGE** and returns the value **HUGE** (positive or negative, depending on the value of *x*).

Error handling can be modified by using the **matherr** routine.

■ See Also

acos, asin, atan, atan2, cos, cosh, tan, tanh

■ Example

```
#include <math.h>

double pi = 3.1415926535, x, y;

x = pi/2;
y = sin(x); /* y is 1.0 */
y = sinh(x); /* y is 2.3 */
```

sopen

■ Summary

```
# include <fcntl.h>
# include <sys\ types.h>
# include <sys\ stat.h>
# include <share.h>
# include <io.h>
```

Required only for function declarations

```
int sopen(pathname, oflag, shflag[], pmode]);
char * pathname;           File path name
int oflag;                Type of operations allowed
int shflag;               Type of sharing allowed
int pmode;                Permission setting
```

■ Description

The **sopen** function opens the file specified by *pathname* and prepares the file for subsequent shared reading or writing, as defined by *oflag* and *shflag*. The integer expression *oflag* is formed by combining one or more of the following manifest constants, defined in **fcntl.h**. When more than one manifest constant is given, the constants are joined with the OR operator (|).

oflag	Meaning
O_APPEND	Reposition the file pointer to the end of the file before every write operation.
O_CREAT	Create and open a new file; this has no effect if the file specified by <i>pathname</i> exists.
O_EXCL	Return an error value if the file specified by <i>pathname</i> exists; only applies when used with O_CREAT .
O_RDONLY	Open file for reading only; if this flag is given, neither O_RDWR nor O_WRONLY may be given.
O_RDWR	Open file for both reading and writing; if this flag is given, neither O_RDONLY nor O_WRONLY may be given.
O_TRUNC	Open and truncate an existing file to 0 bytes in length; the file must have write permission; the contents of the file are destroyed.

O_WRONLY	Open file for writing only; if this flag is given, neither O_RDONLY nor O_RDWR may be given.
O_BINARY	Open file in binary (untranslated) mode. (See fopen for a description of binary mode.)
O_TEXT	Open file in text (translated) mode. (See fopen for a description of text mode.)

Note

O_TRUNC destroys the entire contents of an existing file. Use with care.

The argument *shflag* is a constant expression consisting of one of the following manifest constants, defined in **share.h**. See your MS-DOS documentation for detailed information on sharing modes.

shflag	Meaning
SH_COMPAT	Set compatibility mode
SH_DENYRW	Deny read and write access to file
SH_DENYWR	Deny write access to file
SH_DENYRD	Deny read access to file
SH_DENYNO	Permit read and write access

The *pmode* argument is required only when **O_CREAT** is specified. If the file does not exist, *pmode* specifies the file's permission settings, which are set when the new file is closed for the first time. Otherwise, the *pmode* argument is ignored. The *pmode* argument is an integer expression containing one or both of the manifest constants **S_IWRITE** and **S_IREAD**, defined in **sys\stat.h**. When both constants are given, they are joined with the OR operator (`|`). The meaning of the *pmode* argument is as follows:

sopen

Value	Meaning
S_IWRITE	Writing permitted
S_IREAD	Reading permitted
S_IREAD S_IWRITE	Reading and writing permitted

If write permission is not given, the file is read only. Under MS-DOS, all files are readable; it is not possible to give write-only permission. Thus the modes **S_IWRITE** and **S_IREAD | S_IWRITE** are equivalent.

The **sopen** function applies the current file permission mask to *pmode* before setting the permissions (see **umask**).

■ Return Value

The **sopen** function returns a file handle for the opened file. A return value of -1 indicates an error, and **errno** is set to one of the following values:

Value	Meaning
EACCES	Given path name is a directory; or the file is read only but an open for writing was attempted; or a sharing violation occurred (the file's sharing mode does not allow the specified operations; MS-DOS versions 3.0 or later only).
EEXIST	The O_CREAT and O_EXCL flags are specified, but the named file already exists.
EINVAL	SHARE.COM not installed.
EMFILE	No more file handles available (too many open files).
ENOENT	File or path name not found.

■ See Also

close, **creat**, **fopen**, **open**, **umask**

Note

The **sopen** function should be used only under MS-DOS Version 3.0 or later. Under earlier versions of MS-DOS, the *shflag* argument is ignored.

File sharing modes will not work correctly for buffered files, so do not use **fdopen** to associate a file opened for sharing (or locking) with a stream.

■ Example

```
#include <fcntl.h>
#include <sys\types.h>
#include <sys\stat.h>
#include <share.h>
#include <io.h>

extern unsigned char _osmajor;
int fh;

/* The _osmajor variable is used to test
 * the MS-DOS version number before
 * calling sopen.
 */

if (_osmajor >= 3)
    fh = sopen("data", O_RDWR|O_BINARY, SH_DENYRW);
else
    fh = open("data", O_RDWR|O_BINARY);
```

spawnl – spawnvpe

■ Summary

```
# include <stdio.h>
# include <process.h>

int spawnl(modeflag, pathname, arg0, arg1..., argn,NULL);
int spawnle(modeflag, pathname, arg0, arg1..., argn,NULL, envp);
int spawnlp(modeflag, pathname, arg0, arg1..., argn,NULL);
int spawnlpe(modeflag, pathname, arg0, arg1..., argn,NULL, envp);
int spawnnv(modeflag, pathname, argv);
int spawnve(modeflag, pathname, argv, envp);
int spawnvp(modeflag, pathname, argv);
int spawnvpe(modeflag, pathname, argv, envp);
```

int modeflag;	Execution mode for parent process
char *pathname;	Path name of file to be executed
char *arg0,*arg1,...,*argn ;	List of pointers to arguments
char *argv[];	Array of pointers to arguments
char *envp[];	Array of pointers to environment settings

■ Description

The **spawn** functions create and execute a new child process. Enough memory must be available for loading and executing the child process. The *modeflag* argument determines the action taken by the parent process before and during the **spawn**. The following values for *modeflag* are defined in **process.h**:

Value	Meaning
P_WAIT	Suspend parent process until execution of child process is complete
P_NOWAIT	Continue to execute parent process concurrently with child process

P_OVERLAY Overlay parent process with child, destroying the parent (same effect as **exec** calls)

Only the **P_WAIT** and **P_OVERLAY** *modeflag* values may currently be used. The **P_NOWAIT** value is reserved for possible future implementation. An error value is returned if **P_NOWAIT** is used.

The *pathname* argument specifies the file to be executed as the child process. The *pathname* can specify a full path (from the root), a partial path (from the current working directory), or just a file name. If *pathname* does not have a file-name extension or end with a period (.), search for the file; if unsuccessful, the extension .EXE is attempted. If *pathname* has an extension, only that extension is used. If *pathname* ends with a period, the **spawn** calls search for *pathname* with no extension. The **spawnlp**, **spawnlpe**, **spawnvp**, and **spawnvpe** routines search for *pathname* (using the same procedures) in the directories specified by the **PATH** environment variable.

Arguments are passed to the child process by giving one or more pointers to character strings as arguments in the **spawn** call. These character strings form the argument list for the child process. The combined length of the strings forming the argument list for the child process must not exceed 128 bytes. The terminating null character ('\\0') for each string is not included in the count, but space characters (automatically inserted to separate arguments) are included.

The argument pointers may be passed as separate arguments (**spawnl**, **spawnle**, **spawnlp**, and **spawnlpe**) or as an array of pointers (**spawnv**, **spawnve**, **spawnvp**, and **spawnvpe**). At least one argument, *arg0* or *argv[0]*, must be passed to the child process. By convention, this argument is a copy of the *pathname* argument. (A different value will not produce an error.) Under versions of MS-DOS earlier than 3.0, the passed value of *arg0* or *argv[0]* is not available for use in the child process. However, under MS-DOS 3.0 and later, the *pathname* is available as *arg0* or *arg[0]*.

The **spawnl**, **spawnle**, **spawnlp**, and **spawnlpe** calls are typically used in cases where the number of arguments is known in advance. The *arg0* argument is usually a pointer to *pathname*. The arguments *arg1* through *argn* are pointers to the character strings forming the new argument list. Following *argn* there must be a NULL pointer to mark the end of the argument list.

The **spawnv**, **spawnve**, **spawnvp**, and **spawnvpe** calls are useful when the number of arguments to the child process is variable. Pointers to the arguments are passed as an array, *argv*. The argument *argv[0]* is usually a pointer to the *pathname* and *argv[1]* through *argv[n]* are pointers to the

spawnl – spawnvpe

character strings forming the new argument list. The argument *argv[n+1]* must be a **NULL** pointer to mark the end of the argument list.

Files that are open when a **spawn** call is made remain open in the child process. In the **spawnl**, **spawnlp**, **spawnv**, and **spawnvp** calls, the child process inherits the environment of the parent. The **spawnle**, **spawnlpe**, **spawnve**, and **spawnvpe** calls allow the user to alter the environment for the child process by passing a list of environment settings through the *envp* argument. The argument *envp* is an array of character pointers, each element of which (except for the final element) points to a null-terminated string defining an environment variable. Such a string usually has the form

NAME=*value*

where **NAME** is the name of an environment variable and *value* is the string value to which that variable is set. (Note that *value* is not enclosed in double quotes.) The final element of the *envp* array should be **NULL**. When *envp* itself is **NULL**, the child process inherits the environment settings of the parent process.

■ Return Value

The return value is the exit status of the child process. The exit status is 0 if the process terminated normally. The exit status can also be set to a nonzero value if the child process specifically calls the **exit** routine with a nonzero argument. If not set, a positive exit status indicates an abnormal exit with an **abort** or an interrupt.

A return value of -1 indicates an error (the child process is not started), and **errno** is set to one of the following values:

Value	Meaning
E2BIG	The argument list exceeds 128 bytes, or the space required for the environment information exceeds 32K.
EINVAL	Invalid <i>modeflag</i> argument.
ENOENT	File or path name not found.
ENOEXEC	The specified file is not executable or has an invalid executable file format.
ENOMEM	Not enough memory is available to execute the child process.

Note

The **spawn** calls do not preserve the translation modes of open files. If the child process must use files inherited from the parent, the **setmode** routine should be used to set the translation mode of these files to the desired mode.

Signal settings are not preserved in child processes created by calls to **spawn** routines. The signal settings are reset to the default in the child process.

■ **See Also**

abort, execl, execle, execlp, execlpe, execv, execve, execvp, execvpe, exit, _exit, onexit, system

spawnl – spawnvpe

■ Example

```
#include <stdio.h>
#include <process.h>

extern char **environ;

char *args[4];
int result;

args[0] = "child";
args[1] = "one";
args[2] = "two";
args[3] = NULL;
.
.
.

/* All of the following statements attempt to spawn a
** process called "child.exe" and pass it three arguments.
** The first three suspend the parent, and the last three
** overlay the parent with the child.
*/
result = spawnl(P_WAIT, "child.exe", "child", "one", "two",
                NULL);
result = spawnle(P_WAIT, "child.exe", "child", "one",
                 "two", NULL, environ);
result = spawnlp(P_WAIT, "child.exe", "child", "one",
                 "two", NULL);
result = spawnnv(P_OVERLAY, "child.exe", args);
result = spawnve(P_OVERLAY, "child.exe", args, environ);
result = spawnvp(P_OVERLAY, "child.exe", args);
```

■ Summary

```
#include <stdio.h>
```

```
int sprintf(buffer, format-string[], argument...]);
char *buffer;           Storage location for output
char *format-string;    Format-control string
```

■ Description

The **sprintf** function formats and stores a series of characters and values in *buffer*. Each *argument* (if any) is converted and output according to the corresponding format specification in the *format-string*. The *format-string* consists of ordinary characters and has the same form and function as the *format-string* argument for the **printf** function; see the **printf** reference page for a description of the *format-string* and arguments.

■ Return Value

The **sprintf** function returns the number of characters stored in *buffer*.

■ See Also

fprintf, **printf**, **sscanf**

■ Example

```
#include <stdio.h>

char buffer[200];
int i, j;
double fp;
char *s = "computer";
char c;
.

.

/*
Format and print various data. */
j = sprintf(buffer, "%s\n", s);
j += sprintf(buffer+j, "%c\n", c);
j += sprintf(buffer+j, "%d\n", i);
j += sprintf(buffer+j, "%f\n", fp);
```

sqrt

■ Summary

```
# include <math.h>
```

```
double sqrt(x);
```

```
double x;
```

Non-negative floating-point value

■ Description

The **sqrt** function calculates the square root of *x*.

■ Return Value

The **sqrt** function returns the square root result. If *x* is negative, the function prints a **DOMAIN** error message to **stderr**, sets **errno** to **EDOM**, and returns 0.

Error handling can be modified by using the **matherr** routine.

■ See Also

exp, log, matherr, pow

■ Example

```
#include <math.h>
#include <stdlib.h>

double x, y, z;
.

.

if ((z = sqrt(x+y)) == 0.0)
    if ((x+y) < 0.0)
        perror("sqrt of a negative number");
```

■ Summary

```
# include <stdlib.h>          Required only for function declarations
```

```
void srand(seed);           Seed for random-number generation
unsigned seed;
```

■ Description

The **srand** function sets the starting point for generating a series of pseudorandom integers. To reinitialize the generator, use 1 as the *seed* argument. Any other value for *seed* sets the generator to a random starting point.

The **rand** function is used to retrieve the pseudorandom numbers generated.

■ Return Value

There is no return value.

■ See Also

rand

■ Example

```
#include <stdlib.h>
#include <stdio.h>

int x, ranvals[20];

/* Initialize the random-number generator and save the
** first 20 random numbers generated in an array.
*/
srand(17);
for (x = 0; x < 20; ranvals[x++] = rand( ))
;
```

sscanf

■ Summary

```
# include <stdio.h>
```

```
int sscanf(buffer, format-string[], argument...);  
char *buffer;                                          Stored data  
char *format-string;                                 Format control string
```

■ Description

The **sscanf** function reads data from *buffer* into the locations given by *arguments*. Each *argument* must be a pointer to a variable with a type that corresponds to a type specifier in the *format-string*. The *format-string* controls the interpretation of the input fields and has the same form and function as the *format-string* argument for the **scanf** function; see the **scanf** reference page for a description of the *format-string*.

■ Return Value

The **sscanf** function returns the number of fields that were successfully converted and assigned. The return value does not include fields which were read but not assigned.

The return value is **EOF** for an attempt to read at end-of-string. A return value of 0 means that no fields were assigned.

■ See Also

fscanf, **scanf**, **sprintf**

■ Example

```
#include <stdio.h>

char *tokenstring = "15 12 14...";
int i;
float fp;
char s[81];
char c;
.
.
.
/* Input various data:
 */
sscanf(tokenstring, "%s",s);
sscanf(tokenstring, "%c",&c);
sscanf(tokenstring, "%d",&i);
sscanf(tokenstring, "%f",&fp);
```

stackavail

■ Summary

```
# include <malloc.h>           Required only for function declarations
```

```
unsigned int stackavail( );
```

■ Description

The **stackavail** function returns the approximate size in bytes of the stack space available for dynamic memory allocation with **alloca**.

■ Return Value

The **stackavail** function returns the size in bytes as an unsigned integer value.

■ See Also

alloca, freect, memavl

■ Example

```
#include <malloc.h>

main( )
{
    char *ptr;
    printf("Stack memory available before alloca = %u\n",
           stackavail( ));
    ptr = alloca(1000*sizeof(char));
    printf("Stack memory available after alloca = %u\n",
           stackavail( ));
}
```

Sample output:

```
Stack memory available before alloca = 1682
Stack memory available after alloca = 678
```

■ Summary

```
# include <sys\ types.h>
# include <sys\ stat.h>
```

```
int stat(pathname, buffer);
```

```
char * pathname;
```

Path name of existing file

```
struct stat * buffer;
```

Pointer to structure to receive results

■ Description

The **stat** function obtains information about the file or directory specified by *pathname* and stores it in the structure pointed to by *buffer*. The **stat** structure, defined in **sys\stat.h**, contains the following fields:

Field	Value
st_mode	Bit mask for file mode information. S_IFDIR bit set if <i>pathname</i> specifies a directory; S_IFREG bit set if <i>pathname</i> specifies an ordinary file. User read/write bits set according to the file's permission mode; user execute bits set using the file-name extension.
st_dev	Drive number of the disk containing the file.
st_rdev	Drive number of the disk containing the file (same as st_dev).
st_nlink	Always 1.
st_size	Size of the file in bytes.
st_atime	Time of last modification of file.
st_mtime	Time of last modification of file (same as st_atime).
st_ctime	Time of last modification of file (same as st_atime and st_mtime).

There are three additional fields in the **stat** structure type that do not contain meaningful values under MS-DOS.

stat

■ Return Value

The **stat** function returns the value 0 if the file-status information is obtained. A return value of -1 indicates an error, and **errno** is set to **ENOENT**, indicating that the file name or path name could not be found.

■ See Also

access, **fstat**

Note

If the given *pathname* refers to a device, the size and time fields in the **stat** structure are not meaningful.

■ Example

```
#include <sys\types.h>
#include <sys\stat.h>
#include <stdio.h>

struct stat buf;
int result;
char *args[4];
.

.

result = stat("child.exe",&buf);

if (result == 0)
    if (buf.st_mode & S_IEXEC)
        execv("child.exe", args);
```

■ **Summary**

```
# include <float.h>  
  
unsigned int _status87();
```

Get floating-point status word

■ **Description**

The **_status87** function gets the floating-point status word. The floating-point status word is a combination of the 8087/80287 status word and other conditions detected by the 8087/80287 exception handler, such as floating-point stack overflow and underflow.

■ **Return Value**

The bits in the value returned indicate the floating-point status. See the **float.h** include file for a complete definition of the bits returned by **_status87**.

Note

Many of the math library functions modify the 8087/80287 status word, with unpredictable results. Return values from **_clear87** and **_status87** become more reliable as fewer floating-point operations are performed between known states of the floating-point status word.

■ **See Also**

_clear87, **_control87**

_status87

■ Example

```
#include <stdio.h>
#include <float.h>

double a = 1e-40, b;
float x,y;

main ( )
{
    printf("status = %.4x - clear\n",_status87( ));

    /* store into y is inexact and underflows */
    y = a;
    printf("status = %.4x - inexact, underflow\n",
           _status87( ));

    /* y is denormal */
    b = y;
    printf("status = %.4x - inexact, underflow, denormal\n",
           _status87( ));

    /* clear user 8087 status */
    _clear87( );
}
```

■ Summary

<code># include <string.h></code>	Required only for function declarations
<code>char *strcat(string1, string2);</code> <code>char *string1;</code> <code>char *string2;</code>	Append <i>string2</i> to <i>string1</i> Destination string Source string
<code>char *strchr(string, c);</code> <code>char *string;</code> <code>int c;</code>	Search for first occurrence of <i>c</i> in <i>string</i> Source string Character to be located
<code>int strcmp(string1, string2);</code> <code>char *string1;</code> <code>char *string2;</code>	Compare strings
<code>int strcasecmp(string1, string2);</code> <code>char *string1;</code> <code>char *string2;</code>	Compare strings without regard to case
<code>char strcpy(string1, string2);</code> <code>char *string1;</code> <code>char *string2;</code>	Copy <i>string2</i> to <i>string1</i> Destination string Source string
<code>int strcspn(string1, string2);</code> <code>char *string1;</code> <code>char *string2;</code>	Find first substring in <i>string1</i> of characters not in <i>string2</i> Source string Character set
<code>char *strdup(string);</code> <code>char *string;</code>	Duplicate <i>string</i> Source string
<code>int stricmp(string1, string2);</code> <code>char *string1;</code> <code>char *string2;</code>	Compare strings without regard to case

strcat – strdup

■ Description

The **strcat**, **strchr**, **strcmp**, **strcmpi**, **strcpy**, **strcspn**, **strdup**, and **stricmp** functions operate on null-terminated strings. The string arguments to these functions are expected to contain a null character ('**\0**') marking the end of the string. No overflow checking is performed when strings are copied or appended.

The **strcat** function appends *string2* to *string1*, terminates the resulting string with a null character, and returns a pointer to the concatenated string (*string1*).

The **strchr** function returns a pointer to the first occurrence of *c* in *string*. The character *c* may be the null character ('**\0**'); the terminating null character of *string* is included in the search. The function returns **NULL** if the character is not found.

The **strcmp** function compares *string1* and *string2* lexicographically and returns a value indicating their relationship, as follows:

Value	Meaning
Less than 0	<i>string1</i> less than <i>string2</i>
0	<i>string1</i> identical to <i>string2</i>
Greater than 0	<i>string1</i> greater than <i>string2</i>

The **strcmpi** and **stricmp** functions are case-insensitive versions of **strcmp**. The two arguments *string1* and *string2* are compared without regard to case, meaning that the uppercase and lowercase forms of a letter are considered equivalent.

The **strcpy** function copies *string2*, including the terminating null character, to the location specified by *string1*, and returns *string1*.

The **strcspn** function returns the index of the first character in *string1* that belongs to the set of characters specified by *string2*. This value is equivalent to the length of the initial substring of *string1* that consists entirely of characters not in *string2*. Terminating null characters are not considered in the search. If *string1* begins with a character from *string2*, **strcspn** returns 0.

The **strdup** function allocates storage space (with a call to **malloc**) for a copy of *string* and returns a pointer to the storage space containing the copied string. The function returns **NULL** if storage could not be allocated.

■ Return Value

The return values for these functions are described above.

■ See Also

strncat, strncmp, strncpy, strnicmp, strrchr, strspn

■ Example

```
#include <string.h>

char string[100], template[100], *result;
int numresult;
.

.

/*
Construct the string "computer program" using strcpy
** and strcat.
*/
strcpy(string, "computer");
result = strcat(string, " program");

/* Search a string for the first occurrence of 'a'.
*/
result = strchr(string, 'a');

/* Determine whether a string is less than, greater
** than, or equal to another.
*/
numresult = strcmp(string, template);

/* Compare two strings without regard to case. */
numresult = strcmpl("hello", "HELLO"); /* result is 0 */

/* Make a copy of a string.
*/
result = strcpy(template, string);
```

strcat – strdup

```
/* Search for a's, b's, or c's in a string. */  
strcpy(string, "xyzabbc");  
result = strcspn(string, "abc");           /* result is 3 */  
  
/* Make new string point to a duplicate of string.  
 */  
  
result = strdup(string);
```

■ Summary

<code># include <string.h></code>	Required only for function declarations
<code>char *strerror(string);</code>	
<code>char *string;</code>	User-supplied message
<code>int errno;</code>	Error number
<code>int sys_nerr;</code>	Number of system messages
<code>char sys_errlist[sys_nerr];</code>	Array of error messages

■ Description

If *string* is equal to `NULL`, the **strerror** function returns a pointer to a string containing the system error message for the last library call that produced an error; this string is terminated by the new-line character ('`\n`').

If *string* is not equal to `NULL`, then **strerror** returns a pointer to a string containing, in order, your string message, a colon, a space, the system error message for the last library call producing an error, and a new-line character. Your *string* message can be a maximum of 94 bytes long.

Unlike **perror**, **strerror** alone does not print any messages. To print the message returned by **strerror** to **stderr**, your program will need a **printf** statement, as shown in the following lines:

```
if ((access("datafile", 2)) == -1)
    printf(strerror(NULL));
```

The actual error number is stored in the variable **errno**, which should be declared at the external level. The system error messages are accessed through the variable **sys_errlist**, which is an array of messages ordered by error number. The **strerror** function accesses the appropriate error message by using the **errno** value as an index to **sys_errlist**. The value of the variable **sys_nerr** is defined as the maximum number of elements in the **sys_errlist** array.

To produce accurate results, **strerror** should be called immediately after a library routine returns with an error. Otherwise, the **errno** value may be overwritten by subsequent calls.

strerror

■ Return Value

The **strerror** function returns no value.

■ See Also

clearerr, perror, perror

Note

Under MS-DOS, some of the **errno** values listed in **errno.h** are not used. See Appendix A, "Error Messages," for a list of **errno** values used on MS-DOS, and the corresponding error messages. The **strerror** function prints an empty string for any **errno** value not used under MS-DOS.

■ Example

```
#include <fcntl.h>
#include <sys\types.h>
#include <sys\stat.h>
#include <io.h>
#include <stdlib.h>

int fh1, fh2;

fh1 = open("data1",O_RDONLY);
if (fh1 == -1)
    strerror("open failed on input file");

fh2 = open("data2",O_WRONLY|O_TRUNC|O_CREAT,
           S_IREAD|S_IWRITE);
if (fh2 == -1)
    strerror("open failed on output file");
```

■ Summary

```
# include <string.h>
```

Required only for function declarations

```
int strlen(string);
char *string;
```

Null-terminated string

■ Description

The **strlen** function returns the length in bytes of *string*, not including the terminating null character ('\0').

■ Return Value

The **strlen** function returns the *string* length. There is no error return.

■ Example

```
#include <string.h>

char *string = "some space";
int result;
.

.

/* Determine the length of a string.
 */

result = strlen(string);      /* result = 10 */
```

strlwr

■ Summary

include <string.h> Required only for function declarations

char strlwr(string);
char *string; String to be converted

■ Description

The **strlwr** function converts any uppercase letters in the given null-terminated *string* to lowercase. Other characters are not affected.

■ Return Value

The **strlwr** function returns a pointer to the converted *string*. There is no error return.

■ See Also

strupr

■ Example

```
#include <string.h>

char string[100], *copy;
.
.
/*
 * Make a copy of a string in lowercase.
 */
copy = strlwr(strdup(string));
```

■ Summary

<code># include <string.h></code>	Required only for function declarations
<code>char *strncat(string1, string2, n);</code> <code>char *string1;</code> <code>char *string2;</code> <code>unsigned int n;</code>	Append <i>n</i> characters of <i>string2</i> to <i>string1</i> Destination string Source string Number of characters appended
<code>int strncmp(string1, string2, n);</code> <code>char *string1;</code> <code>char *string2;</code> <code>unsigned int n;</code>	Compare first <i>n</i> characters of strings Number of characters compared
<code>int strnicmp(string1, string2, n);</code> <code>char *string1;</code> <code>char *string2;</code> <code>unsigned int n;</code>	Compare first <i>n</i> characters of strings without regard to case Number of characters compared
<code>char *strncpy(string1, string2, n);</code> <code>char *string1;</code> <code>char *string2;</code> <code>unsigned int n;</code>	Copy <i>n</i> characters of <i>string2</i> to <i>string1</i> Destination string Source string Number of characters copied
<code>char *strnset(string, c, n);</code> <code>char *string;</code> <code>int c;</code> <code>unsigned int n;</code>	Initialize first <i>n</i> characters of <i>string</i> String to be initialized Character setting Number of characters set

■ Description

The **strncat**, **strncmp**, **strnicmp**, **strncpy**, and **strnset** functions operate on, at most, the first *n* characters of null-terminated strings.

The **strncat** function appends, at most, the first *n* characters of *string2* to *string1*, terminates the resulting string with a null character ('\0'), and returns a pointer to the concatenated string (*string1*). If *n* is greater than the length of *string2*, the length of *string2* is used in place of *n*.

strncat – strnset

The **strncmp** function compares, at most, the first *n* characters of *string1* and *string2* lexicographically and returns a value indicating the relationship between the substrings, as listed below:

Value	Meaning
Less than 0	<i>substring1</i> less than <i>substring2</i>
0	<i>substring1</i> equivalent to <i>substring2</i>
Greater than 0	<i>substring1</i> greater than <i>substring2</i>

The **strnicmp** function is a case-insensitive version of **strncmp**; **strnicmp** compares the two strings *string1* and *string2* without regard to case, which means that the uppercase (capital) and lowercase forms of a letter are considered equivalent.

The **strncpy** function copies exactly *n* characters of *string2* to *string1* and returns *string1*. If *n* is less than the length of *string2*, a null character ('\0') is *not* appended automatically to the copied string. If *n* is greater than the length of *string2*, the *string1* result is padded with null characters ('\0') up to length *n*.

The **strnset** function sets, at most, the first *n* characters of *string* to the character *c* and returns a pointer to the altered *string*. If *n* is greater than the length of *string*, the length of *string* is used in place of *n*.

■ See Also

strcat, **strcmp**, **strcpy**, **strset**

■ Example

```
#include <string.h>

char string[30] = {"12345678901234567890"};

main( )
{
    char copy[100], suffix[100], *result;
    int numresult;
    unsigned int nresult;
    .

    .

    /* Combine string with not more than 10 characters (30 minus
     ** the length of the initial string) of suffix. (If more
     ** than 10 characters were used, the example below would write
     ** over other values in memory.)
    */

    result = strncat(string,suffix,10);

    /* Determine the ordering of a string with respect to
     ** "program", but do not consider more than 7
     ** characters. So if string contains the prefix
     ** "program", strncmp will return 0.
    */

    strcpy(string,"programmer");
    numresult = strncmp(string,"program",7); /* numresult is 0 */

    /* Compare four characters of two strings without regard
     ** to case.
    */

    strcpy(string,"PROGRESS");
    nresult = strnicmp(string,"program",4); /* nresult is 0 */

    /* Copy at most 99 characters of a string.
    */

    result = strncpy(copy,string,99);

    /* Set the first four characters of a string to the
     ** character 'x'.
    */

    result = strnset("computer",'x',4); /* result is "xxxxuter" */
}
```

strpbrk

■ Summary

include <string.h>

Required only for function declarations

char *strpbrk(string1, string2);
char *string1;
char *string2;

Find any character from *string2* in *string1*
Source string
Character set

■ Description

The **strpbrk** function finds the first occurrence in *string1* of any character from *string2*. The terminating null character ('\0') is not included in the search.

■ Return Value

The **strpbrk** function returns a pointer to the first occurrence of any character from *string2* in *string1*. A NULL pointer indicates that *string1* and *string2* have no characters in common.

■ See Also

strchr, strrchr

■ Example

```
#include <string.h>

char string[100], *result;
.

.

/* Return a pointer to the first occurrence of either
** 'a' or 'b' in string.
*/
result = strpbrk(string, "ab");
```

■ Summary

include <string.h> Required only for function declarations

char *strrchr(string, c); Find last occurrence of *c* in *string*
char *string; Searched string
int c; Character to be located

■ Description

The **strrchr** function finds the last occurrence of the character *c* in *string*. The *string*'s terminating null character ('\0') is included in the search. (Use **strchr** to find the first occurrence of *c* in *string*.)

■ Return Value

The **strrchr** function returns a pointer to the last occurrence of *c* in *string*. A **NULL** pointer is returned if the given character is not found.

■ See Also

strchr, strpbrk

■ Example

```
#include <string.h>

char string[100], *result;
.

.

/* Search a string for the last occurrence of 'a'.
 */
result = strrchr(string, 'a');
```

strrev

■ Summary

`# include <string.h>` Required only for function declarations

`char *strrev(string);`
`char *string;` String to be reversed

■ Description

The **strrev** function reverses the order of the characters in the given *string*. The terminating null character ('\'0') remains in place.

■ Return Value

The **strrev** function returns a pointer to the altered *string*. There is no error return.

■ See Also

strcpy, strset

■ Example

```
#include <string.h>

char string[100];
int result;
.

.

/*
 * Determine if a string is a palindrome (reads the same
 * forward or backward).
 */

result = strcmp(string,strrev(strdup(string)));
/* If result == 0, the string is a palindrome.
 */
```

■ Summary

include <string.h> Required only for function declarations

char *strset(*string*, *c*);
char **string*; String to be set
int *c*; Character setting

■ Description

The **strset** function sets all characters of the given *string*, except the terminating null character ('\0'), to *c*.

■ Return Value

The **strset** function returns a pointer to the altered *string*. There is no error return.

■ See Also

strnset

■ Example

```
#include <string.h>  
  
char string[100], *result;  
. . .  
/* Set a string to be all blanks.  
 */  
result = strset(string, ' ');
```

strspn

■ Summary

```
# include <string.h>
```

Required only for function declarations

```
int strspn(string1, string2);
```

char *string1;

Searched string

char *string2;

Character set

■ Description

The **strspn** function returns the index of the first character in *string1* that *does not* belong to the set of characters specified by *string2*. This value is equivalent to the length of the initial substring of *string1* that consists entirely of characters from *string2*. The null character ('\0') terminating *string2* is not considered in the matching process. If *string1* begins with a character not in *string2*, **strspn** returns 0.

■ Return Value

The **strspn** function returns an integer value specifying the position of the first character in *string1* not in *string2*.

■ See Also

strcspn

■ Example

```
#include <string.h>

char *string="cabbage";
int result;
.

.

/*
 * Determine the length of the prefix consisting of
 ** a's, b's, and c's.
 */

result = strspn(string, "abc"); /* result = 5 */
```

■ Summary

`# include <string.h>` Required only for function declarations

```
char *strstr(string1, string2);
char *string1;                                Searched string
char *string2;                                String to search for
```

■ Description

The **strstr** function returns a pointer to the first occurrence of *string1* in *string2*.

■ Return Value

The **strstr** function returns a pointer to *string1* if it finds *string1*, and **NULL** if it does not find *string1*

■ See Also

strcspn

■ Example

```
#include <string.h>

main( )
{
    char *string1 = "needle in a haystack";
    char *string2 = "hay";

    printf("%s\n", strstr(string1, string2));
}
```

Output:

haystack

strtod – strtol

■ Summary

```
# include <stdlib.h>
```

```
double strtod(nptr, endptr);
```

Convert the string pointed to by *nptr*
to **double**

```
char *nptr;
```

Pointer to string

```
char **endptr;
```

Pointer to end of scan

```
long strtol(nptr, endptr, base);
```

Convert string to **long** decimal integer
equivalent of number in given *base*

```
char *nptr;
```

```
char **endptr;
```

```
int base;
```

Number base to use

■ Description

The functions **strtod** and **strtol** convert a character string to a double-precision value or a long-integer value, respectively. The input *string* is a sequence of characters that can be interpreted as a numerical value of the specified type. These functions stop reading the string at the first character they cannot recognize as part of a number (which may be the null character at the end of the string); with **strtol** this terminating character could also be the first numeric character greater than or equal to the *base*. If *endptr* is not **NULL**, **endptr* points to the character that stopped the scan.

The **strtod** function expects *nptr* to point to a string with the following form:

[whitespace][sign][digits][.digits][{ d | D | e | E } [sign]digits]

The first character that doesn't fit this form stops the scan.

The **strtol** function expects *nptr* to point to a string with the following form:

[whitespace] [sign] [0] [x] [digits]

If *base* is between 2 and 36, then it is used as the base of the number. If *base* is 0, the initial characters of the string pointed to by *nptr* are used to determine the base: if the first character is '0' and the second character is a digit '1' – '7', then the string is interpreted as an octal integer; if the first character is '0' and the second character is 'x' or 'X', then the string is

interpreted as a hexadecimal integer; if the first character is '1' – '9', then the string is interpreted as a decimal integer.

■ **Return Value**

The **strtod** function returns the value of the floating-point number, except when the representation would cause an overflow or underflow, in which case it returns **±HUGE**.

The **strtol** function returns the value represented in the string, except when the representation would cause an overflow or underflow, in which case it returns **LONG_MAX** or **LONG_MIN**.

In both functions **errno** is set to **ERANGE**.

■ **See Also**

atof, atol

strtod – strtol

■ Example

```
#include <stdlib.h>

main( )

{
    char *string, *stopstring;
    double x;
    long l;
    int bs;

    string = "3.1415926This stopped it";
    x = strtod(string,&stopstring);
    printf("string = %s\n",string);
    printf("    strtod = %f\n",x);
    printf("    Stopped scan at %s\n\n", stopstring);

    string = "10110134932";
    printf("string = %s\n",string);
    for (bs = 2; bs <= 8; bs *= 2) {
        l = strtol(string,&stopstring,bs);
        printf("    strtol = %ld (base %d)\n", l, bs);
        printf("    Stopped scan at %s\n\n", stopstring);
    }
}
```

Output:

```
string = 3.1415926This stopped it
strtod = 3.141593
Stopped scan at This stopped it

string = 10110134932
strtol = 45 (base 2)
Stopped scan at 34932

strtol = 4423 (base 4)
Stopped scan at 4932

strtol = 2134108 (base 8)
Stopped scan at 932
```

■ Summary

# include <string.h>	Required only for function declarations
char *strtok(string1, string2);	Find token in <i>string1</i>
char *string1;	String containing token(s)
char *string2;	Set of delimiter characters

■ Description

The **strtok** function reads *string1* as a series of zero or more tokens and *string2* as the set of characters serving as delimiters of the tokens in *string1*. The tokens in *string1* may be separated by one or more of the delimiters from *string2*. The tokens are broken out of *string1* by a series of calls to **strtok**.

In the first call to **strtok** for a given *string1*, **strtok** searches for the first token in *string1*, skipping leading delimiters. A pointer to the first token is returned.

To read the next token from *string1*, call **strtok** with a **NULL** value for the *string1* argument. The **NULL** *string1* argument causes **strtok** to search for the next token in the previous token string. The set of delimiters may vary from call to call, so *string2* can take any value.

Note

Calls to **strtok** will modify *string1*, since each time **strtok** is called, it inserts a null value ('**\0**') after the token in *string1*.

■ Return Value

The first time **strtok** is called, it returns a pointer to the first token in *string1*. In later calls with the same token string, **strtok** returns a pointer to the next token in the string. A **NULL** pointer is returned when there are no more tokens. All tokens are null terminated.

strtok

■ See Also

strcspn, strspn

■ Example

```
#include <string.h>
#include <stdio.h>

char *string="a  string,of ,,tokens ";
.
.
.

/* The following loop gathers tokens (separated by
** blanks or commas) from a string until there are none
** left:
*/
token = strtok(string, " ");

while (token != NULL) {
    /* insert code to process the token here
     */
    .
    .
    .
    token = strtok(NULL, " "); /* get next token */
}

/* Tokens returned are "a", "string", "of",
** and "tokens". The next call to strtok returns
** NULL and the loop terminates.
*/
```

■ Summary

include <string.h> Required only for function declarations

char *strupr(string);
char *string; String to be capitalized

■ Description

The **strupr** function converts any lowercase letters in the given *string* to uppercase. Other characters are not affected.

■ Return Value

The **strupr** function returns a pointer to the converted *string*. There is no error return.

■ See Also

strlwr

■ Example

```
#include <string.h>

char string[100], *copy;
.
.
.
/* The following statement makes a copy of a string in
** uppercase:
*/
copy = strupr(strdup(string));
```

swab

■ Summary

```
# include <stdlib.h>          Required only for function declarations
```

```
void swab(source, destination, n);
char *source;                  Data to be copied and swapped
char *destination;             Storage location for swapped data
int n;                         Number of bytes copied
```

■ Description

The **swab** function copies *n* bytes from *source*, swaps each pair of adjacent bytes, and stores the result at *destination*. The integer *n* should be an even number to allow for swapping. The **swab** function is typically used to prepare binary data for transfer to a machine that uses a different byte order.

■ Return Value

There is no return value.

■ See Also

fgetc, **fputc**

■ Example

```
#include <stdlib.h>
#define NBYTES 1024

char from[NBYTES], to[NBYTES];

/* Copy n bytes from one location to another,
** swapping each pair of adjacent bytes.
*/
swab(from,to,NBYTES);
```

■ Summary

```
# include <process.h>
# include <stdlib.h>
```

Required only for function declarations
Use either **process.h** or **stdlib.h**

```
int system(string);
char *string;
```

Command to be executed

■ Description

The **system** function passes the given *string* to the command interpreter and executes the string as an MS-DOS command. The **system** function refers to the **COMSPEC** and **PATH** environment variables to locate the MS-DOS file **COMMAND.COM**, which is used to execute the *string* command.

■ Return Value

The **system** function returns the value 0 if *string* is successfully executed. A return value of -1 indicates an error, and **errno** is set to one of the following values:

Value	Meaning
E2BIG	The argument list for the command exceeds 128 bytes, or the space required for the environment information exceeds 32K.
ENOENT	COMMAND.COM cannot be found.
ENOEXEC	The COMMAND.COM file has an invalid format and is not executable.
ENOMEM	Not enough memory is available to execute the command; or the available memory has been corrupted; or an invalid block exists, indicating that the process making the call was not allocated properly.

system

■ See Also

**execl, execle, execlp, execv, execve, execvp, exit, _exit, spawnl,
spawnle, spawnlp, spawnnv, spawnve, spawnvp**

■ Example

```
#include <process.h>

int result;

/* The following statement appends a copy of the DOS
** version number to a log file:
*/
result = system("ver >> result.log");
```

■ Summary

```
# include <math.h>

double tan(x);           Calculate tangent of x

double tanh(x);          Calculate hyperbolic tangent of x

double x;                 Radians
```

■ Description

The **tan** and **tanh** functions return the tangent and hyperbolic tangent of *x*, respectively.

■ Return Value

The **tan** function returns the tangent of *x*. If *x* is large, a partial loss of significance in the result may occur. In such cases, **tan** sets **errno** to **ERANGE** and generates a **PLOSS** error, but no message is printed. If *x* is so large that a total loss of significance occurs, **tan** prints a **TLOSS** error message to **stderr**, sets **errno** to **ERANGE**, and returns 0.

The **tanh** function returns the hyperbolic tangent of *x*. There is no error return.

■ See Also

acos, asin, atan, atan2, cos, cosh, sin, sinh

■ Example

```
#include <math.h>

double pi, x, y;
pi = 3.1415926535;
x = tan(pi/4.0); /* x is 1.0 */
y = tanh(x); /* y is 1.6 */
```

tell

■ Summary

include <io.h> Required only for function declarations

```
long tell(handle);  
int handle;
```

Handle referring to open file

■ Description

The **tell** function gets the current position of the file pointer (if any) associated with *handle*. The position is expressed as the number of bytes from the beginning of the file.

■ Return Value

The **tell** function returns the current position. A return value of -1L indicates an error, and **errno** is set to **EBADF** to indicate an invalid file-handle argument. On devices incapable of seeking (such as terminals and printers), the return value is undefined.

■ See Also

ftell, **lseek**

■ Example

```
#include <io.h>  
#include <stdio.h>  
#include <fcntl.h>  
  
int fh;  
long position;  
  
fh = open("data", O_RDONLY);  
.  
.  
position = tell(fh); /* remember current position */  
.  
. .  
lseek(fh, position, 0); /* seek to previous position */
```

■ Summary

```
# include <stdio.h>
```

```
char *tmpnam(string);
char *string;
```

Pointer to temporary name

```
char *tempnam(dir, prefix);
char *dir;
char *prefix;
```

■ Description

The **tmpnam** function generates a temporary file name that is usable as a temporary file. This name is stored in *string*. If *string* is **NULL**, then memory is allocated for the string using **malloc**. It is the user's responsibility to free memory when using **malloc**.

The character string created by **tmpnam** consists of the digit characters '0' through '9'; the numerical value of this string can range from 1 to 65535.

The **tempnam** function allows the user to create a temporary file in another directory. The *prefix* is the prefix to the file name. The **tempnam** function looks for the file with the given name in the following directories, listed in order of precedence:

Condition

TMP environment variable is set, and directory specified by **TMP** exists.

TMP environment variable not set, or directory specified by **TMP** does not exist.

The *dir* argument is **NULL**, or *dir* is name of nonexistent directory.

P_tmpdir does not exist.

Directory Used by **tempnam**

Directory specified by **TMP**

The *dir* argument to **tempnam**

P_tmpdir in **stdio.h**

\tmp

If all this fails, **tempnam** returns the value **NULL**.

tempnam – tmpnam

■ Return Value

The **tmpnam** and **tempnam** functions both return a pointer to the name generated, unless it is impossible to create this name, or the name is not unique. If the name cannot be created or if it already exists, **tmpnam** and **tempnam** return the value **NULL**.

■ See Also

tmpfile

■ Example

```
#include <stdio.h>

main( )
{
    char *name1, *name2;

    if ((name1 = tmpnam(NULL)) != NULL)
        printf("%s is safe to use as a temporary file.\n", name1);
    else
        printf("cannot create a unique file name\n");

    if ((name2 = tempnam("a:\\\\tmp", "stq")) != NULL)
        printf("%s is safe to use as a temporary file.\n", name2);
    else
        printf("cannot create a unique file name\n");
}
```

■ Summary

include <time.h> Required only for function declarations

long time(*timeptr*);
long **timeptr*; Storage location for time

■ Description

The **time** function returns the number of seconds elapsed since 00:00:00 Greenwich mean time, January 1, 1970, according to the system clock. The return value is also stored in the location given by *timeptr*; *timeptr* may be **NULL**, in which case the return value is not stored.

■ Return Value

The **time** function returns the time in elapsed seconds. There is no error return.

■ See Also

asctime, **ftime**, **gmtime**, **localtime**, **utime**

■ Example

```
#include <time.h>
#include <stdio.h>

long ltime;

time(&ltime);
printf("the time is %s\n", ctime(&ltime));
```

tmpfile

■ Summary

```
# include <stdio.h>

FILE *tmpfile( );
```

Pointer to file structure

■ Description

The **tmpfile** function creates a temporary file and returns a pointer to that file. If the file cannot be opened, **tmpfile** returns a **NULL** pointer.

This temporary file is automatically deleted when the program terminates normally, or when **rmtmp** is called, assuming that the current working directory does not change. The temporary file is opened in "**w+**" mode.

■ Return value

The **tmpfile** function returns a stream pointer, unless it cannot open the file, in which case it returns a **NULL** pointer.

■ See Also

tmpnam, **tempnam**, **rmtmp**

■ Example

```
#include <stdio.h>

FILE *stream;
char tmpstring[ ] = "String to be temporarily written";

main( )

{
    if ((stream = tmpfile( )) == NULL)
        perror("Couldn't make temporary file");
    else
        fprintf(stream, "%s", tmpstring);
}
```

■ Summary

# include <ctype.h>	
int toascii(c);	Convert <i>c</i> to ASCII character
int tolower(c);	Convert <i>c</i> to lowercase if appropriate
int _tolower(c);	Convert <i>c</i> to lowercase
int toupper(c);	Convert <i>c</i> to uppercase if appropriate
int _toupper(c);	Convert <i>c</i> to uppercase
int <i>c</i> ;	Character to be converted

■ Description

The **toascii**, **tolower**, **_tolower**, **toupper**, and **_toupper** macros convert a single character as specified.

The **toascii** macro sets all but the low order 7 bits of *c* to 0, so that the converted value represents a character in the ASCII character set. If *c* already represents an ASCII character, *c* is unchanged.

The **tolower** macro converts *c* to lowercase if *c* represents an uppercase letter. Otherwise, *c* is unchanged.

The **_tolower** macro is a version of **tolower** to be used only when *c* is known to be uppercase. The result of **_tolower** is undefined if *c* is not an uppercase letter.

The **toupper** macro converts *c* to uppercase if *c* represents a lowercase letter. Otherwise, *c* is unchanged.

The **_toupper** macro is a version of **toupper** to be used only when *c* is known to be lowercase. The result of **_toupper** is undefined if *c* is not a lowercase letter.

toascii – _toupper

■ Return Value

The **toascii**, **tolower**, **_tolower**, **toupper**, and **_toupper** macros return the possibly converted character *c*. There is no error return.

■ See Also

isalnum, **isalpha**, **isascii**, **iscntrl**, **isdigit**, **isgraph**, **islower**, **isprint**,
ispunct, **isspace**, **isupper**, **isxdigit**

Note

These routines are implemented as macros. However, **tolower** and **toupper** are also implemented as functions, because the macro versions do not correctly handle arguments with side effects. The function versions can be used by removing the macro definitions through **#undef** directives or by not including **ctype.h**. Function declarations of **tolower** and **toupper** are given in **stdlib.h**.

■ Example

```
#include <stdio.h>
#include <ctype.h>

int ch;

/* The following statements analyze all characters
** between code 0x0 and code 0x7f. The toupper and tolower
** macros are applied to all codes. _Toupper and _tolower are
** applied to codes for which they make sense. */

for (ch = 0; ch <= 0x7f; ch++) {
    printf(" toupper=%#04x", toupper(ch));
    printf(" tolower=%#04x", tolower(ch));

    if (islower(ch))
        printf(" _toupper=%#04x", _toupper(ch));
    if (isupper(ch))
        printf(" _tolower=%#04x", _tolower(ch));

    putchar('\n');
}
```

■ Summary

<code># include <time.h></code>	Required only for function declarations
<code>void tzset();</code>	
<code>int daylight;</code>	Daylight saving time flag
<code>long timezone;</code>	Difference in seconds from GMT
<code>char *tzname[2];</code>	Three-letter time-zone strings

■ Description

The **tzset** function uses the current setting of the environment variable **TZ** to assign values to three variables: **daylight**, **timezone**, and **tzname**. These variables are used by the **ftime** and **localtime** functions to make corrections from Greenwich mean time (GMT) to local time.

The value of the environment variable **TZ** must be a three-letter time-zone name, such as PST, followed by an optionally signed number giving the difference in hours between Greenwich mean time and local time. The number may be followed by a three-letter daylight saving time zone, such as PDT. For example, “PST8PDT” represents a valid **TZ** value for the Pacific time zone.

The following values are assigned to the variables **daylight**, **timezone**, and **tzname** when **tzset** is called:

Variable	Value
timezone	The difference in seconds between Greenwich mean time and local time
daylight	Nonzero value if a daylight saving time zone is specified in the TZ setting; otherwise, 0
tzname[0]	The string value of the three-letter time-zone name from the TZ setting
tzname[1]	The string value of the daylight saving time zone, or an empty string if the daylight saving time zone is omitted from the TZ setting

If **TZ** is not currently set, the default is “PST8PDT”, which corresponds to the Pacific time zone. The default for **daylight** is 1; for **timezone**, 28800; for **tzname[0]**, “PST”; and for **tzname[1]**, “PDT”.

tzset

■ **Return Value**

There is no return value.

■ **See Also**

asctime, ftime, localtime

■ **Example**

```
#include <time.h>

int daylight;
long timezone;
char *tzname[ ];

.
.

putenv("TZ=EST5");
tzset( );           /* daylight is 0,
                      ** timezone is 18000,
                      ** tzname[0] is "EST",
                      ** tzname[1] is empty
*/
```

■ Summary

<code># include <stdlib.h></code>	Required only for function declarations
---	---

<code>char ultoa(value, string, radix);</code>	
<code>unsigned long value;</code>	Number to be converted
<code>char *string;</code>	String result
<code>int radix;</code>	Base of <i>value</i>

■ Description

The **ultoa** function converts the digits of the given *value* to a null-terminated character string and stores the result in *string*. No overflow checking is performed. The *radix* argument specifies the base of *value*; it must be in the range 2–36.

■ Return Value

The **ultoa** function returns a pointer to *string*. There is no error return.

■ See Also

itoa, ltoa

Note

The space allocated for *string* must be large enough to hold the returned string. The function can return up to 33 bytes.

■ Example

```
#include <stdlib.h>

int radix = 16;
char buffer[40];
char *p;
/* p will be "501d9138 */
p = ultoa(1344115000L,buffer,radix);
```

umask

■ Summary

```
# include <sys\ types.h>
# include <sys\ stat.h>
# include <io.h>      Required only for function declarations

int umask(pmode);
int pmode;          Default permission setting
```

■ Description

The **umask** function sets the file-permission mask of the current process to the mode specified by *pmode*. The file permission mask is used to modify the permission setting of new files created by **creat**, **open**, or **sopen**. If a bit in the mask is 1, the corresponding bit in the file's requested permission value is set to 0 (disallowed). If a bit in the mask is 0, the corresponding bit is left unchanged. The permission setting for a new file is not set until the file is closed for the first time.

The argument *pmode* is a constant expression containing one or both of the manifest constants **S_IWRITE** and **S_IREAD**, defined in **sys\stat.h**. When both constants are given, they are joined with the bitwise-OR operator (`|`). The meaning of the *pmode* argument is as follows:

Value	Meaning
S_IWRITE	Writing not allowed (file is read only)
S_IREAD	Reading not allowed (file is write only)

For example, if the write bit is set in the mask, any new files will be read only.

Note

Under MS-DOS, all files are readable—it is not possible to give write-only permission. Therefore, setting the read bit with **umask** has no effect on the file's permissions.

■ Return Value

The **umask** function returns the previous value of *pmode*. There is no error return.

■ See Also

chmod, creat, mkdir, open

■ Example

```
#include <sys\types.h>
#include <sys\stat.h>
#include <io.h>

int oldmask;

oldmask = umask(S_IWRITE); /* create read-only files */
```

ungetc

■ Summary

```
#include <stdio.h>
```

```
int ungetc(c, stream);  
int c;           Character to be pushed  
FILE *stream;   Pointer to file structure
```

■ Description

The **ungetc** function pushes the character *c* back onto the given input *stream*. The *stream* must be buffered and open for reading. A subsequent read operation on the *stream* starts with *c*. An attempt to push **EOF** onto the stream using **ungetc** is ignored. The **ungetc** function returns an error value if nothing has yet been read from *stream* or if *c* cannot be pushed back.

Characters placed on the stream by **ungetc** may be erased if an **fseek** or **rewind** function is called before the character is read from the *stream*.

■ Return Value

The **ungetc** function returns the character argument *c*. The return value **EOF** indicates a failure to push back the specified character.

■ See Also

getc, **getchar**, **putc**, **putchar**

■ Example

```
#include <stdio.h>
#include <ctype.h>

FILE *stream;
int ch;
int result = 0;
.

.

/*
 * The following statements gather a decimal integer
 * from a stream:
 */

while ((ch = getc(stream)) != EOF && isdigit(ch))
    result = result * 10 + ch - '0';

if (ch != EOF)
    ungetc(ch, stream); /* put nondigit back */
```

ungetch

■ Summary

include <conio.h> Required only for function declarations

int ungetch(*c*);

int *c*;

Character to be pushed

■ Description

The **ungetch** function pushes the character *c* back to the console, causing *c* to be the next character read. The **ungetch** function fails if it is called more than once before the next read.

■ Return Value

The **ungetch** function returns the character *c* if it is successful. A return value of **EOF** indicates an error.

■ See Also

cscanf, getch, getche

■ Example

```
#include <conio.h>
#include <ctype.h>

char buffer[100];
int count = 0;
int ch;

/* The following code gets a token, delimited by blanks or
** new lines, from the keyboard:
*/

ch = getche( );

while (isspace(ch))          /* skip preceding white space */
    ch = getche( );

while (count < 99) {           /* gather token */
    if (isspace(ch))          /* end of token */
        break;

    buffer[count++] = ch;
    ch = getche( );
}

ungetch(ch);                  /* put back delimiter */
buffer[count] = '\0';          /* null terminate the token */
```

unlink

■ Summary

```
# include <io.h>
# include <stdio.h>
```

Required only for function declarations
Use either **io.h** or **stdio.h**

```
int unlink(pathname);
char *pathname;
```

Path name of file to be removed

■ Description

The **unlink** function deletes the file specified by *pathname*.

■ Return Value

The **unlink** function returns the value 0 if the file is successfully deleted. A return value of -1 indicates an error, and **errno** is set to one of the following values:

Value	Meaning
EACCES	Path name specifies a directory or a read-only file.
ENOENT	File or path name not found.

■ See Also

close, **remove**

■ Example

```
#include <io.h>
#include <stdlib.h>

int result;

result = unlink("tmpfile");
if (result == -1)
    perror("couldn't delete tmpfile");
```

■ Summary

```
# include <sys\ types.h>
# include <sys\ utime.h>

int utime(pathname, times);
char *pathname; File path name
struct utimbuf *times; Pointer to stored time values
```

■ Description

The **utime** function sets the modification time for the file specified by *pathname*. The process must have write access to the file; otherwise, the time cannot be changed.

Although the **utimbuf** structure contains a field for access time, under MS-DOS only the modification time is set. If *times* is a NULL pointer, the modification time is set to the current time. Otherwise, *times* must point to a structure of type **utimbuf**, defined in **sys\utime.h**. The modification time is set from the **modtime** field in this structure.

■ Return Value

The **utime** function returns the value 0 if the file modification time was changed. A return value of -1 indicates an error, and **errno** is set to one of the following values:

Value	Meaning
EACCES	Path name specifies directory or read-only file.
EMFILE	Too many open files (the file must be opened to change its modification time).
ENOENT	File or path name not found.

■ See Also

asctime, **ctime**, **fstat**, **ftime**, **gmtime**, **localtime**, **stat**, **time**

utime

■ Example

```
#include <sys\types.h>
#include <sys\utime.h>
#include <stdio.h>
#include <stdlib.h>

/* Set a file modification time to the current time:
 */
if (utime("/tmp/data",NULL) == -1)
    perror("utime failed");
```

■ Summary

`# include <varargs.h>`

Required for compatibility with
UNIX V

`# include <stdarg.h>`

Required for compatibility with
proposed ANSI C standard

`void va_start(arg_ptr);`

Macro to set *arg_ptr* to beginning of list
of optional arguments (**varargs.h** version
only)

`void va_start(arg_ptr, prev-param);`

Macro to set *arg_ptr* to beginning of list
of optional arguments (**stdarg.h** version
only)

`type va_arg(arg_ptr, type);`

Macro to retrieve current argument

`void va_end(arg_ptr);`

Macro to reset *arg_ptr*

`va_list arg_ptr;`

Pointer to list of arguments

`type`

Type of argument to be retrieved

`prev-param`

Parameter preceding first optional
argument (**stdarg.h** version only)

`va_alist`

Name of parameter to called function
(**varargs.h** version only)

`va_decl`

Declaration of `va_alist` (**varargs.h**
version only)

■ Description

The `va_start`, `va_arg`, and `va_end` macros provide a portable way to access the arguments to a function when the function takes a variable number of arguments. Two versions of the macros are available: the macros defined in **varargs.h** are compatible with the UNIX System V definition, and the macros defined in **stdarg.h** conform to the proposed ANSI C standard.

Both versions of the macros assume that the function takes a fixed number of required arguments, followed by a variable number of optional arguments. The required arguments are declared as ordinary parameters to the function and can be accessed through the parameter names. The optional arguments are accessed through the **varargs.h** or **stdarg.h** macros, which

va_arg - va_start

set a pointer to the first optional argument in the argument list, retrieve arguments from the list, and reset the pointer when argument processing is completed.

The UNIX System V macros, defined in **varargs.h**, are used as follows:

1. Any required arguments to the function can be declared as parameters in the usual way.
2. The last (or only) parameter to the function represents the list of optional arguments. This parameter must be named **va_alist** (not to be confused with **va_list**, which is defined as the type of **va_alist**).
3. The **va_dcl** macro appears after the function definition and before the opening left brace of the function. This macro is defined as a complete declaration of the **va_alist** parameter, including the terminating semicolon; therefore, no semicolon should follow **va_dcl**.
4. Within the function, the **va_start** macro sets *arg_ptr* to the beginning of the list of optional arguments passed to the function. The **va_start** macro must be used before **va_arg** is used for the first time. The argument *arg_ptr* must have **va_list** type.
5. The **va_arg** macro does the following:
 - Retrieves a value of the given *type* from the location given by *arg_ptr*
 - Increments *arg_ptr* to point to the next argument in the list, using the size of *type* to determine where the next argument starts
6. After all arguments have been retrieved, **va_end** resets the pointer to **NULL**.

The proposed ANSI C standard macros, defined in **stdarg.h**, operate in a slightly different manner, as follows:

1. All required arguments to the function are declared as parameters in the usual way. The **va_dcl** macro is not used with the **stdarg.h** macros.
2. The **va_start** macro sets *arg_ptr* to the first optional argument in the list of arguments passed to the function. The argument *arg_ptr* must have **va_list** type. The argument *prev-param* is the name of the required parameter immediately preceding the first optional

argument in the argument list. The **va_start** macro must be used before **va_arg** is used for the first time.

3. The **va_arg** macro does the following:

- Retrieves a value of the given *type* from the location given by *arg_ptr*
- Increments *arg_ptr* to point to the next argument in the list, using the size of *type* to determine where the next argument starts

The **va_arg** macro can be used any number of times within the function to retrieve arguments from the list.

4. After all arguments have been retrieved, **va_end** resets the pointer to **NULL**.

■ **Return Value**

The **va_arg** macro returns the current argument; **va_start** and **va_end** do not return values.

■ **See Also**

vfprintf, **vprintf**, **vsprintf**

va_arg – va_start

■ Example

Program listing using **varargs.h** for compatibility with UNIX V:

```
#include <stdio.h>
#include <varargs.h>

main( )
{
    int n;
    .
    .
    .
    /* Call function with 4 arguments; last argument is
     ** -1 to mark end of argument list:
    */
    n = average(2, 3, 4, -1);
    printf("Average is: %d\n", n);
    .
    .
    .
    /* Call function with 5 arguments; last argument is
     ** -1 to mark end of argument list:
    */
    n = average(5, 7, 9, 11, -1);
    printf("Average is: %d\n", n);
}

average(va_alist)
va_dcl
{
    int i = 0, count = 0, sum = 0;
    va_list arg_marker;

    va_start(arg_marker);

    /* Retrieve arguments and add to sum until last
     ** argument, -1, is reached:
    */
    for (; (i = va_arg(arg_marker,int)) >= 0; sum+=i, count++)
        ;

    return (count ? (sum/count) : count);
}
```

A similar program, rewritten for compatibility with the ANSI C standard:

```
#include <stdio.h>
#include <stdarg.h>

main( )
{
    int n;
    .
    .
    .
    /* Call function with 4 arguments; last argument is
     ** -1 to mark end of argument list:
    */
    n = average(2, 3, 4, -1);
    printf("Average is: %d\n", n);
    .
    .
    .
    /* Call function with 5 arguments; last argument is
     ** -1 to mark end of argument list:
    */
    n = average(5, 7, 9, 11, -1);
    printf("Average is: %d\n", n);
}

average(first)
int first;
{
    int i = 0, count = 0, sum;
    va_list arg_marker;

    va_start(arg_marker, first);

    /* Add first argument to sum and increment count;
     ** return if first argument is -1:
    */
    if (first != -1)
        sum = first;
    else
        return (0);
    count++;
    /* Retrieve additional arguments and add to sum until
     ** last argument, -1, is reached:
    */
    for (; (i = va_arg(arg_marker,int)) >= 0; sum+=i, count++)
        ;

    return (sum/count);
}
```

vfprintf - vsprintf

■ Summary

# include <stdio.h>	
# include <varargs.h>	Required for compatibility with UNIX V
# include <stdarg.h>	Required for compatibility with proposed ANSI C standard
int vfprintf(stream, format-string, arg_ptr);	
int vprintf(format-string, arg_ptr);	
int vsprintf(buffer, format-string, arg_ptr);	
FILE *stream;	Pointer to file structure
char *buffer;	Storage location for output
char *format-string;	Format control
va_list arg_ptr;	Pointer to list of arguments

■ Description

The **vfprintf**, **vprintf**, and **vsprintf** functions format and output data to *stream*, the standard output, or *buffer*, respectively. These functions are similar to their counterparts **fprintf**, **printf**, and **sprintf**, but **vfprintf**, **vprintf**, and **vsprintf** accept a pointer to a list of arguments rather than a list of arguments.

The *format-string* has the same form and function as the *format-string* argument for the **printf** function; see the **printf** reference page for a description of the *format-string*.

The *arg_ptr* parameter has type **va_list**, which is defined in **varargs.h** and **stdarg.h**. The *arg_ptr* parameter points to a list of arguments that are converted and output according to the corresponding format specifications in the *format-string*.

■ Return Value

The return value is the number of characters written.

■ See also

fprintf, printf, sprintf, va_arg, va_end, va_start

■ Example

Program listing using **varargs.h** for compatibility with UNIX V:

```
#include <stdio.h>
#include <varargs.h>

main( )
{
    int line = 1;
    char *filename = "EXAMPLE";
    .
    .
    .
    error("Error: line %d, file %s\n", line, filename);
    .
    .
    .
    error("Syntax error\n");
}

error(va_alist)
va_dcl
{
    char *fmt;
    va_list arg_ptr;

    va_start(arg_ptr);
    /* arg_ptr now points to format string */
    fmt = va_arg(arg_ptr, char *);
    /* arg_ptr now points to argument after format string */
    vprintf(fmt, arg_ptr);
    va_end(arg_ptr);
}
```

Output:

```
Error: line 1, file EXAMPLE
Syntax error
```

vfprintf - vsprintf

A similar program, rewritten for compatibility with the ANSI C standard:

```
#include <stdio.h>
#include <stdarg.h>

main( )
{
    int line = 1;
    char *filename = "EXAMPLE";
    .
    .
    .
    error("Error: line %d, file %s\n", line, filename);
    .
    .
    .
    error("Syntax error\n");
}

error(fmt)
char *fmt;
{
    va_list arg_ptr;
    va_start(arg_ptr, fmt);
    /* arg_ptr now points to argument after format string */
    vprintf(fmt, arg_ptr);
    va_end(arg_ptr);
}
```

Output:

```
Error: line 1, file EXAMPLE
Syntax error
```

■ Summary

`# include <io.h>` Required only for function declarations

```
int write(handle, buffer, count);
int handle;
char *buffer;
unsigned int count;
```

Handle referring to open file
Data to be written
Number of bytes

■ Description

The **write** function writes *count* bytes from *buffer* into the file associated with *handle*. The write operation begins at the current position of the file pointer (if any) associated with the given file. If the file is open for appending, the operation begins at the current end of the file. After the write operation, the file pointer (if any) is increased by the number of bytes actually written.

■ Return Value

The **write** function returns the number of bytes actually written. The return value may be positive but less than *count* (for example, when running out of space on a disk before *count* bytes are written). A return value of -1 indicates an error, and **errno** is set to one of the following values:

Value	Meaning
EACCES	File is read only or locked against writing.
EBADF	Invalid file handle.
ENOSPC	No space left on device.

If you are writing more than 32K (the maximum size for type **int**) to a file, the return value should be of type **unsigned int**. (See the example that follows.) However, the maximum number of bytes that can be written to a file is 65534, since 65535 (or 0xFFFF) is indistinguishable from -1, and so would return an error.

If the given file was opened in text mode, each line-feed character (LF) is replaced with a carriage-return-line-feed pair (CR-LF) in the output. The replacement does not affect the return value.

write

■ See Also

fwrite, open, read

Note

When writing to files opened in text mode, a character is treated as the logical end-of-file. When writing to a device, a character in the buffer causes output to be terminated.

■ Example

```
#include <io.h>
#include <stdio.h>
#include <fcntl.h>

char buffer[60000];

main()
{
    int fh;
    unsigned int nbytes = 60000, byteswritten;

    if ((fh = open("c:/data/conf.dat", O_WRONLY)) == -1) {
        perror("open failed on output file");
        exit(1);
    }
    if ((byteswritten = write(fh,buffer,nbytes)) == -1)
        perror("");
    else
        printf("Wrote %u bytes to file\n", byteswritten);
    .
    .
}
```

Appendices

- (A Error Messages 431
- (B A Common Library for XENIX and MS-DOS 437

()

2

()

()

Appendix A

Error Messages

A.1 Introduction 433

A.2 errno Values 433

A.3 Math Errors 436

(

S

(

.

(

A.1 Introduction

This appendix lists and describes the values to which the **errno** variable can be set when an error occurs in a call to a library routine. Note that only some routines set the **errno** variable. The reference pages for the routines that set **errno** upon error explicitly mention the **errno** variable. (The reference pages are located in Part 2 of this manual.) If no mention of **errno** occurs, the routine does not set **errno**.

An error message is associated with each **errno** value. This message, along with a user-supplied message, can be printed by using the **perror** function.

The value of **errno** reflects the error value for the last call that set **errno**. The **errno** value is not automatically cleared by later successful calls. Thus, to obtain accurate results, you should test for errors and print error messages, if desired, immediately after a call.

The include file **errno.h** contains the definitions of the **errno** values. However, not all of the definitions given in **errno.h** are used under MS-DOS. The full set of values is provided in the include file to maintain compatibility with the XENIX and UNIX include files having the same name.

This appendix lists only the **errno** values used under MS-DOS. For the complete listing of **errno** values, see the **errno.h** include file.

Also listed in this appendix are the errors produced by math routines when an error occurs. These errors correspond to the exception types defined in **math.h** and returned by the **matherr** function when a math error occurs.

A.2 **errno** Values

Table A.1 gives the **errno** values used on MS-DOS, the system error message corresponding to each value, and a brief description of the circumstances that cause the error.

Table A.1
errno Values and Their Meanings

Value	Message	Description
E2BIG	Arg list too long.	The argument list exceeds 128 bytes, or the space required for the environment information exceeds 32K bytes.
EACCES	Permission denied.	Access denied: the file's permission setting does not allow the specified access. This error can occur in a variety of circumstances; it signifies that an attempt was made to access a file (or, in some cases, a directory) in a way that is incompatible with the file's attributes. For example, the error can occur when an attempt is made to read from a file that is not open, to open an existing read-only file for writing, or to open a directory instead of a file. Under MS-DOS 3.0 and later, EACCES may also indicate a locking or sharing violation. The error can also occur in an attempt to rename a file or directory or to remove an existing directory.
EBADF	Bad file number.	The specified file handle is not a valid file-handle value or does not refer to an open file; or an attempt was made to write to a file or device opened for read-only access (or vice versa).
EDEADLOCK	Resource deadlock would occur.	Locking violation: the file cannot be locked after 10 attempts (MS-DOS Version 3.0 and later only).
EDOM	Math argument.	The argument to a math function is not in the domain of the function.
EEXIST	File exists.	The O_CREAT and O_EXCL flags are specified when opening a file, but the named file already exists.

Table A.1 (*continued*)

Value	Message	Description
EINVAL	Invalid argument.	An invalid value was given for one of the arguments to a function. For example, the value given for the origin when positioning a file pointer is before the beginning of the file.
EMFILE	Too many open files.	No more file handles are available, so no more files can be opened.
ENOENT	No such file or directory.	The specified file or directory does not exist or cannot be found. This message can occur whenever a specified file does not exist or a component of a path name does not specify an existing directory.
ENOEXEC	Exec format error.	An attempt is made to execute a file that is not executable or that has an invalid executable file format.
ENOMEM	Not enough core.	Not enough memory is available. This message can occur when insufficient memory is available to execute a child process or when the allocation request in an <code>sbrk</code> or <code>getcwd</code> call cannot be satisfied.
ENOSPC	No space left on device.	No more space for writing is available on the device (for example, the disk is full).
ERANGE	Result too large.	An argument to a math function is too large, resulting in partial or total loss of significance in the result. This error can also occur in other functions when an argument is larger than expected (for example, when the path-name argument to the <code>getcwd</code> function is longer than expected).
EXDEV	Cross-device link.	An attempt was made to move a file to a different device (using the <code>rename</code> function).

A.3 Math Errors

The following errors can be generated by the math routines of the C run-time library. These errors correspond to the exception types defined in **math.h** and returned by the **matherr** function when a math error occurs; see the **matherr** reference page in Part 2 of this manual for details.

Error	Description
DOMAIN	An argument to the function is outside the domain of the function.
OVERFLOW	The result is too large to be represented in the function's return type.
PLOSS	A partial loss of significance occurred.
SING	Argument singularity: an argument to the function has an illegal value (for example, passing the value 0 to a function that requires a nonzero value).
TLOSS	A total loss of significance occurred.
UNDERFLOW	The result is too small to be represented. (This condition is not currently supported.)

Appendix B

A Common Library for XENIX and MS-DOS

B.1	Introduction	439
B.2	Common Run-Time Routines	439
B.2.1	Common Routines for MS-DOS and XENIX	439
B.2.2	Common Routines for MS-DOS and UNIX System V	441
B.2.3	Routines Specific to MS-DOS	441
B.3	Common Global Variables	442
B.3.1	Common Variables for MS-DOS and XENIX	442
B.3.2	Common Variables for MS-DOS and UNIX System V	443
B.3.3	Variables Specific to MS-DOS	443
B.4	Common Include Files	443
B.4.1	Common Include Files for MS-DOS and XENIX	443
B.4.2	Common Include Files for MS-DOS and UNIX System V	444
B.4.3	Include Files Specific to MS-DOS	444
B.5	Differences Between Common Routines	444
B.5.1	abort	445
B.5.2	access	445
B.5.3	chdir	445
B.5.4	chmod	445

B.5.5	creat	446
B.5.6	exec	446
B.5.7	fopen, freopen	447
B.5.8	fread	448
B.5.9	fseek	448
B.5.10	fstat	448
B.5.11	ftell	449
B.5.12	ftime	449
B.5.13	fwrite	450
B.5.14	getpid	450
B.5.15	locking	450
B.5.16	lseek	451
B.5.17	open	451
B.5.18	read	451
B.5.19	signal	451
B.5.20	stat	452
B.5.21	system	453
B.5.22	umask	453
B.5.23	unlink	453
B.5.24	utime	453
B.5.25	write	454

B.1 Introduction

This appendix lists and describes routines from the Microsoft C Run-Time Library for MS-DOS that operate compatibly with C library routines on XENIX systems. The routines provide an identical interface to a set of operations useful on both XENIX and MS-DOS.

The XENIX and MS-DOS common library routines operate compatibly with UNIX library routines as well. In addition, the Microsoft C Compiler Run-Time Library for MS-DOS contains several routines that are compatible with UNIX System V routines but that are not currently implemented on XENIX.

With the exception of error returns, the math functions in the Microsoft C Compiler Run-Time Library for MS-DOS operate compatibly with the XENIX routines of the same names. Error returns for most math routines in the MS-DOS library have been upgraded for compatibility with UNIX System V math-error handling.

B.2 Common Run-Time Routines

The sections below list routines from the MS-DOS C library that are compatible with XENIX and UNIX System V routines. Routines specific to the MS-DOS environment are also listed.

B.2.1 Common Routines for MS-DOS and XENIX

The following is a list of the common routines for MS-DOS and XENIX. The MS-DOS routines are compatible with the XENIX routines of the same names, except that routines marked by an asterisk (*) have a slightly different operation or meaning in the MS-DOS environment than they do under XENIX. These differences are fully described in later sections of this appendix. Math routines marked with a dagger (†) implement UNIX System V-style error returns on MS-DOS.

abort*	execv*	getchar	perror	strncat
abs	execve*	getcwd	pow†	strcmp
access*	execvp*	getenv	printf	strcpy
acos†	execvpe*	getpid*	putc	strpbrk
asctime	exit	gets	putchar	strrchr
asin†	exp	getw	puts	strspn
assert	fabs	gmtime	putw	strtod
atan2†	fclose	hypot	qsort	strtok
atan†	fcvt	isalnum	rand	strtol
atof	fdopen	isalpha	read*	swab
atoi	feof	isascii	realloc	system*
atol	ferror	iscntrl	rewind	tan†
bessel†, ††	fflush	isdigit	rmtmp	tanh†
bsearch	fgetc	isgraph	sbrk	tempnam
cabs	fgets	islower	scanf	time
calloc	fileno	isprint	setbuf	tmpfile
ceil	floor	ispunct	setjmp	tmpnam
chdir*	fmod	isspace	setvbuf	toascii
chmod*	fopen*	issupper	signal*	tolower
chsize	fprintf	isxdigit	sin†	_tolower
clearerr	fputc	ldexp†	sinh†	toupper
close	fputs	lfind	sprintf	_toupper
cos†	fread*	localtime	sqrt†	tzset
cosh†	free	locking*	srand	umask*
creat*	freopen*	log10†	sscanf	ungetc
ctime	frexp	log†	stat*	unlink*
difftime	fscanf	longjmp	strcat	utime*
dup	fseek*	lsearch	strchr	vfprintf
dup2	fstat*	lseek*	strcmp	vprintf
ecvt	ftell*	malloc	strcpy	vsprintf
execl*	ftime*	mktemp	strcspn	write*
execl*	fwrite*	modf	strupr	
execlp*	gcvt	onexit	strerror	
execle*	getc	open*	strlen	

* Operates differently or has different meaning under MS-DOS than under XENIX

† Implements UNIX System V-style error returns

†† The bessel routine does not correspond to a single function, but to six functions named **j0**, **j1**, **jn**, **y0**, **y1**, and **yn**.

B.2.2 Common Routines for MS-DOS and UNIX System V

The XENIX-compatible routines listed in the previous section are also compatible with the routines of the same names in UNIX System V environments. In addition, the following MS-DOS routines are compatible with UNIX System V routines by the same name. These routines are not implemented on XENIX.

alloca	memchr	memicmp
matherr	memcmp	memset
memccpy	memcpy	putenv

Note that most of the math functions in the MS-DOS library implement error handling in the same manner as the UNIX System V routines of the same name. The math routines marked with a dagger (\dagger) in the list of common routines for MS-DOS and XENIX (see Section B.2.1) implement System V-style error handling.

B.2.3 Routines Specific to MS-DOS

The routines listed below are available only in the MS-DOS C library. Programmers who are writing code to be ported to XENIX systems should avoid using these routines.

FP_OFF	flushall	labs	spawnlp
FP_SEG	_fmalloc	ltoa	spawnlpe
bdos	fmsbintoieee	_memavl	spawnv
cgets	_fmsize	mkdir	spawnve
_clear87	_fpreset	movedata	spawnvp
_control87	fputchar	_msize	spawnvpe
cprintf	_freect	_nfree	stackavail
cputs	getch	_nmalloc	_status87
cscanf	getche	_nmsize	strcmpl
dieetombsbin	alloc	outp	strlwr
bmsbintoieee	hfree	putch	strncmpi
dosexterr	inp	remove	strnicmp
eof	int86	rename	strnset
_exit	int86x	rmdir	strrev
fcloseall	intdos	segread	strset

<code>_ffree</code>	<code>intdosx</code>	<code>setmode</code>	<code>strupr</code>
<code>fgetchar</code>	<code>isatty</code>	<code>sopen</code>	<code>tell</code>
<code>fleetomsbin</code>	<code>itoa</code>	<code>spawnl</code>	<code>ultoa</code>
<code>filelength</code>	<code>kbhit</code>	<code>spawnle</code>	<code>ungetch</code>

B.3 Common Global Variables

The sections below list global variables used in the MS-DOS C library that are also used in XENIX and UNIX environments. The variables specific to the MS-DOS environment are also listed.

B.3.1 Common Variables for MS-DOS and XENIX

The following is a list of global variables used in the run-time library and available in both the MS-DOS and XENIX environments:

`daylight`
`environ`
`errno`
`sys_errlist`
`sys_nerr`
`timezone`
`tzname`

Note

Not all values of `errno` available on XENIX are used by the MS-DOS run-time library.

B.3.2 Common Variables for MS-DOS and UNIX System V

The XENIX-compatible global variables listed in the Section B.3.1 are also available in UNIX System V environments. There are no additional common variables for MS-DOS and UNIX System V.

B.3.3 Variables Specific to MS-DOS

The following global variables are available only in the MS-DOS C library. Programmers who are writing code to be ported to XENIX systems should avoid using these variables.

```
_doserrno  
_osmajor  
_psp  
_fmode  
_osminor
```

B.4 Common Include Files

Structure definitions, return value types, and manifest constants used in the descriptions of some of the common routines may vary from environment to environment and are therefore fully defined in a set of include files for each environment. Include files provided with the MS-DOS C library are compatible with include files of the same name on XENIX and UNIX systems. Some additional include files are compatible with include files of the same name in UNIX System V environments.

Sections B.4.1 and B.4.2 list the MS-DOS include files that are compatible with XENIX and UNIX System V. The include files that apply only to MS-DOS environments are listed in Section B.4.3.

B.4.1 Common Include Files for MS-DOS and XENIX

The following MS-DOS include files are compatible with the XENIX (and UNIX) include files of the same name:

assert.h	math.h	stdio.h	sys\timeb.h
ctype.h	setjmp.h	sys\locking.h	sys\types.h
errno.h	signal.h	sys\stat.h	time.h
fcntl.h			

B.4.2 Common Include Files for MS-DOS and UNIX System V

The XENIX-compatible include files listed in Section B.4.1 are also compatible with the include files of the same names in UNIX System V environments. In addition, the names of the following MS-DOS include files correspond to UNIX System V include files; however, the MS-DOS include files may not contain all the constants and types defined in the corresponding UNIX System V include files.

malloc.h
string.h
memory.h
varargs.h
search.h

B.4.3 Include Files Specific to MS-DOS

The following include files are used only in MS-DOS environments and do not have counterparts on XENIX and UNIX systems:

conio.h	process.h	sys\utime.h
direct.h	share.h	v2tov3.h
dos.h	stdarg.h	
io.h	stdlib.h	

B.5 Differences Between Common Routines

Sections B.5.1 through B.5.25 explain how the MS-DOS routines in the common library for XENIX and MS-DOS differ from their XENIX counterparts. These descriptions are intended to be used in conjunction with the more detailed descriptions of MS-DOS functions provided in the reference section (Part 2 of this manual) and with the descriptions of the XENIX routines in the appropriate XENIX manual.

B.5.1 abort

The MS-DOS version of the **abort** routine terminates the process by a call to an exit routine rather than through a signal. Control is returned to the parent (calling) process with an exit status of 3 and the following message is printed to standard error:

Abnormal program termination

No core dump occurs on MS-DOS.

B.5.2 access

The **access** routine checks the access to a given file. Under MS-DOS, the real and effective user IDs are nonexistent. The permission (access) setting can be any combination of the following values:

Value	Meaning
04	Read
02	Write
00	Check for existence

The "Execute" access mode (01) is not implemented.

In case of error, only the **EACCES** and **ENOENT** values may be returned for **errno** on MS-DOS.

B.5.3 chdir

In case of error, only the **ENOENT** value may be returned for **errno** on MS-DOS.

B.5.4 chmod

The **chmod** routine can set the "owner" access permissions for a given file, but all other permission settings are ignored. The mode argument can be any one of the constant expressions shown in the left-most column below; the equivalent XENIX value is shown in the right-most column.

Constant Expression	Meaning	XENIX Value
S_IREAD	Read by owner	0400
S_IWRITE	Write by owner	0200
S_IREAD S_IWRITE	Read and write by owner	0000

The **S_IREAD** and **S_IWRITE** constants are defined in the **sys\stat.h** include file. Note that the OR operator (**|**) is used to combine these constants to form read and write permission.

If write permission is not given, the file is treated as a read-only file. Giving write-only permission is allowed, but has no effect; under MS-DOS, all files are readable.

In case of error, only the **ENOENT** value may be returned for **errno** on MS-DOS.

B.5.5 creat

The **creat** routine creates a new file or prepares an existing file for writing. If the file is created, the access permissions are set as defined by the mode argument. Only "owner" permissions are allowed (see **chmod** above).

In case of error, only the **EACCES**, **EMFILE**, and **ENOENT** values may be returned for **errno** on MS-DOS.

Use of the **open** routine is preferred over **creat** when creating or opening files in both MS-DOS and XENIX environments.

B.5.6 exec

The MS-DOS versions of the **exec**, **execle**, **execlp**, **execlepe**, **execv**, **execve**, **execvpe**, and **execvp** routines overlay the calling process, as in the XENIX environment. If there is not enough memory for the new process, the **exec** routine will fail and return to the calling process. Otherwise, the new process begins execution.

Under MS-DOS, the **exec** routines *do not* perform the following functions:

- Use the close-on-exec flag to determine open files for the new process.
- Disable profiling for the new process (profiling is not available under MS-DOS).
- Pass signal settings to the child process. Under MS-DOS, all signals (including signals set to be ignored) are reset to the default in the child process.

The combined size of all arguments (including the program name) in an **exec** routine under MS-DOS must not exceed 128 bytes.

In case of error, the **E2BIG**, **EACCES**, **ENOENT**, **ENOEXEC**, and **ENOMEM** values may be returned for **errno** on MS-DOS. In addition, the **EMFILE** value may be used; under MS-DOS, the file must be opened to determine whether or not it is executable.

B.5.7 **fopen**, **freopen**

The MS-DOS versions of the **fopen** and **freopen** routines open stream files just as they do in the XENIX environment. However, under MS-DOS the following additional values for the *type* string are available:

Value	Meaning
t	Opens the file in text mode. Opening a file in this mode causes translation of carriage-return-line-feed (CR-LF) character combinations into a single line feed (LF) on input. Similarly, on output, line feeds are translated into CR-LF combinations.
b	Opens the file in binary mode. This mode suppresses translation.

See the MS-DOS reference pages (in Part 2 of this manual) for the **fopen** and **freopen** routines to obtain more information on the default mode setting.

The MS-DOS and XENIX versions of these routines also differ in their interpretation of append mode ("a" or "a+"). When append mode is specified in the MS-DOS version of **fopen** or **freopen**, the file pointer is repositioned at the end of the file before any write operation. Thus all write operations take place at the end of the file.

In the XENIX versions, all write operations take place at the current position of the file pointer. In append mode, the file pointer is initially positioned at the end of the file, but if the file pointer is later repositioned, write operations take place at the new position rather than at the end of the file.

B.5.8 fread

The MS-DOS **fread** routine uses the low-level **read** function to carry out read operations. If the file has been opened in text mode, **read** replaces each CR-LF pair read from the file with a single LF character. The number of bytes returned is the number of bytes remaining after the CR-LF pairs have been replaced. Thus the return value may not always correspond to the actual number of bytes read. This is considered normal and has no implications for detecting the end of the file.

B.5.9 fseek

The MS-DOS version of the **fseek** routine moves the file pointer to the given position, just as in the XENIX environment. However, for streams opened in text mode, **fseek** has limited use because carriage-return-line-feed translations can cause **fseek** to produce unexpected results. The only **fseek** operations guaranteed to work on streams opened in text mode are: seeking with an offset of 0 relative to any of the origin values, or seeking from the beginning of the file with an offset value returned from a call to **ftell**.

B.5.10 fstat

MS-DOS does not make as much information available for file handles as it does for full path names; thus the MS-DOS version of **fstat** returns less useful information than does the **stat** routine. The MS-DOS **fstat** routine can detect device files, but it must not be used with directories.

The structure returned by **fstat** contains the following members:

Member	Meaning
st_mode	User read and write bits reflect the file's permission setting. The S_IFCHR bit is set for a device; otherwise, the S_IFREG bit is set.

st_ino	Not used.
st_dev	Either the drive number of the disk containing the file, or the file handle in the case of a device.
st_rdev	Either the drive number of the disk containing the file, or the file handle in the case of a device.
st_nlink	Always 1.
st_uid	Not used.
st_gid	Not used.
st_size	Size, in bytes, of the file.
st_atime	Time of last modification of file.
st_mtime	Time of last modification of file (same as st_atime).
st_ctime	Time of last modification of file (same as st_atime and st_mtime).

In case of error, only the **EBADF** value may be returned for **errno** on MS-DOS.

B.5.11 **f.tell**

The MS-DOS version of the **f.tell** routine gets the current file pointer position, just as in the XENIX environment. However, for streams opened in text mode, the value returned by **f.tell** may not reflect the physical byte offset, since text mode causes carriage-return-line-feed translation. The **f.tell** routine can be used in conjunction with the **f.seek** routine to remember and return to file locations correctly.

B.5.12 **f.time**

Unlike the system time on XENIX systems, the MS-DOS system time does not include the concept of a default time zone. Instead, **f.time** uses the value of an MS-DOS environment variable named **TZ** to determine the time zone. The user can set the default time zone by setting the **TZ** variable. If **TZ** is not explicitly set, the default time zone corresponds to the Pacific time zone. See the reference page for **tzset** in Part 2 of this manual for details on the **TZ** variable.

B.5.13 **fwrite**

The MS-DOS **fwrite** routine uses the low-level **write** function to carry out write operations. If the file was opened in text mode, every line-feed (LF) character in the output is replaced by a carriage-return-line-feed (CR-LF) pair before being written. This does not affect the return value.

B.5.14 **getpid**

The **getpid** routine returns a process-unique number. Although the number may be used to uniquely identify the process, it does not have the same meaning as the process ID returned by **getpid** in the XENIX environment.

B.5.15 **locking**

The MS-DOS and XENIX versions of the **locking** routine differ in several respects, as listed below:

1. Under MS-DOS, it is not possible to lock a file only against write access; locking a region of a file prevents both reading and writing in that region. This means that setting **LK_RLCK** in the **locking** call is equivalent to setting **LK_LOCK**, and setting **LK_NBRLCK** is equivalent to setting **LK_NBLCK**.
2. On MS-DOS, specifying **LK_LOCK** or **LK_RLCK** will *not* cause a program to wait until the specified region of a file is unlocked. Instead, up to ten attempts are made to lock the file (one attempt per second). If the lock is still unsuccessful after 10 seconds, the **locking** function returns an error value.

On XENIX, if the first attempt at locking fails, the locking process “sleeps” (suspends execution) and periodically “wakes” to attempt the lock again. There is no limit on the number of attempts, and the process can continue indefinitely.
3. On MS-DOS, locking of overlapping regions of a file is not allowed.
4. On MS-DOS, if more than one region of a file is locked, only one region can be unlocked at a time, and the region must correspond to a region that was previously locked. You cannot unlock more than one region at a time, even if the regions are adjacent.

B.5.16 lseek

In case of error, only the **EBADF** and **EINVAL** values may be returned for **errno** on MS-DOS.

B.5.17 open

The **open** routine opens a file handle for a named file, just as in the XENIX environment. However, two additional *oflag* values (**O_BINARY** and **O_TEXT**) are available and the **O_NDELAY** and **O_SYNCW** values are not available.

The **O_BINARY** flag causes the file to be opened in binary mode, regardless of the default mode setting. Similarly, the **O_TEXT** flag causes the file to be opened in text mode.

In case of error, only the **EACCES**, **EEXIST**, **EMFILE**, and **ENOENT** values may be used for **errno** on MS-DOS.

B.5.18 read

The MS-DOS version of the **read** routine reads characters from the file given by a file handle, just as in the XENIX environment. However, if the file has been opened in text mode, **read** replaces each CR-LF pair read from the file with a single LF character. The number of bytes returned is the number of bytes remaining after the CR-LF pairs have been replaced. Thus the return value may not always correspond to the actual number of bytes read. This is considered normal and has no implications for detecting an end-of-file condition.

In case of error, only the **EBADF** value may be used for **errno** on MS-DOS.

B.5.19 signal

The MS-DOS version of the **signal** routine can only handle the **SIGINT** and **SIGFPE** signals. In MS-DOS, **SIGINT** is defined to be INT 23H (the signal), while **SIGFPE** corresponds to floating-point exceptions that are not masked.

On MS-DOS, child processes executed through the **exec** or **spawn** routines do not inherit the signal settings of the parent process. All signal settings (including signals set to be ignored) are reset to the default settings in the child process.

The MS-DOS version of **signal** uses only **EINVAL** for **errno**.

B.5.20 stat

The **stat** routine returns a structure defining the current status of the given file or directory. The structure members returned by **stat** have the following names and meanings on MS-DOS:

Value	Meaning
st_mode	User read and write bits reflect the file's permission setting. The S_IFDIR bit is set for a device; otherwise, the S_IFREG bit is set.
st_ino	Not used.
st_dev	Drive number of the disk containing the file.
st_rdev	Drive number of the disk containing the file.
st_nlink	Always 1.
st_uid	Not used.
st_gid	Not used.
st_size	Size, in bytes, of the file.
st_atime	Time of last modification of file.
st_mtime	Time of last modification of file (same as st_atime).
st_ctime	Time of last modification of file (same as st_atime and st_mtime).

In case of error, only the **ENOENT** value may be returned for **errno** on MS-DOS.

B.5.21 system

The **system** routine passes the given string to the operating system for execution. For MS-DOS to execute this string, the full path name of the directory containing must be assigned to the environment variable. The **system** call returns an error if cannot be found using these variables.

In case of error, only the **E2BIG**, **ENOENT**, **ENOEXEC**, and **ENOMEM** values may be returned for **errno** on MS-DOS.

B.5.22 umask

The **umask** routine can set a mask for “owner” read and write access permissions only. All other permissions are ignored. (See the discussion of the **access** routine above for details.)

B.5.23 unlink

The MS-DOS version of the **unlink** routine always deletes the given file. Since MS-DOS does not implement multiple “links” to the same file, unlinking a file is the same as deleting it.

In case of error, only the **EACCES** and **ENOENT** values may be returned for **errno** on MS-DOS.

B.5.24 utime

The MS-DOS **utime** routine sets the file modification time only; MS-DOS does not maintain a separate access time.

In case of error, the **EACCES** and **ENOENT** values may be returned for **errno** on MS-DOS. In addition, the **EMFILE** value may be used; under MS-DOS, the file must be opened to set the modification time.

B.5.25 write

The **write** routine writes a specified number of characters to the file named by the given file handle, just as in the XENIX environment. However, if the file has been opened in text mode, every line-feed (LF) character in the output is replaced by a carriage-return-line-feed (CR-LF) pair before being written. This does not affect the return value.

In case of error, only the **EBADF** and **ENOSPC** values may be returned for **errno** on MS-DOS.

Index

- / (forward slash), as path-name delimiter, 21
- abort, 91
 - XENIX version, differences from, 445
- abs, 71
- abs function, 93
- abs macro, 88
- Absolute value
 - abs function, 93
 - cabs function, 115
 - fabs function, 160
 - labs function, 257
- access, 45, 94
- Access mode, 165, 188, 205
- access, XENIX version, differences
 - from, 445
- acos, 26, 58, 96
- alloca, 60, 98
- Allocation. *See* Memory allocation
 - _amblksize variable, 31
- Appending, 166, 188, 205, 298, 354
- Arc
 - cosine function, 96
 - sine function, 102
 - tangent function, 106
- arg0, MS-DOS considerations, 25
- Argument
 - lists, variable, 419, 424
 - singularity, 274
 - type checking, 5, 17, 18
 - type lists, 17
- Arguments
 - macros, with side effects, 15
 - notational conventions, 8
 - variable number, 18, 71
 - variable-length number, 419, 424
- asctime, 70, 100
- asin, 58, 102
 - floating-point support, 26
- assert, 71, 104
- assert.h, 72
- assert.h, contents, 76
- Assertions, 104
- atan, 58, 106
- atan
 - floating-point support, 26
- atan2, 58, 106
 - floating-point support, 26
- atof, 44, 107
 - floating-point support, 26
- atoi, 44, 107
- atol, 44, 107
- Backslash (\) as
 - escape character, 22
 - path-name delimiter, 21
- bdos, 63, 109
- bessel, 58, 111
 - bessel
 - floating-point support, 26
- Bessel functions, 111
- Binary
 - format, conversion to IEEE
 - double precision, 141
 - floating point, 179
- int
 - reading, 232
 - writing, 319
- mode, 23, 34, 166, 189, 206, 299, 346, 355
 - search, 113, 259
- BINMODE.OBJ, 23, 34
- Bold capitals, use of, 8
- Bold font, use of, 8
- Break value, 334
- bsearch, 67, 113
- Buffer manipulation
 - include file, 42
 - memccpy, 41, 277
 - memchr, 41, 278
 - memcmp, 41, 279
 - memcpy, 41, 280
 - memicmp, 41, 281
 - memset, 41, 283
 - movedata, 41, 288
- Buffering, 46, 51
 - preopened streams, 51

- Buffers
 assigning, 343
 comparing, 279, 281
 copying, 277, 280, 288
 overlapping moves, 280
 flushing, 52, 171, 183
 searching, 278
 setting characters in, 283
BUFSIZ constant, 49, 84
Byte order, swapping, 396
BYTEREGS type, 78
- cabs, 58, 115
 floating-point support, 26
calloc, 60, 116
- Carriage-return-line-feed translation.
 See Binary mode; Text mode
- Carry flag, 109, 241, 243, 246, 248
- Case sensitivity
 C language, 20
 MS-DOS, 20
 XENIX, 20
- ceil, 117
 floating-point support, 26
- Ceiling function, 117
- cgets, 56, 118
- Character conversion. *See* Character,
 classification and conversion
- Character
 classification and conversion
 include files, 43
 isalnum, 42, 250
 isalpha, 250
 isascii, 250
 iscntrl, 253
 isdigit, 253
 isgraph, 42, 253
 islower, 42, 253
 isprint, 42, 253
 ispunct, 42, 253
 isspace, 42, 253
 isupper, 42, 253
 isxdigit, 42, 253
 toascii, 42, 405
 -- tolower, 42, 405, 421
 tolower, 42, 405, 421
 -- toupper, 42, 405, 421
 toupper, 42, 405, 421
- device, 252
- Characters
 conversion to
 ASCII, 405
 lowercase, 405
 uppercase, 405
 reading, 175, 222, 324
 reading from console, 224
 with echo, 225
 reading from port, 240
 ungetting, 412, 414
 writing, 196, 313, 427
 writing to console, 315
 writing to port, 302
- chdir, 44, 120
 XENIX version, differences from, 445
- Child process, 151, 358
 effects on floating-point state of
 parent, 192
 signal settings, 153, 358
 translation mode, 153, 358
- chmod, 45, 121
 XENIX version, differences from, 445
- chsize, 45, 123
 -- clear87, 58, 125
 clearerr, 20, 47, 127
- Clearing
 end-of-file, streams, 127
 errors, 127
- close, 53, 128
- Command interpreter. *See*
 COMMAND.COM
- COMMAND.COM, 412
- Common library
 common routines listed, 439, 441
 global variables, 442
 include files, 443
 run-time routine, differences, 444
- Compatibility
 differences listed, 444
 global variables, 442
 include files, 443
 math routines, 439
 mode, 354
 run-time routines, 439
 UNIX, 439
 XENIX, 439
- complex type, 36, 80
- conio.h, 57
- conio.h, contents, 76
- Console, ungetting characters from,
 414

- _control87, 58, 129
- Conventions, notational, 8
- Conversion
 - characters to ASCII, 405
 - characters to lowercase, 405
 - characters to uppercase, 405
 - floating-point numbers to integers and fractions, 287
 - floating-point numbers to strings, 148, 163, 221
 - IEEE double to MS binary double, 141
 - IEEE floating point to MS binary floating point, 179
 - integers to strings, 255
 - long integers to strings, 272, 409
 - MS binary double to IEEE double, 141
 - MS binary floating point to IEEE floating point, 179
 - strings to floating-point values, 107
 - strings to lowercase, 380
 - strings to uppercase, 395
- cos, 58, 131
 - floating-point support, 26
- cosh, 58, 131
 - floating-point support, 26
- Cosine, 131
- cprintf, 56, 132
- cprintf
 - See also* printf family
 - argument-type-checking limitations, 18
- cputs, 57, 134
- creat, 53, 135
 - XENIX version, differences from, 446
- CR-LF translation. *See* Binary mode;
 - Text mode
- cscanf, 57, 137
- cscanf
 - See also* scanf family
 - argument-type-checking limitations, 18
- ctime, 70, 139
- Ctype routines, 250, 254
 - _ctype variable, 77
 - ctype.h, 43
 - ctype.h, contents, 76
- Data conversion
 - See also* Conversion
 - atof, 44, 107
 - atoi, 44, 107
 - atol, 44, 107
 - ecvt, 44, 148
 - fcvt, 44, 163
 - gcvt, 44, 221
 - include files, 44
 - itoa, 44, 255
 - ltoa, 44, 272
 - strtod, 44, 390
 - strtol, 44, 390
 - ultoa, 44, 409
- Data items
 - reading, 199
 - writing, 219
- Date routines. *See* Time routines
- daylight variable, 32, 407
- Deallocating memory, 173, 201, 237, 292
- Declarations, function. *See* Function declarations
- Default translation mode, 23, 34, 299, 346, 354
 - changing, 23
 - child process, used in, 153, 358
 - overriding, 24
- Delimiters for path-name components.
 - See* Path names
- dieetombsin, 141
- difftime, 70, 142
- direct.h, 45
- direct.h, contents, 77
- Directories
 - changing, 120
 - creating, 284
 - current working directory, getting, 226
 - deleting, 332
 - renaming, 329
- Directory control
 - chdir, 44, 120
 - chmod, 121
 - getcwd, 44, 226
 - include files, 45
 - mkdir, 44, 284
 - remove, 328
 - rmdir, 44
 - unlink, 416

- Directory names, notational
 - conventions, 8
- dmsbintoieee, 141
- DOMAIN, 274, 436
 - _doserrno variable, 33
- DOSERROR type, 36, 78, 144
- dosexterr, 63, 144
 - MS-DOS considerations, 24
- dos.h, 63
- dos.h, contents, 77
- Double brackets, use of, 9
- dup, 24, 53, 146
 - dup2, 53, 146
 - MS-DOS considerations, 24
- Dynamic allocation. *See* Memory allocation
- \ (backslash) as
 - escape character, 22
 - path-name delimiter, 21
- E2BIG, 434
- EACCES, 434
- EBADF, 434
- Echoing characters, 225
- ecvt, 44, 148
- EDEADLOCK, 434
- EDOM, 434
- EEXIST, 434
- EINVAL, 435
- Ellipsis dots, use of, 9
- EMFILE, 435
- End-of-file condition, 20
- End-of-file
 - low-level I/O, 150
 - stream I/O, 168
 - clearing, 127, 331
- ENOENT, 435
- ENOEXEC, 435
- ENOMEM, 435
- ENOSPC, 435
- environ variable, 35, 228, 317
- Environment table, 35, 72, 228, 316
- Environment variable names,
 - notational conventions, 8
- Environment variables, 228, 316
- eof, 20, 53, 150
- EOF constant, 49, 84
- ERANGE, 435
- errno variable, 19, 20, 33, 56, 72, 78, 83, 303, 377, 433
 - errno.h, 433
 - errno.h, contents, 78
- Error
 - handling, 19
 - logic errors, 104
 - MS-DOS error codes, 33
 - MS-DOS system calls, 144
 - perror, 303
 - stream operations, 20
 - strerror, 377
 - indicator, 20, 53, 127, 169
 - messages, 433
 - user supplied, 303, 377
 - returns, 19
- Euclidean distance, 239
- exception type, 36, 80, 274
- EXDEV, 435
- exec family, 64, 151
 - exec routines, differences between, 66
 - MS-DOS considerations, 25
 - path-name delimiters, 22
 - XENIX version, differences from, 446
- exec1, 64, 151
- exec2
 - See also* exec family
 - argument-type-checking limitations, 19
 - XENIX version, differences from, 446
- execle, 64, 151
- execle2
 - See also* exec family
 - argument-type-checking limitations, 19
 - XENIX version, differences from, 446
- execclp, 64, 151
- execelp
 - See also* exec family
 - argument-type-checking limitations, 19
 - XENIX version, differences from, 446
- execlepe, 64, 151
 - See also* exec family
 - argument-type-checking limitations, 19
 - XENIX version, differences from, 446
- Executing programs from within
 - programs, 151, 358
- execv, 64, 151
 - See also* exec family
 - XENIX version, differences from, 446
- execve, 64, 151
 - See also* exec family

- execve** (*continued*)
 XENIX version, differences from, 446
- execvp**, 64, 151
 See also exec family
 XENIX version, differences from, 446
- execvpe**, 64, 151
 See also exec family
 $_exit$, 65, 155
- exit**, 64, 155
 Exiting processes, 155
- exp**, 58, 157
 floating-point support, 26
- _expand**, 60, 158
- Exponential functions**
 exp, 157
 frexp, 208
 ldexp, 258
 log, 266
 log10, 266
 pow, 305
 sqrt, 364
- fabs**, 58, 160
 floating-point support, 26
- Far pointers**, 191
- fclose**, 47, 161
- fcloseall**, 47, 161
- fcntl.h**, contents, 79
- fcvt**, 44, 163
- fdopen**, 48, 165
- feof**, 20, 48, 168
- ferror**, 20, 48, 169
- fflush**, 48, 171
 $_ffree$, 60, 173
- fgetc**, 48, 175
- fgetchar**, 48, 175
- fgets**, 48, 177
- freeetombsin**, 179
- File handles**, 54
 duplication, 146
 predefined, 54
 stream, used with, 181
- File handling**
 access, 45, 94
 chmod, 45
 chsize, 45, 123
 filelength, 45, 180
 fstat, 45, 213
 include files, 45
 isatty, 45
- File handling** (*continued*)
 locking, 45, 263
 mktemp, 45, 285
 remove, 45
 rename, 45, 329
 setmode, 45, 346
 stat, 45, 369
 umask, 45, 410
 unlink, 45
- File-name conventions**, 20
- File names**, notational conventions, 8
- File permission mask**. *See* Permission mask
- File pointer**, 52, 55
 positioning, 211, 215, 270, 331, 400
- File status information**, 213, 369
- FILE**
 pointer, 46, 49
 structure, 49
 type, 36, 84
- filelength**, 45, 180
- fileno**, 48, 55, 181
- Files**
 changing size of, 123
 closing, 56, 128
 creating, 135, 298, 354
 deleting, 328, 416
 file pointer, positioning, 270, 400
 length, determination of, 180
 locking, 263
 modification time, setting of, 417
 opening, 54, 135, 298, 354
 reading characters from, 324
 renaming, 329
 status information, 213, 369
 temporary, 285
 writing characters to, 427
- float.h**, contents, 79
- Floating point not loaded**, 27
- Floating-point**
 control word, getting and setting, 129
 errors, recovery from, 192
 exceptions, 79, 350
 math package
 $_clear87$, 125
 $_control87$, 129
 $_fpreset$, 192
 reinitialization, 192
 $_status87$, 371

- Floating-point (*continued*)
 numbers, conversion to strings, 148, 163, 221
 ranges, 79
 status word, 125, 371
 support, 26
floor, 59, 182
 floating-point support, 26
flushall, 48, 183
Flushing buffers, 52, 171, 183
 _fmalloc, 60, 185
fmod, 59, 186
fmod
 floating-point support, 26
 _fmode variable, 23, 34
fmsbintoieee, 179
 _fmsize, 60, 187
fopen, 48, 188
 default translation mode, changing, 23
 default translation mode, overriding, 24
 XENIX version, differences from, 447
Formatted I/O, 132, 137, 194, 209, 306, 336, 363, 366, 424
Forward slash (/), as path-name
 delimiter, 21
FP_OFF, 63, 191
 _fpreset, 59, 192
fprintf, 48, 194
fprintf
 See also printf family
 argument-type-checking limitations, 18
FP_SEG, 63, 191
fputc, 48, 196
fputchar, 48, 196
fputs, 48, 198, 318
fread, 48, 199
 XENIX version, differences from, 448
free, 60, 201
 _freet, 60, 203
Freeing memory blocks, 173, 201, 237, 292
freopen, 48, 205
 XENIX version, differences from, 447
frexp, 59, 208
 floating-point support, 26
fscanf, 48, 209
 See also scanf family
 argument-type-checking limitations, 18
fseek, 48, 211
 XENIX version, differences from, 448
fstat, 45, 213
 XENIX version, differences from, 448
ftell, 48, 215
 XENIX version, differences from, 449
ftime, 70, 217
 XENIX version, differences from, 449
Function declarations, 17, 75
Functions, advantages over macros, 14
fwrite, 48, 219
 XENIX version, differences from, 450
gcvt, 44, 221
getc, 48, 222
getch, 57, 224
getchar, 48, 222
getche, 57, 225
getcwd, 44, 226
getenv, 72, 228
getpid, 65, 230
 XENIX version, differences from, 450
gets, 48, 231
getw, 48, 232
gmtime, 70, 234
Goto, nonlocal, 72, 267, 344
Greenwich mean time, 70, 234
halloc, 60, 236
Handle. *See* File handle
hfree, 60, 237
Huge arrays, use in library functions, 27
Huge pointers, use in library functions, 27
HUGE, 81
HUGE_VAL, 81
Hyperbolic cosine, 131
Hyperbolic sine, 353
Hyperbolic tangent, 399
hypot, 59, 239
 floating-point support, 26
Hypotenuse, 239

Identifiers, notational conventions, 8
 IEEE, converting to Microsoft binary
 double precision, 141
 floating point, 179
 Include files
 assert.h, 76
 buffer manipulation routines, used
 with, 42
 character classification and
 conversion, 43
 common library, use in, 443
 conio.h, 76
 console and port I/O, 57
 ctype.h, 76
 data conversion, 44
 direct.h, 77
 directory control, 45
 dos.h, 77
 errno.h, 78
 fcntl.h, 79
 file handling, 45
 float.h, 79
 function declarations, 75
 io.h, 79
 limits.h, 80
 low-level I/O, 54
 malloc.h, 80
 math routines, 59
 math.h, 80
 memory allocation, 61
 memory.h, 81
 miscellaneous routines, 72
 MS-DOS interface routines, 63
 naming conventions, 6
 notational conventions, 8
 process control, 66
 process.h, 81
 search.h, 82
 searching and sorting, 67
 setjmp.h, 82
 share.h, 82
 signal.h, 82
 stdarg.h, 83
 stddef.h, 83
 stdio.h, 83
 stdlib.h, 85
 stream I/O, 49
 string manipulation, 69
 string.h, 85
 sys\ locking.h, 86
 sys\ stat.h, 86

Include files (*continued*)
 sys\ timeb.h, 86
 sys\ types.h, 86
 sys\ utime.h, 87
 time routines, 70
 time.h, 87
 v2tov3.h, 87
 varargs.h, 87
 Initializing buffers. *See* Buffers, setting
 characters in
 inp, 56, 240
 Input and output. *See* I/O
 Input/Output. *See* I/O
 int86, 63, 241
 int86x, 63, 243
 intdos, 63, 246
 intdosx, 63, 248
 Integers
 conversion to strings, 255
 long, conversion to strings, 272, 409
 Interrupt signals, 350
 Interrupts. *See* MS-DOS interrupts
 _iob array, 84
 io.h, 45, 54
 io.h, contents, 79
 isalnum, 42, 250
 isalpha, 250
 isascii, 250
 isatty, 45, 252
 iscntrl, 253
 isdigit, 42, 253
 isgraph, 42, 253
 islower, 42, 253
 isprint, 42, 253
 ispunct, 42, 253
 isspace, 42, 253
 isupper, 42, 253
 isxdigit, 42, 253
 itoa, 44, 255, 409
 I/O
 buffered, 46
 console and port, 47
 cgets, 56, 118
 cprintf, 56, 132
 cputs, 56, 134
 cscanf, 56, 137
 getch, 56, 224
 getche, 56, 225
 include files, 57
 inp, 56, 240
 kbhit, 57, 256

- console and port (*continued*)
 - outp, 56, 302
 - putch, 56, 315
 - ungetch, 56, 414
- low level, 47
 - use of errno, 20
 - close, 53, 128
 - creat, 53, 135
 - dup, 53, 146
 - dup2, 53, 146
 - eof, 53, 150
 - error handling, 20, 56
 - include files, 54
 - lseek, 53, 270
 - open, 53, 298
 - read, 53, 324
 - sopen, 53, 354
 - tell, 53, 400
 - write, 53, 427
- stream, 46, 47
- Italics, use of, 8
- j0. *See* Bessel functions
- j1. *See* Bessel functions
- jmp_buf type, 36
- jn. *See* Bessel functions
- kbhit, 56, 256
- Keys, key sequences, notational conventions, 10
- Keystroke, testing for, 256
- Keywords, notational conventions, 8
- labs, 71, 257
- ldexp, 59, 258
 - floating-point support, 26
- Length of
 - files, 180
 - strings, 379
- lfind, 67, 259
- limits.h, contents, 80
- Lines
 - reading, 177, 231
 - writing, 318
- LINT_ARGS, 5, 18, 75
- Local time corrections, 32, 261, 407
- localtime, 70, 261
- locking, 45, 263
- locking (*continued*)
 - MS-DOS considerations, 24
 - XENIX version, differences from, 450
- locking.h. *See* sys\locking.h
- log function, 59, 266
 - floating-point support, 26
- log10 function, 59, 266
 - floating-point support, 26
- Logarithmic functions
 - log, 266
 - log10, 266
- Long integers, conversion to strings, 272
- Long pointers, 191
- longjmp, 71, 267
- lsearch, 68, 259
- lseek, 53, 270
 - XENIX version, differences from, 451
- ltoa, 44, 272
- Macros
 - advantages over functions, 14
 - arguments with side effects, 15, 43
 - notational conventions, 8
 - restrictions on use, 14
- malloc, 60, 273
- malloc.h, 61
- malloc.h, contents, 80
- Manifest constants, notational conventions, 8
- Mask. *See* Permission mask
- Math errors, 436
- matherr, 19, 59, 274
- math.h, 44, 59
- math.h, contents, 80
- max macro, 88
 - _memavl, 61, 276
- memccpy, 41, 277
- memchr, 41, 278
- memcmp, 41, 279
- memcpy, 41, 280
- memicmp, 41, 281
- Memory
 - allocation, 31
 - alloca, 60
 - available, determination of, 203
 - calloc, 60, 116
 - _expand, 60, 158
 - _ffree, 60, 173
 - _fmalloc, 60, 185

- allocation (*continued*)
 - _fmsize, 60, 187
 - free, 60, 201
 - _freect, 60, 203
 - malloc, 60, 236
 - hfree, 60, 237
 - include files, 61
 - malloc, 61, 273
 - _memavl, 61, 276
 - _msize, 61, 290
 - _nfree, 61, 292
 - _nmalloc, 61, 294
 - _nmsize, 61, 295
 - realloc, 61, 326
 - sbrk, 61, 334
 - stackavail, 61, 368
- models, use of with huge arrays and huge pointers, 27
- memory.h, 42
- memory.h, contents, 81
- memset, 41, 283
- min macro, 88
- mkdir, 44, 284
- mktemp, 45, 285
- modf, 59, 287
 - floating-point support, 26
- Modification time, 417
- movedata, 41, 288
- MS-DOS
 - commands, execution of from within programs, 397
 - considerations, 24
 - error codes, 33
 - version number, detection of, 34
 - interface routines
 - bdos, 63, 109
 - dosexterr, 63, 144
 - FP_OFF, 63
 - FP_SEG, 63
 - include files, 63
 - int86, 63, 241
 - int86x, 63, 243
 - intdos, 63, 246
 - intdosx, 63, 248
 - segread, 63, 342
 - interrupts
 - invoking, 241, 243
 - SIGINT, 350
 - system calls
 - error handling, 144
 - invoking, 109, 246, 248
- MS-DOS (*continued*)
 - version number, 34
 - _msize, 61, 290
- NDEBUG, 72, 76, 104
- _NFILE constant, 84
- _nfree, 61, 292
- _nmalloc, 61, 294
- _nmsize, 61, 295
- Nonlocal goto, 72, 267, 344
- Notational conventions, 8
- Null pointer, 84
- NULL, 83
- NULL
 - constant, 84
 - pointer, 49
- O_BINARY, 23, 34
- oflag. *See* Open flag
- onexit, 65, 296
- open, 53, 298, 346
 - argument-type-checking limitations, 18
 - default translation mode, changing, 23
 - default translation mode, overriding, 24
 - XENIX version, differences from, 451
- Open flag, 298, 354
- Optional arguments, notational conventions, 9
 - _osmajor variable, 25, 34
 - _osminor variable, 25, 34
- O_TEXT, 24
- outp, 57, 302
- Output. *See* I/O
- OVERFLOW, 274, 436
- Overlapping moves, 280
- Overlay of parent process, 359
- Parameters
 - variable-length number, 419, 424
 - variable number, 71
- Parent process, 152, 358
 - overlay, 359
 - suspension, 358
- Path names
 - delimiters, 20, 21

Path names (*continued*)
 notational conventions, 8
Path-name conventions, 20
Permission mask, 410
Permission setting, 135, 298, 354
 access, 94
 changing, 121
 umask, 410
 perror, 19, 71, 303
PLOSS, 274, 436
Port I/O. *See* I/O, console and port
Portability, 20
 See also Compatibility
Positioning file pointer, 211, 215, 270,
 331, 400
pow, 59, 305
 floating-point support, 26
Predefined
 handles, 54
 stream pointers, 50
printf, 48, 306
 argument-type-checking limitations,
 18
printf family
 floating-point support, 26
Printing. *See* Write operations
Process, defined, 65
Process control
 abort, 64, 91
 exec family, 64
 execl, 64, 151
 execle, 64, 151
 execlp, 64, 151
 execlepe, 64, 151
 execv, 64, 151
 execve, 64, 151
 execvp, 64, 151
 execvpe, 64, 151
 _exit, 155, 159
 exit, 64, 155, 159
 getpid, 65, 230
 include files, 66
 onexit, 65, 296
 signal, 65, 350
 spawn family, 65
 spawnl, 65, 358
 spawnle, 65, 358
 spawnlp, 65, 358
 spawnlpe, 65, 358
 spawnnv, 65, 358
 spawnve, 65, 358

Process control (*continued*)
 spawnvp, 65, 358
 spawnvpe, 65, 358
 system, 65, 397
Process ID, 230
process.h, 66
process.h, contents, 81
Program segment prefix, 35
Programming examples, notational
 conventions, 9
Pseudorandom integers, 323, 365
 _psp variable, 35
PSP. *See* Program segment prefix
ptrdiff_t, 83
putc, 48, 313
putch, 57, 315
putchar, 48, 313
putenv, 71, 316
puts, 48
putw, 48, 319

qsort, 68, 321
Quick sort, 321

rand, 71, 323
Random access, 211, 215, 270, 331, 400
Random-number generator, 323, 365
read, 53, 324
 end-of-file condition, 20
 XENIX version, differences from, 451
Read access. *See* Permission setting
Read operations
 binary int value from stream, 232
 character from stdin, 175, 222
 character from stream, 175, 222
 characters from file, 324
 data items from stream, 199
 formatted, 137, 209, 336, 366
 from console, 118, 137, 224
 checking for keystroke, 256
 with echo, 225
 from port, 240
 line from stdin, 231
 line from stream, 177
realloc, 61, 326
Reallocation
 -expand, 158
 realloc, 326
Redirection, 51, 55, 205

- Register, segment. *See Segment registers*
- REGS type, 36, 78
- Remainder function, 186
- remove, 45, 328
- rename, 45, 329
- Return value on error. *See Error returns*
- Reversing strings, 386
- rewind, 49, 331
- rmdir, 44, 332
- rmtmp, 49, 333
- Routines
- argument lists, variable-length
 - `va_arg`, 71, 419
 - `va_end`, 71, 419
 - `va_start`, 71, 419
 - `vfprintf`, 424
 - `vprintf`, 424
 - `vsprintf`, 424
 - math
 - `acos`, 58, 96
 - `asin`, 58, 102
 - `atan`, 58, 106
 - `atan2`, 58, 106
 - `bessel`, 58, 111
 - `cabs`, 58
 - `ceil`, 58, 117
 - `_clear87`, 58
 - `_control87`, 58
 - `cos`, 58, 131
 - `cosh`, 58, 131
 - `dieetomsbin`, 58
 - `dmsbintoieee`, 58
 - `errno`, use of, 19
 - error handling, 5, 19, 60
 - `exp`, 58, 157
 - `fabs`, 58, 160
 - `fieetomsbin`, 59
 - `floor`, 59, 182
 - `fmod`, 59, 186
 - `fmsbintoieee`, 59
 - `_fpreset`, 59
 - `frexp`, 59, 208
 - `hypot`, 59, 239
 - include files, 59
 - `ldexp`, 59, 258
 - `log`, 59, 266
 - `log10`, 59, 266
 - `matherr`, 59, 274
 - `modf`, 59, 287
 - math (*continued*)
 - `pow`, 59, 305
 - `sin`, 59, 353
 - `sinh`, 59, 353
 - `sqrt`, 59, 364
 - `_status87`, 59
 - `tan`, 59, 399
 - `tanh`, 59, 399
 - miscellaneous
 - `abs`, 71
 - `assert`, 71, 104
 - `getenv`, 71, 228
 - include files, 72
 - `labs`, 71
 - `longjmp`, 71, 267
 - `perror`, 71, 303
 - `putenv`, 71, 316
 - `rand`, 71, 323
 - `setjmp`, 71, 344
 - `srand`, 71, 365
 - `strerror`, 377
 - `swab`, 71, 396
 - Routines by category, 41
 - `sbrk`, 61, 334
 - `scanf`, 49, 336
 - See also* `scanf` family
 - argument-type-checking limitations, 18
 - `scanf` family
 - floating-point support, 26
 - Scanning. *See Read operations*
 - `search.h`, 68
 - `search.h`, contents, 82
 - Searching and sorting
 - `bsearch`, 67, 113
 - include files, 68
 - `lfind`, 67, 259
 - `lsearch`, 68, 259
 - `qsort`, 68, 321
 - Seed, 365
 - Segment registers, obtaining values, 342
 - `segread`, 63, 342
 - `setbuf`, 49, 51, 343
 - `setjmp`, 71, 344
 - `setjmp.h`, 72, 82
 - `setmode`, 24, 45, 346
 - `setvbuf`, 49, 51, 348
 - `share.h`, 82

- shflag. *See* Flag, sharing
Side effects in macro arguments, 15, 43
SIGFPE, 79, 350
SIGINT, 350
signal, 65, 350
 settings, child process, 153, 358
 XENIX version, differences from, 451
signal.h, 66, 82
sin, 59, 353
 floating-point support, 26
Sine, 353
SING, 274, 436
sinh, 59, 353
 floating-point support, 26
size_t, 83
Small capitals, use of, 10
sopen, 53, 354
 argument-type-checking limitations, 18
 MS-DOS considerations, 24
Sorting. *See* Searching and sorting
spawn family, 65, 358
 MS-DOS considerations, 25
 path-name delimiters, 22
 spawn routines, differences between, 66
spawnl, 65, 358
 See also spawn family
 argument-type-checking limitations, 19
spawnle, 65, 358
 See also spawn family
 argument-type-checking limitations, 19
spawnlp, 65, 358
 See also spawn family
 argument-type-checking limitations, 19
spawnlpe, 65, 358
 See also spawn family
 argument-type-checking limitations, 19
spawnnv, 65, 358
 See also spawn family
spawnv, 65, 358
 See also spawn family
spawnvpe, 65, 358
 See also spawn family
sprintf, 47, 363
- sprintf (*continued*)
 See also printf family
 argument-type-checking limitations, 18
sqrt, 59, 364
 floating-point support, 26
Square-root function, 364
rand, 71, 365
SREGS type, 36, 78
sscanf, 366
 See also scanf family
 argument-type-checking limitations, 18
- Stack environment
 restoring, 267
 saving, 344
stackavail, 61, 368
- Standard auxiliary. *See* stdaux
- Standard error. *See* stderr
- Standard input. *See* stdin
- Standard output. *See* stdout
- Standard print. *See* stdprn
- Standard types
 complex, 36, 80
 DOSERROR, 36, 78, 144
 exception, 36, 79, 274
 FILE, 36, 84
 jmp_buf, 36
 listed, 36
 REGS, 36, 78
 SREGS, 36, 78
 stat, 37, 86, 213, 369
 timeb, 37, 217
 time_t, 142
 tm, 37, 87, 234
 utimbuf, 37, 87, 417
 stat, 45, 369
 XENIX version, differences from, 452
 stat type, 37, 86, 213, 369
 stat.h. *See* sys\stat.h
 status87, 59, 371
 stdarg.h, contents, 83
 stdaux, 50
 buffering, 51
 default translation mode, overriding, 24
 file handle, 54
 translation mode, changing, 346
 stddef.h, contents, 83
 stderr, 50
 buffering, 51

- stderr (continued)*
- default translation mode, overriding, 24
 - file handle, 54
 - translation mode, changing, 346
- stdin*, 50
- buffering, 51
 - default translation mode, overriding, 24
 - file handle, 54
 - translation mode, changing, 346
- stdio.h*, 49
- stdio.h*, contents, 83
- stdlib.h*, 43, 44, 72
- stdlib.h*, contents, 85
- stdout*, 50
- buffering, 51
 - default translation mode, overriding, 24
 - file handle, 54
 - translation mode, changing, 346
- stdprn*, 50
- buffering, 51
 - default translation mode, overriding, 24
 - file handle, 54
 - translation mode, changing, 346
- strcat*, 68, 373
- strchr*, 68, 373
- strcmp*, 68, 373
- strcmpi*, 68, 373
- strcpy*, 68, 373
- strcspn*, 68, 373
- strdup*, 68, 373
- Stream I/O*, 46, 47
- See also* I/O, console and port
 - buffering, 51
 - clearerr, 47, 127
 - error handling, 20, 53
 - fclose, 47, 161
 - fcloseall, 47, 161
 - fdopen, 48, 165
 - feof, 48, 168
 - ferror, 48, 169
 - fflush, 48, 171
 - fgetc, 48, 175
 - fgetchar, 48, 175
 - fgets, 48, 177
 - fileno, 48, 181
 - flushall, 48, 183
 - fopen, 48, 188
- Stream I/O (continued)*
- fprintf*, 48, 194
 - fputc*, 48, 196
 - fputchar*, 48, 196
 - fputs*, 48, 198, 318
 - fread*, 48, 199
 - freopen*, 48, 205
 - fscanf*, 48, 209
 - fseek*, 48, 211
 - ftell*, 48, 215
 - fwrite*, 48, 219
 - getc*, 48, 222
 - getchar*, 48, 222
 - gets*, 48, 231
 - getw*, 48, 232
 - include files, 49
 - printf*, 48, 306
 - putc*, 48, 313
 - putchar*, 48, 313
 - puts*, 48
 - putw*, 48, 319
 - rewind*, 49, 331
 - rmtmp*, 49
 - scanf*, 49, 336
 - setbuf*, 49, 343
 - setvbuf*, 49
 - sprintf*, 49, 363
 - sscanf*, 49, 366
 - tmpnam*, 49
 - tmpfile*, 49
 - tmpnam*, 49
 - ungetc*, 49, 412
 - vfprintf*, 49, 424
 - vprintf*, 49, 424
 - vsprintf*, 49, 424
- Stream pointer*, 46
- Streams*
- appending, 166, 188, 205
 - buffering, 343
 - clearing errors, 127
 - closing, 52, 161
 - file handles for, 181
 - file-pointer positioning, 211, 215, 331
 - formatted I/O, 194, 209, 306, 336, 363, 366, 424
 - opening, 49, 165, 188
 - reading
 - binary int value, 232
 - characters, 175, 222
 - data items, 199
 - lines, 177, 231

Streams (*continued*)
 reopening, 205
 rewinding, 331
 stdaux, 50
 stderr, 50
 stdin, 50
 stdout, 50
 stdprn, 50
 translation mode, 166, 189, 206
 ungetting characters, 412
 writing
 binary int value, 319
 characters, 196, 313
 data items, 219
 lines, 318
 strings, 198
strerror, 19, 68, 377
strcmp, 68, 373
String manipulation
 include files, 69
 strcat, 68, 373
 strchr, 68, 373
 strcmp, 68, 373
 strcmpi, 68, 373
 strcpy, 68, 373
 strcspn, 68, 373
 strdup, 68, 373
 strerror, 68
 strcmp, 68, 373
 strlen, 68, 379
 strlwr, 68, 380
 strncat, 68, 381
 strncmp, 68, 381
 strncpy, 68, 381
 strnicmp, 68, 381
 strnset, 69, 381
 strupr, 69, 384
 strrchr, 69, 385
 strrev, 69, 386
 strset, 69, 387
 strspn, 69, 388
 strstr, 69, 389
 strtok, 69, 393
 strupr, 69, 395
string.h, 69
string.h, contents, 85
Strings, 22
 comparing, 373
 comparing parts of, 381
 concatenating, 373, 381

Strings (*continued*)
 conversion to
 floating-point values, 107
 lowercase, 380
 uppercase, 395
 copying, 373
 copying parts of, 381
 initialization, 381, 387
 length of, 379
 reading from console, 118
 reversing, 386
 searching, 373, 384, 385, 388, 389
 searching for tokens, 393
 writing, 198
 writing to console, 132, 134
strlen, 68, 379
strlwr, 68, 380
strncat, 68, 381
strncmp, 68, 381
strncpy, 68, 381
strnicmp, 68, 381
strnset, 69, 381
strupr, 69, 384
strrchr, 69, 385
strrev, 69, 386
strset, 69, 387
strspn, 69, 388
strstr, 69, 389
strtod, 44, 390
strtok, 69, 393
strtol, 44, 390
strupr, 69, 395
Subdirectory conventions, 20, 21
swab, 71, 396
Syntax conventions. *See* Notational conventions
sys subdirectory, 21
sys\ locking.h, contents, 86
sys\ stat.h, contents, 86
sys\ timeb.h, 70
sys\ timeb.h, contents, 86
sys\ types.h, 70
sys\ types.h, contents, 86
sys\ utime.h, 70
sys\ utime.h, contents, 87
sys_errlist, 33
sys_errlist variable, 78, 303, 377
sys_nerr, 33
sys_nerr variable, 303, 377
sysat.h, 45
system, 65, 397

- system (*continued*)
 - path-name delimiters, 22
 - XENIX version, differences from, 453
 System calls. *See* MS-DOS system calls
 System time. *See* Time
- tan, 59, 399
 - floating-point support, 26
 Tangent, 399
 tanh, 59, 399
 - floating-point support, 26
 tell, 53, 400
 tempnam, 49, 401
 Terminal capabilities, 252
 Text mode, 23, 34, 166, 189, 206, 299, 346, 355
 time, 70, 403
 Time
 - computing time differences, 142
 - conversion from
 - long integer to string, 139
 - long integer to structure, 234, 261
 - structure to string, 100
 - correcting for local time, 261
 - global variables, setting, 407
 - obtaining, 217, 403
 - routines
 - asctime, 70, 100
 - ctime, 70, 139
 - difftime, 70, 142
 - ftime, 70, 217
 - gmtime, 70, 234
 - include files, 70
 - localtime, 70, 261
 - time, 70, 403
 - tzset, 70, 407
 - utime, 70, 417
 - timeb type, 37, 217
 - timeb.h. *See* sys\ timeb.h
 - time.h, 70
 - time.h, contents, 87
 - time_t type, 142
 - timezone variable, 32, 407
 - TLOSS, 274, 436
 - tm type, 37, 87, 234
 - tmpfile, 49, 404
 - tmpnam, 49, 401
 - toascii, 42, 405
 - Tokens, finding in strings, 393- _tolower, 42, 405, 421
- tolower, 42, 405, 421
 - function version, use of, 43
 - side effects, 43
- _toupper, 42, 405, 421
 toupper, 42, 405, 421
 - function version, use of, 43
 - side effects, 43
- Translation mode. *See* Binary mode; Text mode
- Trigonometric functions
 - acos, 96
 - asin, 102
 - atan, 106
 - atan2, 106
 - cos, 131
 - cosh, 131
 - hypot, 239
 - sin, 353
 - sinh, 353
 - tan, 399
 - tanh, 399
- Type checking, arguments. *See* Argument type checking
 types.h. *See* sys\ types.h
 Types, predefined. *See* Standard types
 TZ environment variable, 32
 TZ variable, 261, 407
 tzname variable, 32, 407
 tzset, 70, 407
- ultoa, 44, 409
 umask, 45, 410
 XENIX version, differences from, 453
 UNDERFLOW, 274, 436
 ungetc, 49, 412
 ungetch, 57, 414
 UNIX operating system, 439
 unlink, 45, 416
 XENIX version, differences from, 453
 Update, 166, 188, 205
 utimbuf type, 37, 87, 417
 utime, 70, 417
 XENIX version, differences from, 453
 utime.h. *See* sys\ utime.h
- v2tov3.h, contents, 87
 va_arg, 71, 419
 va_end, 71, 419
 varargs.h, contents, 87

- Variable
 - global, 31
 - amblksize, 31
 - common library, use in, 442
 - daylight, 32, 407
 - doserrno, 33
 - environ, 35, 228, 317
 - errno, 33, 78, 303, 377, 433
 - fmode, 34
 - osmajor, 34
 - osminor, 34
 - psp, 35
 - sys_errlist, 33, 78, 303, 377
 - sys_nerr, 33, 303, 377
 - timezone, 32, 407
 - tzname, 32, 407
 - va_start, 71, 419
- Version number (MS-DOS), 34
- vfprintf, 49, 424
- vprintf, 49, 424
- vscanf, 49, 424
- Word. *See* Binary int
- WORDREGS type, 78
- write, 53, 427
- Write access. *See* Permission setting
 - XENIX version, differences from, 454
- Write operations
 - binary int value to stream, 319
 - character to
 - console, 414
 - file, 427
 - stdout, 196, 313
 - stream, 196, 313, 412
 - console, to, 132, 134, 315
 - data items from stream, 219
 - formatted, 132, 194, 306, 363, 424
 - line to stream, 318
 - port, to, 302
 - string to stream, 198
- XENIX operating system, 439
- y0. *See* Bessel functions
- y1. *See* Bessel functions
- yn. *See* Bessel functions



16011 NE 36th Way, Box 97017, Redmond, WA 98073-9717

Software Problem Report

Name _____

Street _____

City _____ State _____ Zip _____

Phone _____ Date _____

Instructions

Use this form to report software bugs, documentation errors, or suggested enhancements. Mail the form to Microsoft.

Category

Software Problem

Documentation Problem

(Document #_____)

Software Enhancement

Other

Software Description

Microsoft Product _____

Rev. _____ Registration # _____

Operating System _____

Rev. _____ Supplier _____

Other Software Used _____

Rev. _____ Supplier _____

Hardware Description

Manufacturer _____ CPU _____ Memory _____ KB

Disk Size _____" Density: _____ Sides:

Single _____ Single _____

Double _____ Double _____

Peripherals _____

Problem Description

Describe the problem. (Also describe how to reproduce it, and your diagnosis and suggested correction.) Attach a listing if available.

Microsoft Use Only

Tech Support _____

Date Received _____

Routing Code _____

Date Resolved _____

Report Number _____

Action Taken: