

[Video Toolbox](#) / [VTFrameSilo](#)

API Collection

VTFrameSilo

An object that stores sample buffers from a multipass encoding session.

Overview

A frame silo object starts out empty and is populated by calls to [`VTFrameSiloAddSampleBuffer\(_ :sampleBuffer:\)`](#) to add sample buffers in ascending decode order. After the first full pass, additional passes may be performed to replace sample buffers. Each such pass must begin with a call to [`VTFrameSiloSetTimeRangesForNextPass\(_ :timeRangeCount :timeRangeArray:\)`](#), which takes a list of time ranges. Samples in these time ranges are deleted, and calls to [`VTFrameSiloAddSampleBuffer\(_ :sampleBuffer:\)`](#) can then be made to provide replacements.

Call [`VTFrameSiloCallFunctionForEachSampleBuffer\(:in :refcon :callback:\)`](#) or [`VTFrameSiloCallBlockForEachSampleBuffer\(:in :handler:\)`](#) to retrieve sample buffers. The frame silo object may write sample buffers and data to the backing file between addition and retrieval; don't expect to get identical object pointers back.

The sample buffers are ordered by decode timestamp.

Topics

Creating Frame Silos

```
func VTFrameSiloCreate(allocator: CFAllocator?, fileURL: CFURL?, timeRange: CMTimeRange, options: CFDictionary?, frameSiloOut: UnsafeMutablePointer<VTFrameSilo?>) -> OSStatus
```

Creates a frame silo object using a temporary file.

Configuring Frame Silos

```
func VTFrameSiloAddSampleBuffer(VTFrameSilo, sampleBuffer: CMSampleBuffer) -> OSStatus
```

Adds a sample buffer to a frame silo object.

```
func VTFrameSiloSetTimeRangesForNextPass(VTFrameSilo, timeRangeCount: CMItemCount, timeRangeArray: UnsafePointer<CMTTimeRange>) -> OSStatus
```

Begins a new pass of samples to be added to a frame silo object.

```
func VTFrameSiloCallBlockForEachSampleBuffer(VTFrameSilo, in: CMTTimeRange, handler: (CMSampleBuffer) -> OSStatus) -> OSStatus
```

Retrieves sample buffers from a frame silo object.

```
func VTFrameSiloCallFunctionForEachSampleBuffer(VTFrameSilo, in: CMTTimeRange, refcon: UnsafeMutableRawPointer?, callback: (UnsafeMutableRawPointer?, CMSampleBuffer) -> OSStatus) -> OSStatus
```

Retrieves sample buffers from a frame silo object.

Inspecting Frame Silos

```
func VTFrameSiloGetProgressOfCurrentPass(VTFrameSilo, progressOut: UnsafeMutablePointer<Float32>) -> OSStatus
```

Gets the progress of the current pass.

```
func VTFrameSiloGetTypeID() -> CFTTypeID
```

Retrieves the Core Foundation type identifier for the frame silo object.

Data Types

```
class VTFrameSilo
```

An object that stores a large number of sample buffers, as produced by a multipass compression session.

See Also

Compression

- { } Encoding video for low-latency conferencing
Configure a compression session to optimize encoding for video-conferencing apps.
- { } Encoding video for live streaming
Configure a compression session to encode video for live streaming.
- { } Encoding video for offline transcoding
Configure a compression session to transcode video in offline workflows.
- ≡ VTCompressionSession
An object that compresses video data.
- ≡ VTDecompressionSession
An object that decompresses video data.
- ≡ VTMultiPassStorage
An object that stores video encoding metadata from a multipass encoding session.