COMP445 Data Communications & Computer Networks

Wk7: Transport Layer - Part3

Abdelwahab Elnaka, PhD

Department of Computer Science & Software Engineering Concordia University, Montreal, Canada

These slides have been extracted, modified and updated from original slides of Computer Networking: A Top Down Approach 7th edition Jim Kurose, Keith Ross © Pearson/Addison Wesley, April 2016

KUROSE • ROSS

Computer Networking

outline


- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control


Principles of congestion control

congestion:

- informally: "too many sources sending too much data too fast for network to handle"
- different from flow control!
- manifestations:
 - lost packets (buffer overflow at routers)
 - long delays (queueing in router buffers)





- one router, finite buffers
- sender retransmission of timed-out packet
 - application-layer input = application-layer output: λ_{in} = λ_{out}
 - transport-layer input includes retransmissions : $\lambda_{in} \ge \lambda_{in}$



idealization: perfect knowledge

 sender sends only when router buffers available






Idealization: known loss


packets can be lost, dropped at router due to full buffers


 sender only resends if packet known to be lost



Idealization: known loss packets can be lost, dropped at router due to full buffers


 sender only resends if packet known to be lost






Realistic: duplicates


- packets can be lost, dropped at router due to full buffers
- sender times out prematurely, sending two copies, both of which are delivered





Realistic: duplicates

- packets can be lost, dropped at router due to full buffers
- sender times out prematurely, sending two copies, both of which are delivered




"costs" of congestion:


- more work (retrans) for given "goodput"
- unneeded retransmissions: link carries multiple copies of pkt
 - decreasing goodput


- four senders
- multihop paths
- timeout/retransmit

Q: what happens as λ_{in} and λ_{in} increase?

A: as red λ_{in} increases, all arriving blue pkts at upper queue are dropped, blue throughput → 0







another "cost" of congestion:

when packet dropped, any "upstream transmission capacity used for that packet was wasted!

outline


- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control


TCP congestion control: additive increase multiplicative decrease

- approach: sender increases transmission rate (window size), probing for usable bandwidth, until loss occurs
 - additive increase: increase cwnd by I MSS every RTT until loss detected
 - multiplicative decrease: cut cwnd in half after loss

AIMD saw tooth behavior: probing for bandwidth cwnd: TCP sender



TCP Congestion Control: details



sender limits transmission:

 cwnd is dynamic, function of perceived network congestion


TCP sending rate:

 roughly: send cwnd bytes, wait RTT for ACKS, then send more bytes

rate
$$\approx \frac{\text{cwnd}}{\text{RTT}}$$
 bytes/sec

TCP Slow Start

- when connection begins, increase rate exponentially until first loss event:
 - initially cwnd = I MSS
 - double cwnd every RTT
 - done by incrementing cwnd for every ACK received
- summary: initial rate is slow but ramps up exponentially fast



TCP: detecting, reacting to loss

- loss indicated by timeout:
 - cwnd set to I MSS;
 - window then grows exponentially (as in slow start) to threshold, then grows linearly
- loss indicated by 3 duplicate ACKs: TCP RENO
 - dup ACKs indicate network capable of delivering some segments
 - cwnd is cut in half window then grows linearly
- TCP Tahoe always sets cwnd to I (timeout or 3 duplicate acks)


TCP: switching from slow start to CA

Q: when should the exponential increase switch to linear?

A: when **cwnd** gets to 1/2 of its value before timeout.




- variable ssthresh
- on loss event, ssthresh is set to 1/2 of cwnd just before loss event



^{*} Check out the online interactive exercises for more examples: http://gaia.cs.umass.edu/kurose_ross/interactive/


Summary: TCP Congestion Control



TCP throughput

- avg. TCP thruput as function of window size, RTT?
 - · ignore slow start, assume always data to send
- W: window size (measured in bytes) where loss occurs
 - avg. window size (# in-flight bytes) is ³/₄ W
 - avg. thruput is 3/4W per RTT

avg TCP thruput =
$$\frac{3}{4} \frac{W}{RTT}$$
 bytes/sec



TCP Futures: TCP over "long, fat pipes"


- example: 1500 byte segments, 100ms RTT, want
 10 Gbps throughput
- requires W = 83,333 in-flight segments
- throughput in terms of segment loss probability, L [Mathis 1997]:

TCP throughput =
$$\frac{1.22 \cdot MSS}{RTT \sqrt{L}}$$

- ⇒ to achieve 10 Gbps throughput, need a loss rate of L = $2 \cdot 10^{-10}$ a very small loss rate!
- new versions of TCP for high-speed

TCP Fairness


fairness goal: if K TCP sessions share same bottleneck link of bandwidth R, each should have average rate of R/K



Why is TCP fair?

two competing sessions:

- additive increase gives slope of I, as throughout increases
- multiplicative decrease decreases throughput proportionally



Fairness (more)

Fairness and UDP

- multimedia apps often do not use TCP
 - do not want rate throttled by congestion control
- instead use UDP:
 - send audio/video at constant rate, tolerate packet loss


Fairness, parallel TCP connections

- application can open multiple parallel connections between two hosts
- web browsers do this
- e.g., link of rate R with 9 existing connections:
 - new app asks for I TCP, gets rate R/I0
 - new app asks for 11 TCPs, gets R/2

Explicit Congestion Notification (ECN)

network-assisted congestion control:

- two bits in IP header (ToS field) marked by network router to indicate congestion
- congestion indication carried to receiving host
- receiver (seeing congestion indication in IP datagram)) sets ECE bit on receiver-to-sender ACK segment to notify sender of congestion



summary

- principles behind transport layer services:
 - multiplexing, demultiplexing
 - reliable data transfer
 - flow control
 - congestion control
- instantiation, implementation in the Internet
 - UDP
 - TCP

next:

- leaving the network "edge" (application, transport layers)
- into the network "core"
- two network layer chapters:
 - data plane
 - control plane