Panorama Quick Start

Before You Begin

- Register your Panorama software at http://support.paloaltonetworks.com to obtain the latest software updates, and to activate support.
- Obtain an IP address for Panorama from your system administrator.
- If you don't already have VMware, download the VMware Player or Server from http://www.vmware.com/download for the host OS you will be deploying Panorama on.

Performing the Installation

1. If not already installed, install VMware on the server intended to be used for Panorama.
2. Insert Panorama CD-ROM into the CD-ROM drive on the server.
3. Copy the compressed Panorama zip file from the CD-ROM to the server.
4. Unzip the Panorama zip file
5. Launch VMware on the server.
6. Select **File > Open** within VMware and browse to the Panorama Appliance directory that was copied to the server.
7. Open the Panorama.vmdk file.
8. Click **Start** in VMware to start the Panorama appliance.
9. When the Panorama completes booting and the console appears, continue to the next section.

Performing the Final Setup

Configuring the Network Interface

1. Log in to the console by admin at both the login and password prompts.
2. Type configure to switch to configuration mode in the CLI.
3. Type set deviceconfig system ip-address <Panorama IP address> netmask <netmask> default-gateway <gateway IP address> to set applicable network configuration for your network.
4. Type commit to make the change active.
5. Connect the server to the network.

Verifying the Network Configuration

6. Open a browser and connect to **https://<Panorama IP address>**.
7. Log in to the web interface of Panorama.

Changing the Default Password

8. Click **Panorama > Administrators > admin**.
9. Type **admin** in the **Old Password** field.
10. Type your new password in the **New Password** field.
11. Type your new password again in the **Confirm New Password** field.
12. Click **OK**.

Creating an SSL Certificate to Encrypt the Management Connection

13. Click **Panorama > Certificates > Generate a self signed certificate**.
14. Enter the desired certificate details in the dialog and click **OK**.
15. Click **Commit** to make the changes active.

Adding a Managed Device

1. Click **Panorama > Managed Devices**.
2. Click the **Edit** button at the bottom of the page.
3. Enter the serial number of the device to be managed and click **Add**.
4. Click **OK**.
5. Login to the devices web interface and click **Devices > Setup**.
6. Click **Edit** on the box containing the Panorama setting.
7. Enter the Panorama IP address in the Panorama field and click **OK**.
8. Click **Commit** to make the changes active.
9. Return to Panorama and click **Panorama > Managed Devices** and verify that the device has connected

Where to Go Next

- To learn about using Panorama to manage PAN-OS devices, refer to the Palo Alto Networks Administrator's Guide.

Palo Alto Networks™ is a registered trademark of Palo Alto Networks, Inc.
All other trademarks belong to their respective owners.

Copyright © 2007 Palo Alto Networks, Inc. Contents subject to change without notice.
P/N 810-000016-00B

paloalto NETWORKS