ARP

READ

ARP Overview

If your network is using the IPv4 communications protocol, the Address Resolution Protocol, or ARP, is what you need to map IPv4 addresses to MAC addresses. This here explains how ARP works.

Every IP device on an Ethernet network has a unique Ethernet MAC address. When a device sends an Ethernet Layer 2 frame, it contains these two addresses:

- **Destination MAC address** – The Ethernet MAC address of the destination device on the same local network segment. If the destination host is on another network, then the destination address is the frame would be that of the default gateway (i.e., router).
- **Source MAC address** – The MAC address of the Ethernet NIC on the source host.

The figure illustrates the problem when sending a frame to another host on the same segment on an IPv4 network.



To send a packet to another host on the same local IPv4 network, a host must know the IPv4 address and the MAC address of the destination device. Device destination IPv4 addresses are either known or resolved to a device name. Network MAC addresses must be discovered.

A device uses Address Resolution Protocol (ARP) to determine the destination MAC address of a local device when it knows its IPv4 address.

ARP provides two basic functions:

- Resolving IPv4 addresses to MAC addresses
- Maintaining a table of IPv4 to MAC address mappings

READ

ARP Functions

When a packet is sent to the data link layer to be encapsulated into an Ethernet frame, the device refers to a table in its memory to find the MAC address that is mapped to the IPv4 address. This table is stored temporarily in RAM memory and called the ARP table or the ARP cache.

The sending device will search its ARP table for a destination IPv4 address and a corresponding MAC address.

- If the packet's destination IPv4 address is on the same network as the source IPv4 address, the device will search the ARP table for the destination IPv4 address.
- If the destination IPv4 address is on a different network from the source IPv4 address, the device will search the ARP table for the IPv4 address of the default gateway.

In both cases, the search is for an IPv4 address and a corresponding MAC address for the device.

Each entry, or row, of the ARP table binds an IPv4 address with a MAC address. We call the relationship between the two values a map. This simply means that you can locate an IPv4 address in the table and discover the corresponding MAC address. The ARP table temporarily saves (caches) the mapping for the devices on the LAN.

If the device locates the IPv4 address, its corresponding MAC address is used as the destination MAC address in the frame. If there is no entry is found, then the device sends an ARP request.

Click Play in the figure to see an animation of the ARP function.



READ

Video – ARP Request

An ARP request is sent when a device needs to determine the MAC address that is associated with an IPv4 address, and it does not have an entry for the IPv4 address in its ARP table.

ARP messages are encapsulated directly within an Ethernet frame. There is no IPv4 header. The ARP request is encapsulated in an Ethernet frame using the following header information:

- **Destination MAC address** – This is a broadcast address FF-FF-FF-FF-FF-FF assigning all Ethernet NICs on the LAN to accept and process the ARP request.
- **Source MAC address** – This is the MAC address of the sender of the ARP request.
- **Type** – ARP messages have a type field of 0x806. This informs the receiving NIC that the data portion of the frame needs to be passed to the ARP process.

Because ARP requests are broadcasts, they are flooded out all ports by the switch, except the receiving port. All Ethernet NICs on the LAN process broadcasts and must deliver the ARP request to its operating system for processing. Every device must process the ARP request to see if the target IPv4 address matches its own. A router will not forward broadcasts out other interfaces.

Only one device on the LAN will have an IPv4 address that matches the target IPv4 address in the ARP request. All other devices will not reply.

Click Play in the figure to view a demonstration of an ARP request for a destination IPv4 address that is on the local network.

READ

Video – ARP Operation – ARP Reply

Only the device with the target IPv4 address associated with the ARP request will respond with an ARP reply. The ARP reply is encapsulated in an Ethernet frame using the following header information:

- **Destination MAC address** – This is the MAC address of the sender of the ARP request.
- **Source MAC address** – This is the MAC address of the sender of the ARP reply.
- **Type** – ARP messages have a type field of 0x806. This informs the receiving NIC that the data portion of the frame needs to be passed to the ARP process.

Only the device that originally sent the ARP request will receive the unicast ARP reply. After the ARP reply is received, the device will add the IPv4 address and the corresponding MAC address to its ARP table. Packets for the IPv4 address will now be encapsulated in frames using its corresponding MAC address.

If a device responds to the ARP request, the sender is dropped because it cannot reach the intended host.

Entries in the ARP table are time stamped. If a device does not receive a frame from a particular device before the timeslot expires, the entry for this device is removed from the ARP table.

Additionally, static map entries can be entered in an ARP table, but this is rarely done. Static ARP table entries do not expire over time and must be manually removed.

Note: IPv6 uses a similar process to ARP for IPv4, known as ICMPv6 Neighbor Discovery (ND). IPv6 uses neighbor solicitation and neighbor advertisement messages, similar to IPv4 ARP requests and ARP replies.

Click Play in the figure to view a demonstration of an ARP reply.

READ

Video – ARP Role in Remote Communications

When the destination IPv4 address is not on the same network as the source IPv4 address, the source device needs to send the frame to its default gateway. This is the interface of the local router. Whenever a source device is a packet with an IPv4 address on another network, it will encapsulate that packet in a frame using the destination MAC address of the router.

The IPv4 address of the default gateway is stored in the IPv4 configuration of the hosts. When a host creates a packet for a destination, it compares the destination IPv4 address and its own IPv4 address to determine if the two IPv4 addresses are located on the same Layer 3 network. If the destination host is not on its same network, the host will forward the packet for a among with the IPv4 address of the default gateway. If there is not an entry, it uses the ARP process to determine a MAC address of the default gateway.

Click Play to view a demonstration of an ARP request and ARP reply associated with the default gateway.

READ

Removing Entries from an ARP Table

For each device, an ARP cache timer removes ARP entries that have not been used for a specified period of time. The times differ depending on the operating system of the device. For example, newer Windows operating systems store ARP table entries between 17 and 40 seconds, as illustrated in the figure.



PC-A's ARP Cache

IPv4 Address	MAC Address
192.168.1.1	00-0D

Note: MAC addresses are shortened for demonstration purposes.

Commands may also be used to manually remove some or all of the entries in the ARP table. After an entry has been removed, the process for sending an ARP request and receiving an ARP reply must occur again to enter the map in the ARP table.

READ

ARP Tables on Networking Devices

On a Cisco router, the **show ip arp** command is used to display the ARP table, as shown in the figure.

```
R2#show ip arp
Protocol  Address          Age (min)  Hardware Addr  Type  Interface
Internet  192.168.1.1            -   00e0.a3ac.d0d0  ARPA  GigabitEthernet0/0
Internet  192.168.1.80           0   d8a8.d0fb.a180  ARPA  GigabitEthernet0/0
Internet  192.168.1.88           1   a8b1.6701.b095  ARPA  GigabitEthernet0/0
R2#
```

On a Windows 10 PC, the **arp -a** command is used to display the ARP table, as shown in the figure.

```
C:\Users\PC1> arp -a
Interface: 192.168.1.110 --- 0x10
  Internet Address      Physical Address      Type
  192.168.1.1           ff-ff-ff-ff-ff-ff     static
  192.168.1.100         00-0b-be-dc-f0-78     dynamic
  192.168.1.106         98-5a-ec-f0-f0-7d     dynamic
  192.168.1.111         a0-36-9f-1a-e6-bb     dynamic
  192.168.1.117         a0-51-0b-ba-bd-dd     dynamic
  192.168.1.217         98-5a-ec-f0-f0-7d     dynamic
  192.168.1.218         a0-36-9f-1a-e6-bb     dynamic
  192.168.1.240         ff-ff-ff-ff-ff-ff     static
  224.0.0.22            01-00-5e-00-00-16     static
  224.0.0.251           01-00-5e-00-00-fb     static
  224.0.0.252           01-00-5e-00-00-fc     static
  239.255.255.250       01-00-5e-7f-ff-fa     static
  255.255.255.255       ff-ff-ff-ff-ff-ff     static
C:\Users\PC1>
```

READ

ARP Issues – ARP Broadcasts and ARP Spoofing

As a broadcast frame, an ARP request is received and processed by every device on the local network. On a typical business network, these broadcasts would cause only minor delays in network performance. If a network is poorly designed, or if it is subject to a large broadcast storm, network performance can be affected. At the same time, there could be some reduction in performance for a short period of time, as all devices on the figure. After the devices send out the initial ARP broadcasts and have learned the necessary MAC addresses, any impact on the network will be minimized.



In some cases, the use of ARP can lead to a potential security risk. A threat actor can use ARP spoofing to perform an ARP poisoning attack. This is a technique used by a threat actor to reply to an ARP request for an IPv4 address that belongs to another device, such as the default gateway, as shown in the figure. The threat actor sends an ARP reply with its own MAC address. The receiver of the ARP reply will add the wrong MAC address to its ARP table and send these packets to the threat actor.

Enterprise level switches include mitigation techniques known as dynamic ARP inspection (DAI). DAI is beyond the scope of this course.



Note: MAC addresses are shortened for demonstration purposes.

READ

Packet Tracer – Examine the ARP Table

In this Packet Tracer, activity you will complete the following objectives:

- Examine an ARP Request
- Examine a Static MAC Address Table
- Examine the ARP Process in Remote Communications

This activity is optimized for viewing PDUs. The devices are already configured. You will gather PDU information in simulation mode and answer a series of questions about the data you collect.

Examine the ARP Table

Examine the ARP Table

READ

Check Your Understanding – ARP

Check your understanding of ARP by choosing the correct answer to the following questions.

1. What two functions are provided by ARP? (Choose two.)
   - Maintains a table of IPv4 address to domain names
   - Maintains a table of IPv4 to MAC address mappings
   - Maintains a table of IPv6 to MAC address mappings
   - Resolves IPv4 addresses to domain names
   - Resolves IPv4 addresses to MAC addresses
   - Resolves IPv6 addresses to MAC addresses
2. Where is the ARP table stored on a device?
   - ACM
   - Flash
   - NVRAM
   - RAM
3. Which statement is true about ARP?
   - An ARP cache cannot be manually deleted.
   - ARP entries are cached permanently.
   - ARP entries are cached temporarily.
4. Which command could be used on a Cisco router to view its ARP table?
   - **arp -a**
   - **arp -d**
   - **show arp table**
   - **show ip arp**
5. What is an attack using ARP?
   - ARP broadcasts
   - ARP hopping attacks
   - ARP poisoning
   - ARP saturation

Check

Show Me

Reset