## HƯỚNG DẪN CẦU HÌNH CONNECT ANSIBLE TỚI WINDOWS SERVER


**Bước 1**: Kiểm tra powershell để đảm bảo version PS >= 4.0

- Run PowerShell với quyền Adminitator
- Run lênh: \$PSVersionTable



Bước 2: Copy file zip ansible-devel.zip vào desktop trên server và giải nén

- Kiểm tra đường dẫn giải nén để thực hiện cấu hình bước 3



**Bước 3**: Run 2 lệnh sau trong powershell những lệnh sau:

 $\label{lem:configure} $$file = "C:\Users\app\Desktop\ansible-devel\examples\scripts\Configure\Remoting\For\Ansible.ps1"$ 

powershell.exe -ExecutionPolicy ByPass -File \$file -Verbose

Bước 4: Thay đổi port winrm https tới 10000 (do xin connect)

- winrm set winrm/config/Listener?Address=\*+Transport=HTTP '@{Port="9999"}'
- winrm set winrm/config/Listener?Address=\*+Transport=HTTPS
   '@{Port="10000"}'

Bước 5: Set trustHosst tới server jenkins

- winrm set winrm/config/client '@{TrustedHosts="10.60.156.96,10.60.156.43"}'

Bước 6: Kiểm tra lại config

winrm e winrm/config/listener

```
PS C:\Windows\system32> winrm enumerate winrm/config/Listener

Listener

Address = *

Transport = HTTP
Port = 9999
Hostname
Enabled = true
URLPrefix = wsman
CertificateThumbprint
ListeningOn = 10.60.156.203, 127.0.0.1, ::1, fe80::5efe:10.60.156.203%13, fe80::e9e9:e2f1:44e4:e72c%12

Listener

Address = *

Transport = HTTPS
Port = 10000
Hostname = WIN-T3GLPIK271H
Enabled = true
URLPrefix = wsman
CertificateThumbprint = 007EC44495EE3A5A345385B448D1DBEB1AD204FB
ListeningOn = 10.60.156.203, 127.0.0.1, ::1, fe80::5efe:10.60.156.203%13, fe80::e9e9:e2f1:44e4:e72c%12
```

- Check trên jenkins server. Ví dụ:

```
[app@tempcent7 ~]$ sudo vi /etc/ansible/hosts
[app@tempcent7 ~]$ sudo ansible 10.60.156.203 -m win_ping
10.60.156.203 | SUCCESS => {
    "changed": false,
    "ping": "pong"
}
[app@tempcent7 ~]$ ||
```