
# Expert4x RSI ForexLiberator EA for MT5

May 18, 2024



## **Contents**

Chapter 1: Copyright Notices	5
Chapter 2: Getting Started with the RSI ForexLiberator EA	6
2.1 Installing the RSI ForexLiberator EA	
2.2 RSI ForexLiberator Expert Advisor First Time Activation	
<b>'</b>	
Chapter 3: System Requirements	14
3.1 Operating System Requirements	
3.2 Hardware Requirements	
3.3 MetaTrader (MT5) Requirements and Settings	
3.4 Forex Broker Requirements	
3.5 Hedging Support Requirements	
3.6 Non-FIFO Support Requirements	
3.7 Account Type and Minimum Lot Size Requirements	
3.8 ECN/STP Broker Accounts	
Chapter 4: RSI ForexLiberator EA Configuration Guide	16
4.1 Configuration and Operation Principles	
4.2 RSI ForexLiberator EA Parameter Descriptions	
4.2.1 TRADE ENTRY	
Direction of Initial Trade Entry	
RSI Period	
RSI Applied Price	
RSI OverBought/Sold Levels	
Price Gap	
Gap Scaling Start Level	
Gap Scaling Rate	
Minimum Gap Size	
Lots for Initial Trade Entry	20
Topup Lots Multiplier	20
Topup Lots Change by Lots	21
Topup Trades to Skip	
Initial Lots Adjustment: Base Account Equity Amount	
Initial Lots Adjustment: Required Equity Change	
Initial Lots Adjustment: Initial Lots Adjustment	
4.2.2 INITIAL TRADE MANAGEMENT	
Initial: Take Profit	
Initial: Hidden TP	
Initial Trade Trailing Stop	
4.2.3 HEDGE TRADES MANAGEMENT	
Allow Buy & Sell the Same Pair at the Same Time	
4.2.4 BASKET OF TRADES MANAGEMENT	
Pair: Target Closure \$ Amount	
Pair: Target Profit Pips Closure	
Portfolio: Closure at Profit \$ Amount	
Portfolio: Reentry After Closure	
Pairs to Trade	
Maximum Traded Pairs	

	Maximum Currency Exposure	29
	Maximum Topup Trades per Pair per Direction	29
	Topup TP Mode	29
4.2.5	PRUNING OF TRADES	
	Start Pruning at Trade Count in a Pair Direction	
	Trade Pair Pruning Approach	
	Gap Pruning From This Scale of Initial Gap	
4.2.6	TIME OF DAY FOR INITIAL ENTRY	
	Reference Time Selection	
	GMT Offset of Broker	
	Entry Window From Hour/Minute - Entry Window Until Hour/Minute	
4.0 -	Monday Sunday Trade Entry	
4.2.7	MISCELLANEOUS	
	Closeout Summary Text Colour	
	Closeout Text Display	
	BUY:Approx. Closeout Price Level Colour.	
	SELL:Approx. Closeout Price Level Colour	
	Tick Scaling for CFD Markets	
	Magic Number	
428	Examples	
4.2.0	Example - Normal Entry	
	Example - Reverse Entry	
	Example - Entry with TP Only	
	Example - Entry with TP and Hidden TP	
	Example - Entry with TP, Hidden TP and Trailing	
	Example - Trade Not More Than 2 Out of Multiple Markets	
	Example - Trade Max 1 Pair Involving the Same Currency	
	Example - Stop Trading of Certain Pairs	
	Example - Scale Price Gap Up by Rate	
	Example - Scale Price Gap Down by Rate	45
	Example - Same Initial Lots All the Time	46
	Example - Initial Lots Adjustment Upward Only	46
	Example - Initial Lots Adjustment Up & Down	
	Example - Same Position Size All the Time	
	Example - Scale Lots Up by Multiplier	
	Example - Scale Lots Down by Multiplier	
	Example - Scale Lots Up by Amount	
	Example - Scale Lots Down by Amount	
	Example - Skip Topup and Scale Up by Multiplier	
	Example - Skip Topups and Scale Down by Multiplier	
	Example - Skip Topup and Scale Up by Amount	
	Example - Skip Topups and Scale Down by Amount	
	Example - Closure at Profit Amount  Example - Closure at Pips Profit	
	Example - Closure at Pips Profit	
	Example - Closure at Portfolio Loss	
	Example - Stop Trading After Portfolio Closure	
	Example - Balanced Amount Pruning	
	Example - First & Last Trades Pruning	
	Example - Gap Pruning	
	Example - FIFO Trading	
Chanter 5:	Knowledgebase	52
•	_	
	Download MT5  Download the Setup Application	
	Install the RSI ForexLiberator EA	
	Upgrade the EAUpgrade the EA	
	Attach the RSI ForexLiberator Expert Advisor to a Chart	
J.J 110W 10 /	The thorn of the continuous of the continuous to a chart	02

5.6 RSI ForexLiberator Expert Advisor First Time Activation	66
5.7 🥯 Sign Instead of 😂 Sign After Attach	70
5.8 What is the Leverage of My Account	71
5.9 How to Figure Out My Broker's GMT Offset?	
5.10 EA Is Not Starting Up After Attach to Chart	
5.11 No Updates to Chart	
5.12 Prompted for Access ID at Service Access Settings	74
5.13 How to Edit the EA Input Values	75
5.14 Not Enough Memory For Bar History Or Indicator	75
5.15 No Trades Due to Trade Disabled	76
5.16 Backtest In Visual Mode Not Working	77
5.17 Backtest Not Working	
5.18 Connection Down Message	
5.19 Computer Always-on	79
5.20 No Trades During Backtesting	
5.21 Visual Mode Checkbox Missing in Strategy Tester	
5.22 Step-by-step Installation of Expert4x EAs and Indicators	
5.23 How to download an EA setup in VPS environment	
5.24 How to enable JavaScript in your Internet Explorer	
5.25 How to Enable Download in your Internet Explorer	101
Chapter 6: Operational Messages	105
Chapter 6: Operational Messages	
6.1 Operational Messages	
6.1.1 Message 1001	
6.1.2 Message 1002	
6.1.3 Message 1006	
6.1.4 Message 1007	
6.1.5 Message 1008	
6.1.6 Message 1121	
6.1.7 Message 1163	
6.1.8 Message 2101	
6.1.9 Message 2118	113
Chapter 7: Support	115
Index	.116

## Chapter

1

## **Copyright Notices**

Copyright©2024 – Expert4x, all rights reserved. This eBook is intended for the purchaser's personal use only. No part of this eBook may be reproduced or transmitted in any form whatsoever, electronic, or mechanical, including photocopying, recording, or by any informational storage or retrieval system without expressed written permission from Expert4x.

Copyright©2024 EAfactory, all rights reserved. All title, including but not limited to copyrights, in and to the RSI ForexLiberator EA and any copies thereof are owned by EAfactory or its suppliers. All title and intellectual property rights in and to the content which may be accessed through use of the RSI ForexLiberator EA is the property of the respective content owner and may be protected by applicable copyright or other intellectual property laws and treaties. All rights not expressly granted are reserved by EAfactory. For the full details please refer to the End-User License Agreement ("EULA").

## Chapter

2

## Getting Started with the RSI ForexLiberator EA

Getting Started provides a guided exploration of the RSI ForexLiberator EA. It is geared for an audience that has little or no knowledge of installing an MT5 EA. It walks the novice user through downloading and installing the RSI ForexLiberator EA.

## 2.1 Installing the RSI ForexLiberator EA

The RSI ForexLiberator EA comes with a setup application to provide a wizard based installation process to the selected MT5 terminal.

#### Before you start...

- Ensure that you have the login credentials to the Web Support Centre.
- Ensure that you have an MT5 terminal version 5.00 build 4260 or later installed.
- 1. Exit the MT5 if it was running.
- 2. Visit the RSI ForexLiberator EA Web Support Centre page.
- 3. Read the Web Support Centre Terms and Conditions and Privacy Policy then tick the checkbox to accept them.





Download I accept the terms and conditions for signing up to this service, and hereby confirm I have read the privacy policy. == FOR MT4 FOR MT5 **Users Guide Download EA Setup** Version **Quick Links** Download and Install MT5 Download and Install EA Attach EA to Chart Upgrade EA Changes Log **EULA** B

4. Click on the **Download EA Setup** button to download the EA setup for the MT5 terminal.

- 5. Run the downloaded setup application. Select the MT5 instance through the setup wizard pages to where you want the EA to be installed.
- 6. When the setup completes start the MT5 up. The RSI ForexLiberator EA entry should appear under the Expert Advisors node in the Navigator window (View > Navigator)

These pictures highlight the steps how to install the EA.






The setup application lists the available MT5 instances. Select one or multiple of them for installation target and click on the **Next**.


#### Note:

If you see an empty list then you probably need to install an MT5 first. In that case download and run the MT5 setup application from your preferred broker's web site. After that run again this EA setup application.

If you are an advanced user and you run the MT5 in portable mode from a custom location then copy this EA setup application into the Data Folder of the MT5, then run the EA setup application from that Data Folder. In order to find the Data Folder of the MT5 select the File > Open Data Folder in the MT5's menu.



When the installation is complete start the MT5 up and check that the EA appears in the **Navigator** window (**View** > **Navigator**):



Now everything is set up for the first activation of the RSI ForexLiberator Expert Advisor.


## 2.2 RSI ForexLiberator Expert Advisor First Time Activation

Step by step guide to get the EA up and running on a chart for the first time.


The following pictures demonstrate the first time activation of the RSI ForexLiberator Expert Advisor in a few steps.

#### Attach the EA to a chart

 Drag & drop the RSI ForexLiberator Expert Advisor from the Navigator window (View > Navigator) to a chart window. In the appearing properties window select the Dependencies tab and tick the checkbox Allow DLL imports:



#### 2. Go to the Common tab and tick the checkbox Allow Algo Trading:




#### Note:

#### Ensure that the

- Allow DLL imports and
- Allow Algo Trading

are **ticked** otherwise the RSI ForexLiberator EA is not able to start up.

#### 3. Select the Inputs tab:




This lists the parameters of the EA where the operational aspect of the RSI ForexLiberator EA can be set up. For more details see the RSI ForexLiberator EA Configuration Guide – for now click on the **OK** button and let the EA start up with default settings.

#### Note:

At the very first time the EA may prompt for the Access ID to verify that the usage of product is licensed.


The Access ID is pre-configured and is the same as the login name to the web support site. Feel free to change your Access ID at the Web Support Centre and ensure not to share it with anyone else. Enter the Access ID and click on the **Save** button:



**Tip:** If you do not remember your Access ID then click on the **Help! What is my Access ID?** to see it on your Web Support Centre user profile.


#### The RSI ForexLiberator EA is up and running

After successful authentication the RSI ForexLiberator EA starts up.



The RSI ForexLiberator Expert Advisor has been attached to the chart. The smiley face in the top-right corner shows that the initialisation of the RSI ForexLiberator Expert Advisor was successful and the EA is now looking for trading opportunities.

See the smiley face in the corner:



In case of a problem getting the EA up and running please refer to the Knowledgebase section.

## Chapter

## System Requirements

Overview of prerequisites in order to install and get the product up and running.

## 3.1 Operating System Requirements

In order to operate the RSI ForexLiberator EA a Microsoft Windows operating system is required which supports MetaQuotes MetaTrader version 5.00 platform.

Note that the MetaQuotes MetaTrader software is also known and often referred to as MT5.

## 3.2 Hardware Requirements

The minimum Random Access Memory (RAM) requirement is 1024MB (1GB), however 2048MB (2GB) RAM is recommended to avoid extended virtual memory usage. Note that this memory requirement is for MetaTrader application only, excluding other applications running at the same time (e.g. MS Office). If other applications are running parallel with MetaTrader application please increase the RAM requirement accordingly.

## 3.3 MetaTrader (MT5) Requirements and Settings

The EA is compatible with MetaQuotes MetaTrader platform version 5.00 build 4260 or higher. In general this is referred to as MT5 terminal, build 4260 or newer.

## 3.4 Forex Broker Requirements

The RSI ForexLiberator EA is compatible with both 4 and 5-digit data feeds based brokers. The RSI ForexLiberator EA automatically detects the type of the feed and adjusts the EA parameter pip values if and when necessary.

Both fixed and variable spread broker platforms are supported.

The broker account must support retail hedging mode in order for the EA to operate. Note that the netting mode broker account is not compatible with the EA.

The selected MetaTrader based broker should allow keeping open orders on the account for long period of time, i.e. the broker should not close and re-open orders over night for swap calculation, or should not merge open orders for any reason.

IMPORTANT: For smooth trade management the MetaTrader application and the EA should be online, up and running during all market open hours (usually Sunday to Friday).

## 3.5 Hedging Support Requirements

The broker account must support the hedging of trades when the option Both Buy & Sell Allowed on Same Pair at Same Time is selected for the Allow Buy & Sell the Same Pair at the Same Time.

Hedging support is not required on the broker account when the option Only One Direction Allowed on Same Pair at Same Time is selected for the Allow Buy & Sell the Same Pair at the Same Time.

Do not trade the broker account manually and/or by other EAs along with the RSI ForexLiberator EA as trading the same markets can result in unintended hedging of trades on the same market.

The broker account must support retail hedging mode in order for the EA to operate. Note that the netting mode broker account is not compatible with the EA.

## 3.6 Non-FIFO Support Requirements

The broker account must support the order handling in non-FIFO manner when the option Both Buy & Sell Allowed on Same Pair at Same Time is selected for the Allow Buy & Sell the Same Pair at the Same Time.

Do not trade the broker account manually and/or by other EAs along with the RSI ForexLiberator EA. Trading the same markets by multiple parties can result in demand to close a specific open trade first which is outside the control of the RSI ForexLiberator EA, i.e. blocking the trade executions and potentially causing losses.

The broker account must support retail hedging mode in order for the EA to operate. Note that the netting mode broker account is not compatible with the EA.

## 3.7 Account Type and Minimum Lot Size Requirements

The broker account must support retail hedging mode in order for the EA to operate. Note that the netting mode broker account is not compatible with the EA.

A so-called *Micro* broker account is necessary if the available funds for the EA trading is less than approx. \$1000. The micro account allows the EA to open a position with minimum lot size of 0.01. If you plan to use a broker account with the above funding please ensure that your broker account offers this minimum lot size.

An easy way to double check the minimum lot size available on the broker account is to attach the EA to a chart and check the Market Info section on the chart:

```
Market Info -
Spread - Current: 1.3 Avg: 1.3 Max: 1.3 at Server Time: 2019. 12.13 23:59:00
Lot - Size:100K Min:0.01 Step:0.01 Margin req:370.68 Pip value:USD 10.00
```

The Lot line shows Min:0.01 which tells that the minimum lot size requirement is 0.01 on this broker account.

## 3.8 ECN/STP Broker Accounts

Many brokers offer Electronic Communications Network (ECN) or Straight Through Processing (STP) accounts. Common behaviour for these accounts is the variable spread and market orders where no initial stop loss and take profit targets can be specified. In this case the market order must be submitted with no SL and TP values, and these values are to be set in the second step using an additional order to the opened ticket.

The RSI ForexLiberator EA is compatible with the above ECN/STP broker accounts and needs no additional settings to operate on them.

## Chapter

## **RSI ForexLiberator EA Configuration Guide**

The RSI ForexLiberator EA configuration guide.

In order to activate the RSI ForexLiberator EA attach it to a chart window - for more details see RSI ForexLiberator EA First Time Activation section.

## 4.1 Configuration and Operation Principles

The RSI ForexLiberator EA operational overview.

The RSI ForexLiberator EA manages only those tickets (a.k.a positions) on the account which belong to the RSI ForexLiberator EA: every order submitted to the account is marked with the Magic Number and, in return, only those tickets on the account will be considered by the RSI ForexLiberator EA which are marked with this Magic Number.

The RSI ForexLiberator EA may enter positions on multiple markets and keep them open for a period of time. The EA is NOT limited to the symbol of the chart it is attached to, it may open positions on other symbols as well.

In general it is recommended to run one RSI ForexLiberator EA on the same broker account at a time. This helps understanding the ongoing trades and troubleshoot situation if and when needed. If multiple RSI ForexLiberator EA instances are run at the same time (i.e. multiple charts hosting the RSI ForexLiberator EA) then each RSI ForexLiberator EA must have its own unique Magic Number configured for each chart.

Using multiple 3rd party expert advisors on the same account is only viable if each and all expert advisor can manage only their own tickets on the account by following the magic number based separation logic.


IMPORTANT: If you plan to use multiple expert advisors (other than the RSI ForexLiberator EA) on the same account please ensure upfront with the expert advisor providers that their EA's are suitable for that as per the above.

Market	MagicNumber
Single chart with the EA	EA default or any other
Multiple charts: EURUSD chart 1	15000
Multiple charts: EURUSD chart 2	15001
Multiple charts: EURUSD chart 3	15002
Multiple charts: GBPUSD chart 1	15003
Multiple charts: GBPUSD chart 2	15004
Multiple charts: GBPUSD chart 3	15005

## 4.2 RSI ForexLiberator EA Parameter Descriptions

The RSI ForexLiberator EA parameter descriptions.

## **4.2.1 TRADE ENTRY**




### **Direction of Initial Trade Entry**

## **Direction of Initial Trade Entry**

The RSI indicator may give a trade trigger and the direction of that trigger. This EA parameter decides to trade with that RSI trigger direction for the initial trade or against that.

Any potential topup trades are always entered with direction of the initial trade, regardless of the RSI indicator readings at that later time.



Direction of Initial Trade Entry	Description
Same as Trigger Direction	<ul> <li>The new trade is entered as:</li> <li>When the RSI indicator identifies a BUY opportunity -&gt; opens a BUY position.</li> <li>When the RSI indicator identifies a SELL opportunity -&gt; opens a SELL position.</li> </ul>
Reverse of Trigger Direction	<ul> <li>The new trade is entered as:</li> <li>When the RSI indicator identifies a BUY opportunity -&gt; opens a SELL position.</li> <li>When the RSI indicator identifies a SELL opportunity -&gt; opens a BUY position.</li> </ul>

Refer to the examples for more details.

- 1. Example Normal Entry
- 2. Example Reverse Entry

#### **RSI Period**

#### **RSI Period**

Used for the **Period** parameter of the RSI indicator.

The trade trigger and its direction is determined based on the RSI readings off the last three closed bars (preceding the currently forming bar):

- Buy (long) direction: the three RSI readings go down then up, i.e. a hook is formed in the oversold (bottom) area of the RSI indicator window.
- Sell (short) direction: the three RSI readings go up then down, i.e. a hook is formed in the overbought (upper) area of the RSI indicator window.

The initial trade's direction always follows the Direction of Initial Trade Entry selection. The direction of the subsequent topup trades always the same as of the initial trade.

The EA enters a new initial trade in line with the Entry Window settings. However, the entry time of the subsequent topup trades are not limited to the Entry Window period, i.e. they can take place at any time and they are only based on price actions.

Refer to the examples for more details.

- 1. Example Normal Entry
- 2. Example Reverse Entry

#### **RSI Applied Price**

### **RSI Applied Price**


Used for the Apply to parameter of the RSI indicator.



## **RSI OverBought/Sold Levels**

#### RSI OverBought/Sold Levels

Selects the values marking the overbought and oversold levels for the RSI indicator.



The following table shows what overbought and oversold values are used by the EA when an item is selected in the dropdown list:

RSI OverBought/Sold Levels	Overbought Area Used	Oversold Area Used
OBought 95, OSold 5	95 to 100	0 to 5
OBought 90, OSold 10	90 to 100	0 to 10
OBought 85, OSold 15	85 to 100	0 to 15

RSI OverBought/Sold Levels	Overbought Area Used	Oversold Area Used
OBought 80, OSold 20	80 to 100	0 to 20
OBought 75, OSold 25	75 to 100	0 to 25
OBought 70, OSold 30	70 to 100	0 to 30
OBought 65, OSold 35	65 to 100	0 to 35
OBought 60, OSold 40	60 to 100	0 to 40
OBought 55, OSold 45	55 to 100	0 to 45
OBought 51, OSold 49	51 to 100	0 to 49

The start and end values of the above ranges are inclusive when the RSI entry criteria is evaluated.

Refer to the examples for more details.

- 1. Example Normal Entry
- 2. Example Reverse Entry
- 3. Example Trade Not More Than 2 Out of Multiple Markets

#### **Price Gap**

#### Price Gap

Determines where the EA enters a new topup trade as the market price moves against the last topup by this number of pips. The topup trades will be gapped from each other by this number of pips. forming a ladder as the market price keeps moving against the initial trade.

Refer to the examples for more details.

- 1. Example Normal Entry
- 2. Example Reverse Entry
- 3. Example Trade Not More Than 2 Out of Multiple Markets

#### **Gap Scaling Start Level**

#### **Gap Scaling Start Level**

When the market price goes against the direction of the initial trade the Price Gap is scaled up or down. The scaling starts when the price moves against the initial trade by this number of levels and applied to all the subsequent levels.

Refer to the examples for more details.

- 1. Example Scale Price Gap Up by Rate
- 2. Example Scale Price Gap Down by Rate

#### **Gap Scaling Rate**

#### Gap Scaling Rate

The percent rate of scaling by which the price gap gets bigger or smaller. When the market price goes against the direction of the initial trade the Price Gap is scaled up or down by this rate. The scaling starts when the price moves against the initial trade by the configured price levels and applied to all the subsequent levels.

The scaling is applied based on the value of this Gap Scaling Rate parameter:

Price Gap Scaling Rate	Description
	Scales <b>UP</b> the price gap and it becomes bigger by that rate. For example:
Above 100	<ul> <li>130 scales up to 130% of the previous gap (i.e. up by 30%)</li> <li>150 scales up to 150% of the previous gap (i.e. up by 50%)</li> <li>200 scales up to 200% of the previous gap (i.e. up by 100%)</li> </ul>
Exactly 100	No change to the price gap size. 100 means keep it the same, at the 100% of the previous level's gap.
	Scales <b>DOWN</b> the price gap and it becomes smaller by that rate. For example:
Below 100	<ul> <li>80 scales down to 80% of the previous gap (i.e. down by 20%)</li> <li>50 scales down to 50% of the previous gap (i.e. down by 50%)</li> <li>30 scales down to 30% of the previous gap (i.e. down by 70%)</li> </ul>

Refer to the examples for more details.

- 1. Example Scale Price Gap Up by Rate
- 2. Example Scale Price Gap Down by Rate

### Minimum Gap Size

### Minimum Gap Size

The lower limit or the floor for the price gap scaling, in pips. The price gap scaling may reduce the gap by the rate configured. The EA ensures that the scaled down gap never becomes smaller than this Minimum Gap Size pips.

Refer to the examples for more details.

1. Example - Scale Price Gap Down by Rate

#### **Lots for Initial Trade Entry**

#### **Lots for Initial Trade Entry**

The number of lots which is used to enter the initial trade. This initial lots size may get adapted according to the latest broker account funds by the Initial Lots Adjustment at the time of the initial trade entry.

The subsequent topup trades may have different lots sizing according to the Topup Lots Multiplier and Topup Lots Change by Lots settings.

Refer to the examples for more details.

- 1. Example Same Position Size All the Time
- 2. Example Scale Lots Up by Multiplier
- 3. Example Scale Lots Down by Multiplier
- 4. Example Scale Lots Up by Amount
- 5. Example Scale Lots Down by Amount
- 6. Example Skip Topup and Scale Up by Multiplier
- 7. Example Skip Topups and Scale Down by Multiplier
- 8. Example Skip Topup and Scale Up by Amount
- 9. Example Skip Topups and Scale Down by Amount

#### **Topup Lots Multiplier**

#### **Topup Lots Multiplier**

The rate of change which is used to scale the lots size for the topup trades at each entry.

During the scaling the EA ensures that the scaled lots sizes stay within the broker required minimum and maximum lots range.

**Important:** The scaling values add up (compound) across the topup entries.

Topup Lots Multiplier	Description
	Scales <b>UP</b> the lots for the topup trade at the entry. For example:
Above 1.0	<ul> <li>1.3 scales up to 130% of the previous lots (i.e. up by 30%)</li> <li>1.5 scales up to 150% of the previous lots (i.e. up by 50%)</li> <li>2.0 scales up to 200% of the previous lots (i.e. up by 100%)</li> </ul>
Exactly 1.0	No change to the lots. 1.0 means keep it the same, at the 100% of the previous level's lots.
	Scales <b>DOWN</b> the lots for the topup trade at the next entry. For example:
Below 1.0	0.8 scales down to 80% of the previous lots (i.e. down by 20%)
	0.5 scales down to 50% of the previous lots (i.e. down by 50%)
	0.3 scales down to 30% of the previous lots (i.e. down by 70%)
Excatly 0.0	This lots multiplier is not used. Instead the Topup Lots Change by Lots is used to scale the lots.

Refer to the examples for more details.

- 1. Example Same Position Size All the Time
- 2. Example Scale Lots Up by Multiplier
- 3. Example Scale Lots Down by Multiplier
- 4. Example Skip Topup and Scale Up by Multiplier
- 5. Example Skip Topups and Scale Down by Multiplier

#### **Topup Lots Change by Lots**

#### **Topup Lots Change by Lots**

The **amount** of change which is used to scale the lots size for the topup trades at each entry.

During the scaling the EA ensures that the scaled lots sizes stay within the broker required minimum and maximum lots range.

**Important:** The scaling values add up (compound) across the topup entries.

Topup Lots Change by Lots	Description	
	Scales <b>UP</b> the lots for the topup trade at the entry. For example:	
	0.01 scales up by adding 0.01 to the previous lots (i.e. up by 0.01 lots)	
Above 0.00	<ul> <li>0.50 scales up by adding 0.05 to the previous lots (i.e. up by 0.05 lots)</li> </ul>	
	0.10 scales up by adding 0.10 to the previous lots (i.e. up by 0.10 lots)	

Topup Lots Change by Lots	Description
Exactly 0.00	This change by lots is not used. Instead the Topup Lots Multiplier is used to scale the lots.
Below 0.00	Scales <b>DOWN</b> the lots for the topup trade at the next entry. For example:  • -0.01 scales down by subtracting 0.01 from the previous lots (i.e. down by 0.01 lots)  • -0.05 scales down by subtracting 0.05 from the previous lots (i.e. down by 0.05 lots)  • -0.10 scales down by subtracting 0.10 from the previous lots (i.e. down by 0.10 lots)

Refer to the examples for more details.

- 1. Example Same Position Size All the Time
- 2. Example Scale Lots Up by Amount
- 3. Example Scale Lots Down by Amount
- 4. Example Skip Topup and Scale Up by Amount
- 5. Example Skip Topups and Scale Down by Amount

#### **Topup Trades to Skip**

## **Topup Trades to Skip, Count**

Provides an option **not** to enter the first couple of topup trades after the initial trade. The scaling of the topup lots still takes place even if some of the first topup trades are skipped.

Refer to the examples for more details.

- 1. Example Skip Topup and Scale Up by Multiplier
- 2. Example Skip Topups and Scale Down by Multiplier
- 3. Example Skip Topup and Scale Up by Amount
- 4. Example Skip Topups and Scale Down by Amount

#### **Initial Lots Adjustment: Base Account Equity Amount**

#### **Initial Lots Adjustment: Base Account Equity Amount**

Over time the broker account's equity may go up or down. The Initial Lots Adjustment allows for adapting the lots size of the initial trades to the account equity changes over time.

This parameter is the starting (reference) equity amount at the time of first use of the EA. This starting equity is later compared to the broker account equity amount at the time of a new initial trade entry and the lots size for the initial trade gets adjusted accordingly. The initial trade's lots may get adjusted up or down depending on the Required Equity Change and Initial Lots Adjustment settings. The subsequent topup trades apply their topup lots scaling to this adjusted inital lots size.

Refer to the examples for more details.

- 1. Example Same Initial Lots All the Time
- 2. Example Initial Lots Adjustment Upward Only
- 3. Example Initial Lots Adjustment Up & Down

#### **Initial Lots Adjustment: Required Equity Change**

### **Initial Lots Adjustment: Required Equity Change**

Determines how often to scale the lots for the initial trades. Every time the broker account equity grows (or decreases) by this much percentage then the initial trades' lots size gets adjusted up (or down).

Refer to the examples for more details.

- 1. Example Same Initial Lots All the Time
- 2. Example Initial Lots Adjustment Upward Only
- 3. Example Initial Lots Adjustment Up & Down

#### **Initial Lots Adjustment: Initial Lots Adjustment**


#### **Initial Lots Adjustment: Initial Lots Adjustment**

Determines by how much to scale the lots for the initial trades. Every time the broker account equity grows (or decreases) by the required percentage then the initial trades' lots size gets adjusted up (or down) by this percentage.

Refer to the examples for more details.

- 1. Example Same Initial Lots All the Time
- 2. Example Initial Lots Adjustment Upward Only
- 3. Example Initial Lots Adjustment Up & Down

### 4.2.2 INITIAL TRADE MANAGEMENT



#### **Initial: Take Profit**

#### Initial: Take Profit

Target profit value in pips for a new intial trade. The trade's TP is set to this Take Profit value on the broker server side.

When topup trades are entered this take profit is no longer used. Instead, a single exit price is calculated for all the basket of trades on the same market to achieve the target dollar amount or pips profit.

Refer to the examples for more details.

- 1. Example Entry with TP Only
- 2. Example Entry with TP and Hidden TP
- 3. Example Entry with TP, Hidden TP and Trailing

- 4. Example Trade Not More Than 2 Out of Multiple Markets
- 5. Example FIFO Trading

#### Initial: Hidden TP

#### Initial: Hidden TP

An alternative Take Profit value, in pips, which is not visible to the broker server and tracked by the EA. This hidden TP must be smaller than the Initial: Take Profit.


When only the initial trade is open (i.e. no topup trades yet) and the initial trade reaches this hidden TP profit then the EA closes off the initial trade.

When topup trades are entered this hidden TP is no longer used.

Refer to the examples for more details.

- 1. Example Entry with TP Only
- 2. Example Entry with TP and Hidden TP
- 3. Example Entry with TP, Hidden TP and Trailing
- 4. Example Trade Not More Than 2 Out of Multiple Markets
- 5. Example FIFO Trading

### **Initial Trade Trailing Stop**



## **Trailing Start at Profit**

The trailing feature protects the profits so far achieved by moving the positions stop loss alongside the market price movements, keeping the stop loss behind the last high (or low) of price by a fixed distance. This trailing is only applied to the initial trade. When topup trades are entered this trailing feature is no longer used.

The EA starts off the trailing of price by moving an existing open position's stop loss when the position gets into profit by at least this Trailing Start at Profit pips. The Trailing SL distance is used to set the stop loss of the position. Once the trailing got activated, the SL gets adjusted every time when the price moves further and the position gets further into profit by Trailing Stepping pips.

Refer to the examples for more details.

- 1. Example Entry with TP Only
- 2. Example Entry with TP and Hidden TP
- 3. Example Entry with TP, Hidden TP and Trailing
- 4. Example Trade Not More Than 2 Out of Multiple Markets
- 5. Example FIFO Trading

### Trailing SL

When trailing feature is activated, the SL of the position is set by this amount of pips behind the last high (or low) of price.

Refer to the examples for more details.

- 1. Example Entry with TP Only
- 2. Example Entry with TP and Hidden TP
- 3. Example Entry with TP, Hidden TP and Trailing
- 4. Example Trade Not More Than 2 Out of Multiple Markets


### **Trailing Stepping**

When trailing feature is activated this parameter tells how often the SL of the position has to be adjusted. Every time the position gets into further profit by this stepping pips the EA adjusts the SL of the position to lock in to the new profits.

Refer to the examples for more details.

- 1. Example Entry with TP Only
- 2. Example Entry with TP and Hidden TP
- 3. Example Entry with TP, Hidden TP and Trailing
- 4. Example Trade Not More Than 2 Out of Multiple Markets

#### 4.2.3 HEDGE TRADES MANAGEMENT



#### Allow Buy & Sell the Same Pair at the Same Time

### Allow Buy & Sell the Same Pair at the Same Time

Over time there could be buy as well as sell triggers on the same market, potentially resulting in hedged positions on the market. This EA parameter turns on or off the hedged trading of the same market.

Note: The EA manages and monitors its own trades only. Trades entered manually or by other EAs may interfere and result in hedging. If hedging is not desired then ensure that no trades are placed manually or by other EAs on the same Pairs to Trade or Pairs to Get Out.

Important: The EA automatically turns off hedged trading for the Pairs to Get Out, i.e. only allowing the one direction trading for those pairs. The purpose of this is to expedite getting out of those markets, however this may involve higher drawdowns for some or all of those markets.



Allow Buy & Sell the Same Pair at the Same Time	Description
Only One Direction Allowed on Same Pair at Same Time	The EA is NOT allowed to enter <b>buy</b> trades should there be existing open <b>sell</b> trades on the same market. Furthermore, the EA is NOT allowed to enter <b>sell</b> trades should there be existing open <b>buy</b> trades on the same market. This avoids the use of hedge on a traded market.
Both Buy & Sell Allowed on Same Pair at Same Time	The EA is allowed to enter and keep open both buy and sell trades over time on the same market, potentially resulting in hedged trades on the same market.




Attention: For brokers where hedging is not availabe or FIFO is observed the Only One Direction

Refer to the examples for more details.

- 1. Example Stop Trading of Certain Pairs
- 2. Example FIFO Trading

#### 4.2.4 BASKET OF TRADES MANAGEMENT



### **Pair: Target Closure \$ Amount**

### **Pair: Target Closure \$ Amount**

The target profit dollar amount for the initial and topup trades together on the same market, at which amount the closure of those initial and topup trades should take place. This is the exit point in dollar amount for all the open trades on the same market. After the closure the EA may stop or carry on with trading depending on the Portfolio: Reentry After Closure selection.

When there are no topups yet, but only the initial trade is open then this EA parameter is not used. Regarding the initial trade exit refer to the INITIAL TRADE MANAGEMENT section.

Refer to the examples for more details.

- 1. Example Closure at Profit Amount
- 2. Example Closure at Pips Profit
- 3. Example Trade Not More Than 2 Out of Multiple Markets

#### **Pair: Target Profit Pips Closure**

#### **Pair: Target Profit Pips Closure**

The target profit in pips for the initial and topup trades together on the same market, at which pips profit the closure of those initial and topup trades should take place. This is the exit point in pips for all the open trades on the same market. After the closure the EA monitors all the markets for a new initial entry as usual.

When there are no topups yet, but only the initial trade is open then this EA parameter is not used. Regarding the initial trade exit refer to the INITIAL TRADE MANAGEMENT section.

Refer to the examples for more details.

- 1. Example Closure at Profit Amount
- 2. Example Closure at Pips Profit
- 3. Example Trade Not More Than 2 Out of Multiple Markets

#### Portfolio: Closure at Profit \$ Amount

#### Portfolio: Closure at Profit \$ Amount

The target profit dollar amount for all the open trades across all the markets, at which amount the closure of all trades should take place. Should the profits of all the open trades by the EA reach or exceed this amount the EA closes off all its open trades across all the markets. After the closure the EA may stop or carry on with trading depending on the Portfolio: Reentry After Closure selection.

Refer to the examples for more details.

- 1. Example Closure at Portfolio Profit
- 2. Example Stop Trading After Portfolio Closure

#### Portfolio: Closure at Maximum Loss \$ Amount

#### Portfolio: Closure at Maximum Loss \$ Amount

The dollar amount losses for all the open trades across all the markets, at which amount the closure of all trades should take place. Should the losses of all the open trades by the EA reach or exceed this amount the EA closes off all its open trades across all the markets. After the closure the EA may stop or carry on with trading depending on the Portfolio: Reentry After Closure selection.

Refer to the examples for more details.

- 1. Example Closure at Portfolio Loss
- 2. Example Stop Trading After Portfolio Closure

#### **Portfolio: Reentry After Closure**

### **Portfolio: Reentry After Closure**

Determines how to carry on with trading after a closure of the portfolio.



Portfolio: Reentry After Closure	Description
Reentry Disabled	Trading is <b>not</b> allowed after a portfolio closure. The EA displays a popup window about the closeout and stops trading. This popup window must be dismissed in order to allow the EA to start trading again.
Reentry Allowed	Trading <b>is</b> allowed without any delay after a portfolio closure. This means that the EA monitors the markets for new trade opportunities and enters new initial trades as usual after a portfolio closure.

Refer to the examples for more details.

- 1. Example Closure at Portfolio Profit
- 2. Example Closure at Portfolio Loss
- 3. Example Stop Trading After Portfolio Closure

#### **Pairs to Trade**

#### Pairs to Trade

The list of market names (e.g. forex pair names), separated by a space character, the EA is to trade.

When the EA should only trade the symbol of the chart (to which the EA is attached) then enter the word **chart** into this EA input.

In order to stop trading a pair with open trades remove the pair name from this Pairs to Trade and add it to the Pairs to Get Out. For more details refer to the Example - Stop Trading of Certain Pairs.

Refer to the examples for more details.

- 1. Example Trade Not More Than 2 Out of Multiple Markets
- 2. Example Trade Max 1 Pair Involving the Same Currency
- 3. Example Stop Trading of Certain Pairs

#### Pairs to Get Out

#### Pairs to Get Out

The list of market names (e.g. forex pair names) for which the EA is to complete the ongoing trading sequence and after that to stop any further trading. For these pairs the EA still manages any open trades, may enter new topup trades in the future as necessary, and closes the open trades when the ongoing trading sequences reach their targets. However, the EA will not enter new initial trade on these pairs after the closure of the open trades. This provides a managed way to get out of trading of the listed markets over time. Once the EA has closed all open trades on a listed market that market name can be safely removed from this list.

All the EA settings - including the likes of the gap scaling, lots scaling, pair and portfolio targets (pips or amount), maximum traded pairs and currency exposure etc - are still applicable to this list, with the exception of the hedged trades settings:

Important: For the pairs listed in the Pairs to Get Out the hedged trading is turned off automatically: the Only One Direction Allowed on Same Pair at Same Time is selected for the Allow Buy & Sell the Same Pair at the Same Time for these particular pair names. The purpose of this is to expedite getting out of those markets, however this may involve higher drawdowns for some or all of those markets.

Refer to the examples for more details.

1. Example - Stop Trading of Certain Pairs

#### **Maximum Traded Pairs**

#### **Maximum Traded Pairs**

This limits the EA how many different markets can be traded at the same time. The combined Pairs to Trade and Pairs to Get Out lists may have 10 or more markets listed, however this EA parameter can limit the EA to trade only a certain number of them the most at the same time.

Refer to the examples for more details.

- 1. Example Trade Not More Than 2 Out of Multiple Markets
- 2. Example Stop Trading of Certain Pairs

#### **Maximum Currency Exposure**

#### **Maximum Currency Exposure**

This limits how many different pairs can be traded at the same time involving the same currency. Listing multiple EUR crosses like EURUSD EURJPY EURCHF as part of the Pairs to Trade and Pairs to Get Out while setting this parameter to 1 will ensure that the EA can have open trades for only one of those EUR crosses at the same time.

Refer to the examples for more details.

1. Example - Trade Max 1 Pair Involving the Same Currency

#### Maximum Topup Trades per Pair per Direction

#### Maximum Topup Trades per Pair per Direction

This limits the EA how many topup trades can be entered on the same market. This limit is indendently applied to the buy and the sell directions: if this limit is set to 10 then there could be up to 10 topups in the buy direction and another 10 topups in the sell direction, that is 20 topups in total, on the same market.

### **Topup TP Mode**

### **Topup TP Mode**

A choice whether to make the TP visible on the broker server or not. This choice is in effect when 1 or more topup trades have been entered after the initial trade.




Topup TP Mode	Description
Set Topup TP with Broker	The TP <b>is visible</b> to the broker server and the TP <b>is set</b> for the open trades on the broker server. The broker server closes off the open trades on that market when the market price reaches the TP.
Hide Topup TP from Broker	The TP is <b>not visible</b> to the broker server and the TP is <b>not set</b> for the open trades on the broker server. The EA tracks the market price and when the market price reaches the TP the EA closes off all the open trades on that market.

Refer to the examples for more details.

1. Example - FIFO Trading

### 4.2.5 PRUNING OF TRADES



#### **Start Pruning at Trade Count in a Pair Direction**

#### Start Pruning at Trade Count in a Pair Direction

The number of open trades on a pair, in either buy or sell direction, when pruning is to take place for that direction. The EA looks for opportunities to reduce the number of those open trades once this trade count is reached.

The pruning has two tiers:

- Pruning by pair of trades: Trade Pair Pruning Approach
- Pruning by scaled gap retracement: Gap Pruning From This Scale of Initial Gap

The gap retracement based pruning kicks in when the gap scaling is turned on and the last gap grows to a certain size. Otherwise the pruning is performed by pair of trades.

Refer to the examples for more details.

- 1. Example Balanced Amount Pruning
- 2. Example First & Last Trades Pruning
- 3. Example Gap Pruning

#### Related reference

Trade Pair Pruning Approach on page 30 Gap Pruning From This Scale of Initial Gap on page 31

#### **Trade Pair Pruning Approach**

#### Trade Pair Pruning Approach

Selects the way how to pick the pair of open trades for pruning. The pruning always picks two open trades which are in the same direction (both buy or sell) and on the same pair.



Trade Pair Pruning Approach	Description
Balanced Amount Pruning	When the most recent topup retraces to the previous level then the EA matches this topup (which is in profit) with another trade which has suitable losses to close out those two trades with a combined small profit or small loss amount. In the case of no matching trade was available to deliver a small profit or loss then no pruning takes place, i.e. no pair of trades gets closed out.  The small combined profit amount outcome is preferred over the a
	small loss amount - provided that the small loss is not more than 10% of the profits of the retracing topup trade.
First & Last Trades Pruning	When the most recent topup retraces to the previous level the EA closes that topup and the initial (or oldest) trades. This approach does not take into consideration the combined profit or loss amounts, instead it reduces the overall price range covered by the open trades.

Refer to the examples for more details.

- 1. Example Balanced Amount Pruning
- 2. Example First & Last Trades Pruning

#### Related reference

Start Pruning at Trade Count in a Pair Direction on page 30 Gap Pruning From This Scale of Initial Gap on page 31

#### **Gap Pruning From This Scale of Initial Gap**

### **Gap Pruning From This Scale of Initial Gap**

The gap pruning kicks in when the latest gap size grows into this scale rate of the initial gap. As an example, when this EA parameter has the value of 200, and the latest gap becomes twice as big as the initial gap then this gap pruning gets applied instead of the Trade Pair Pruning Approach.

The gap pruning closes the most recent topup trade when it retraces half of the last gap size. This gap pruning makes an attempt to cash-in some profits when the gap grew wide.


Refer to the examples for more details.

1. Example - Gap Pruning

#### Related reference

Start Pruning at Trade Count in a Pair Direction on page 30 Trade Pair Pruning Approach on page 30


## 4.2.6 TIME OF DAY FOR INITIAL ENTRY



#### **Reference Time Selection**

#### **Reference Time Selection**

Selects the nature of the time used by the EA when time specific actions are performed.




Reference Time Selection	Description
Broker Server Time	Entry window hour and minute settings are relevant to the broker's server time. See below picture showing the broker server time in the Market Watch window.
PC Local Time	Entry window hour and minute settings are relevant to the local time of the PC hosting the MT5 terminal and EA. When setting up the time parameters consider the time zone differences between the market open hours versus the PC local time.
	Entry window hour and minute settings are relevant to the selected GMT offset.
GMT Time (Set GMT Offset Below)	This feature is useful to keep the entry window hour and minute settings the same when the EA is executed across different brokers. In this case only the broker GMT offset needs to be set on the different brokers' MT5 instances, and the EA adjusts automatically the entry window for the broker.  In this case, use the GMT Offset of Broker to select the broker offset and always set the window hour values in GMT +0 time zone.

#### **GMT Offset of Broker**

#### **GMT Offset of Broker**

The time zone shift of the MT5 broker's server time. This parameter is only required if GMT Time option is selected for the Reference Time Selection.



Unfortunately MT5 terminal does not provide this broker GMT offset information therefore a query to the broker maybe needed to get this value. As an alternative, one may make an attempt to calculate this offset through the following steps:

1. The Market Watch window's header shows the broker's server time, press Ctrl+M in the MT5 terminal:



This time can be compared to the GMT+0 time to calculate the GMT offset of the broker.

- 2. In a web browser search for gmt time keywords to see the current GMT time.
- 3. Then compare the search result of current GMT time to the current time displayed by the Market Watch window of the MT5 terminal. The difference of the two times gives the broker GMT offset.

Based on past experience, with no guarantee that the information is correct, these are a few sample broker GMT offsets observed as of July 2015:

MT5 Terminal	Broker	GMT Offset
AxiTrader	AxiCorp Financial Services Pty Ltd	+3
IC Markets	International Capital Markets Pty Ltd	+3
InstaForex	InstaForex Companies Group	+3
FXCM	Forex Capital Markets Inc	+3

MT5 Terminal	Broker	GMT Offset
ThinkForex	TF Global Markets (Aust) Pty Ltd	+3
RoboForex EU	RoboForex (CY) Ltd	+3
Tallinex	Tallinex Ltd	0
Oanda	OANDA Corporation	-4
MB Trading FX	MB Trading Futures Inc	-4

The value in the GMT Offset column could be used for the EA parameter GMT Offset of Broker.

### **Entry Window From Hour/Minute - Entry Window Until Hour/Minute**

### **Entry Window From Hour/Minute - Entry Window Until Hour/Minute**

Limits the period of a day when a new position entry may take place.

The From Hour & Minute is inclusive, while the Until Hour & Minute is exclusive. The following table shows examples how to configure these parameters for the entry window period:

Desired Entry Period	Entry Window From	Entry Window Until
8 – 10 (i.e. 8:00.00–9:59.59)	Hour = 8 & Minute = 0	Hour = 10 & Minute = 0
10 – 17 (i.e. 10:00.00-16:59.59)	Hour = 10 & Minute = 0	Hour = 17 & Minute = 0
All Day	Hour = 0 & Minute = 0	Hour = 24 & Minute = 0

The entry window from and until hours are specific to the selected time at Reference Time Selection.

#### **Monday ... Sunday Trade Entry**


### Monday ... Sunday Trade Entry

Days allowed for new position entry. Subsequent management of stop loss or exit of already open trades may happen outside of the enabled days, only the entry of new positions is limited to the selected days:

Monday Trade Entry [select]	Entry Enabled ~
Tuesday Trade Entry [select]	No Entry
Wednesday Trade Entry [select]	Entry Enabled
Thursday Trade Entry [select]	Entry Enabled
Friday Trade Entry [select]	Entry Enabled
Saturday Trade Entry [select]	Entry Enabled
Sunday Trade Entry [select]	Entry Enabled

Day of Week Trade Entry	Description
	No new entry is executed on that day.
No Entry	Stop Loss management, if turned on, for existing open positions are still executed as normal.
Entry Enabled	New entry is allowed for the day when all other entry criteria are met.

## **4.2.7 MISCELLANEOUS**



#### **Closeout Summary Text Colour**

### **Closeout Summary Text Colour**


The colour of the text in the chart describing the summary of the closure, e.g. upon Initial: Hidden TP or Portfolio: Closure at Maximum Loss \$ Amount events.



#### **Closeout Text Display**

### **Closeout Text Display**

The presentation of the closure summary in the chart area.



Closeout Text Display	Description
No Text Displayed	No details of the closeout gets displayed in the chart area.
Show Horizontal Text	The details of the closeout gets displayed in a <b>horizontal</b> line in the chart area.
Show Vertical Text	The details of the closeout gets displayed in a <b>vertical</b> line in the chart area.

### **BUY:Approx. Closeout Price Level Colour**

#### **BUY:Approx. Closeout Price Level Colour**

The colour of the line in the chart area giving an approximate estimate where the exit to take place for open sell trades. The exit level is determined by one of the Initial: Take Profit, Initial: Hidden TP, Pair: Target Closure \$ Amount or Pair: Target Profit Pips Closure.

Important: Due to the variable spread, commissions, exchange rate fluctuations etc this line represents a best effort estimate only. The actual closure may take place below or above this estimated line.



## **SELL:Approx. Closeout Price Level Colour**

#### **SELL:Approx. Closeout Price Level Colour**

The colour of the line in the chart area giving an approximate estimate where the exit to take place for open buy trades. The exit level is determined by one of the Initial: Take Profit, Initial: Hidden TP, Pair: Target Closure \$ Amount or Pair: Target Profit Pips Closure.

Important: Due to the variable spread, commissions, exchange rate fluctuations etc this line represents a best effort estimate only. The actual closure may take place below or above this estimated line.



#### **Pair Name Prefix & Suffix**

#### **Pair Name Prefix & Suffix**

There are standard market names which are commonly used for currency pairs, like EURUSD, GBPUSD, USDCHF, USDJPY etc. Many broker offers these standard market names on their MT5 platform, however some brokers may add some prefix or suffix to the market names resulting in broker specific symbols like EURUSDecn, EURUSD.r or mEURUSD etc.

As a convenience, the EA makes an attempt to discover the broker specific prefix and suffix and use those automatically. Alternatively, the prefix and the suffix can be manually configured as well. The below table shows the different approaches how to configure the prefix and suffix parts of the market symbols for trading.

Approach	Input Entered into Pair Name Prefix & Suffix	Trading Outcome Examples
		When the EA is attached to the EURUSD chart then it trades the
		EURUSD
	chart	GBPUSD
The chart's		USDCHF
symbol is used to automatically discover the prefix & suffix		etc symbols with no prefix or suffix.
		When the EA is attached to the EURUSD <u>.r</u> chart then it trades the
		EURUSD <u>.r</u>
		GBPUSD <u>.r</u>
		USDCHF <u>.r</u>
		etc symbols with the .r suffix.


Approach	Input Entered into Pair Name Prefix & Suffix	Trading Outcome Examples	
		When the EA is attached to the <u>m</u> EURUSD <u>.r</u> chart then it trades the	
		<u>m</u> EURUSD <u>.r</u>	
		<u>m</u> GBPUSD <u>.r</u>	
		<u>m</u> USDCHF <u>.r</u>	
		etc symbols with the <b>m</b> prefix and <b>.r</b> suffix.	
		The EA always trades the	
	.r	EURUSD <u>.r</u>	
Manual entry of suffix only		GBPUSD <u>.r</u>	
,		USDCHF <u>.r</u>	
		etc symbols with the .r suffix.	
		The EA always trades the	
		<u>m</u> EURUSD <u>.r</u>	
Manual entry of prefix & suffix	m .r	<u>m</u> GBPUSD <u>.r</u>	
		<u>m</u> USDCHF <u>.r</u>	
		etc symbols with the ${\bf m}$ prefix and ${\bf .r}$ suffix.	

If the prefix and suffix should be added to other non-FOREX symbol names as well (like US30) then add the word always to the end of the Pair Name Prefix & Suffix.

#### **Tick Scaling for CFD Markets**

### **Tick Scaling for CFD Markets**

Provides a consistent tick, pip, cent and point values across various markets and brokers. This is specific to stock indices, metal, commodity etc markets keeping the cent or dollar unit consistently applied. Wherever the EA is configured with a 'Pip' value then it is consistently mapped to the cent or dollar unit for those non-FOREX markets.



Tick Scaling for CFD Markets	Description
Auto Scale for Index Markets	Based on the characteristics of the market the EA automatically recognizes if the underlying market was a stock index market, like the US30, GER30 or JP225 etc. In this case the 'pip' values configured for the EA are scaled up to the 'dollar' value of the index: 12345.67
Never Scale	The EA does not scale up the 'pip' values even if the market could be recognized as a stock index market.
Always Scale	The EA applies the scaling up of the 'pip' values to the 'dollar' value even if the market could not be recognized as stock index market. This option is useful if the 'dollar' based approach is desired for trading.

**Note:** The EA always deals with the fractional pip values therefore there is no need to increase the 'pip' values for brokers with 1, 3 or 5-digit data feed.

### Examples:

Trading Approach	Chart of Market	Stop Loss EA Parameter Value	Tick Scaling for CFD Markets Value	Buy Entry Fill Price	Calculated Stop Loss Value	Description
Index market with \$1.00 unit	US30	100	Auto Scale for Index Markets Alternative: Always Scale	26 <u>1</u> 23.90	26 <u>0</u> 23.90	The EA scales the 100 'pips' parameter to market price of 100.00 US dollar units (i.e. 100.00 points)
FOREX pair with 0.0001 unit	EURUSD	100	Auto Scale for Index Markets Alternative: Never Scale	1.1 <u>3</u> 412	1.1 <u>2</u> 412	The EA keeps the 100 'pips' parameter as it is
Gold market with \$0.01 unit	XAUUSD	100	Auto Scale for Index Markets Alternative: Never Scale	128 <u>8</u> .23	128 <u>7</u> .23	The EA maps the 100 'pips' parameter to 100 cent units
Gold market with \$1.00 unit	XAUUSD	100	Always Scale	1 <u>2</u> 88.23	1 <u>1</u> 88.23	The EA maps the 100 'pips' parameter to 100 dollar units
Oil market with \$0.01 unit	USOil	100	Auto Scale for Index Markets Alternative: Never Scale	5 <u>6</u> .752	5 <u>5</u> .752	The EA maps the 100 'pips' parameter to 100 cent units

Trading Approach	Chart of Market	Stop Loss EA Parameter Value	Tick Scaling for CFD Markets Value	Buy Entry Fill Price	Calculated Stop Loss Value	Description
Oil market with \$1.00 unit	USOil	10	Always Scale	<u>5</u> 6.752	<u>4</u> 6.752	The EA maps the 10 'pips' parameter to 10 dollar units
Copper market with \$0.01 unit	COPPER	100	Auto Scale for Index Markets Alternative: Never Scale	<u>2</u> .9245	<u>1</u> .9245	The EA maps the 100 'pips' parameter to 100 cent units
Cocoa market with \$0.01 unit	COCOA	100	Auto Scale for Index Markets Alternative: Never Scale	2 <u>1</u> 60	2 <u>0</u> 60	The EA maps the 100 'pips' parameter to 100 cent units
Natural gas market with \$0.01 unit	NGAS	100	Auto Scale for Index Markets Alternative: Never Scale	<u>2</u> .843	<u>1</u> .843	The EA maps the 100 'pips' parameter to 100 cent units

### **Magic Number**

#### **Magic Number**

The EA marks its orders with this value when submitting to the broker account, and picks up orders which are marked with this magic number value. When you want to have multiple charts with the EA at the same time then change this MagicNumber to a new and unique number for each chart. Also ensure that none of other 3rd party EAs are using the same MagicNumber value. See Configuration and Operation Principles section for more explanation.

# 4.2.8 Examples

Settings examples.

#### **Example - Normal Entry**

#### **Example - Normal Entry**

Goal: I want bounce back trades which are triggered in the RSI 0-20 oversold or RSI 80-100 overbought area. I want to use the 4 period RSI indicator and the first topup to enter when the price moves 30 pips against the initial trade.

- **How-to:** Here is an example EA configuration how to achieve the above:
  - 1. RSI Period = 4
  - 2. RSI OverBought/Sold Levels = OBought 80, OSold 20
  - 3. Price Gap = 30
- **Description:** The EA monitors all the markets listed at the Pairs to Trade. When the RSI(4) indicator forms a hook in the oversold (0-20) or overbought (80-100) area on a market then the EA enters an initial trade if that market is not yet traded in that direction. The initial trade is entered as a buy in the oversold and a sell in the overbought RSI area. That initial trade gets closed off when it hits one of its targets. Should the initial trade go into 30 pips loss the EA enters the first topup. Every time the last topup goes into 30 pips loss the EA again enters a subsequent topup. The basket of the initial and the topup trades on a market gets closed off when their combined profit reaches the target amount or target pips profits.

#### **Example - Reverse Entry**

#### **Example - Reverse Entry**

- Goal: I want trend continuation trades which are triggered in the RSI 0-20 oversold or RSI 80-100 overbought area. I want to use the 4 period RSI indicator and the first topup to enter when the price moves 30 pips against the initial trade.
- How-to: Here is an example EA configuration how to achieve the above:
  - 1. Direction of Initial Trade Entry = Reverse Trigger Direction
  - **2.** RSI Period = 4
  - 3. RSI OverBought/Sold Levels = OBought 80, OSold 20
  - **4.** Price Gap = 30
- Description: The EA monitors all the markets listed at the Pairs to Trade. When the RSI(4) indicator forms a hook in the oversold (0-20) or overbought (80-100) area on a market then the EA enters an initial trade if that market is not yet traded in that direction. The initial trade is entered as a sell (reverse of buy) in the oversold and a buy (reverse of sell) in the overbought RSI area. That initial trade gets closed off when it hits one of its targets. Should the initial trade go into 30 pips loss the EA enters the first topup. Every time the last topup goes into 30 pips loss the EA again enters a subsequent topup. The basket of the initial and the topup trades on a market gets closed off when their combined profit reaches the target amount or target pips profits.

#### **Example - Entry with TP Only**

#### **Example - Entry with TP Only**

- Goal: I want to use 30 pips for Take Profit for the initial trade. This TP is sent with the trade to the broker server and visible to other traders. I do not want to use hidden TP which is only visible to
- **How-to:** Here is an example EA configuration how to achieve the above:
  - 1. Initial: Take Profit = 30
  - 2. Initial: Hidden TP = 0
  - 3. Trailing Start at Profit = 0
- Description: Upon a new trade trigger on a not yet traded market the EA enters the initial trade. The EA sets the 30 pips TP for the open initial trade. This TP is sent to the broker server therefore the broker can see it and close the trade when the market price hits the TP.

#### **Example - Entry with TP and Hidden TP**

#### **Example - Entry with TP and Hidden TP**

Goal: I want to use 30 pips for Take Profit for the initial trade. This TP is sent with the trade to the broker server and visible to other traders. I also want to use 25 pips for hidden TP which is only visible to me.

- **How-to:** Here is an example EA configuration how to achieve the above:
  - 1. Initial: Take Profit = 30
  - 2. Initial: Hidden TP = 25
  - 3. Trailing Start at Profit = 0
- **Description:** Upon a new trade trigger on a not yet traded market the EA enters the initial trade. The EA sets the 30 pips TP for the open initial trade. This TP is sent to the broker server therefore the broker can see it and close the trade when the market price hits the TP. The EA also monitors the market price and closes off the initial trade when the price hits the 25 pips hidden TP.

#### **Example - Entry with TP, Hidden TP and Trailing**

# **Example - Entry with TP, Hidden TP and Trailing**

- Goal: I want to use 30 pips for Take Profit for the initial trade. This TP is sent with the trade to the broker server and visible to other traders. I also want to use 25 pips for hidden TP which is only visible to me. I want to trail the initial trade when it reaches 10 pips profit, with 8 pips trailing stop loss. The trailing should happen every time the initial trade makes another 2 pips profit.
- **How-to:** Here is an example EA configuration how to achieve the above:
  - 1. Initial: Take Profit = 30
  - 2. Initial: Hidden TP = 25
  - 3. Trailing Start at Profit = 10
  - 4. Trailing SL = 8
  - 5. Trailing Stepping = 2
- Description: Upon a new trade trigger on a not yet traded market the EA enters the initial trade. The EA sets the 30 pips TP for the open initial trade. This TP is sent to the broker server therefore the broker can see it and close the trade when the market price hits the TP. The EA also monitors the market price and closes off the initial trade when the price hits the 25 pips hidden TP. Furthermore, the EA starts adjusting the SL of the initial trade when trade gets into 10 pips profit. At the start the EA sets the SL to 8 pips behind the market price high for a buy (or low for a sell), then keeps updating the SL every time the price makes another high (or low) by 2 pips or more. During trailing, the EA keeps the SL of the initial trade 8 pips behind the recent market price high (or low).

#### **Example - Trade Not More Than 2 Out of Multiple Markets**

#### **Example - Trade Not More Than 2 Out of Multiple Markets**

Goal: I want to monitor the EURUSD, GBPUSD, AUDUSD, USDCAD and USDCHF markets but trade not more than 2 of them at the same time. I want to use the RSI 0-25 & 75-100 ranges for triggers. For the initial trade I want to use 30 pips take profit sent to the broker along with 25 pips hidden TP, and trailing SL of 10 pips which kicks off at 12 pips profit and the SL to be adjusted after 1 pip of extra profit. I want to add topups when the intial trade goes into 30 pips loss and close out all the trades when the combined profit of the open initial and topups trades reaches 7 pips.

- **How-to:** Here is an example EA configuration how to achieve the above:
  - RSI OverBought/Sold Levels = OBought 75, OSold 25
  - 2. Price Gap = 30
  - Initial: Take Profit = 30 3.
  - 4. Initial: Hidden TP = 25
  - 5. Trailing Start at Profit = 12
  - Trailing SL = 10 6.
  - Trailing Stepping = 1 7.
  - Pair: Target Closure \$ Amount = 0
  - Pair: Target Profit Pips Closure = 7
  - 10. Pairs to Trade = EURUSD GBPUSD AUDUSD USDCAD USDCHF
  - 11. Maximum Traded Pairs = 2
- Description: The EA monitors all the EURUSD, GBPUSD, AUDUSD, USDCAD and USDCHF markets. When the RSI indicator forms a hook in the oversold (0-25) or overbought (75-100) area on a market then the EA enters an initial trade provided that no other market or only 1 of the other markets is being currently traded. The initial trade is entered as a buy in the oversold and a sell in the overbought RSI area. The EA sets the 30 pips TP for the new initial trade. This TP is sent to the broker server therefore the broker can see it & close the trade when the market price hits the 30 pips TP. The EA also monitors the market price and closes off the initial trade when the price hits the 25 pips hidden TP. Furthermore, the EA starts adjusting the SL of the initial trade when the trade gets into 12 pips profit. At the start, the EA sets the SL to 10 pips behind the market price high for a buy (or low for a sell), then keeps updating the SL every time the price makes another high (or low) by 1 pip or more. During trailing, the EA keeps the SL of the initial trade 10 pips behind the recent market price high (or low). On the other hand, should the initial trade go into 30 pips loss the EA enters the first topup. Every time the last topup goes into 30 pips loss the EA again enters a subsequent topup. The basket of the initial and the topup trades on that market gets closed off when their combined profit becomes 7 pips or more.

# **Example - Trade Max 1 Pair Involving the Same Currency**

#### **Example - Trade Max 1 Pair Involving the Same Currency**

- Goal: I want to monitor the EURUSD, GBPUSD, EURJPY, GBPJPY, CADCHF and USDCHF markets but trade the same currency (e.g. the EUR, the GBP, the CAD or the CHF currency) only once across these pairs at the same time.
- **How-to:** Here is an example EA configuration how to achieve the above:
  - 1. Pairs to Trade = EURUSD GBPUSD EURJPY GBPJPY CADCHF USDCHF
  - 2. Maximum Currency Exposure = 1
- Description: The EA monitors all the EURUSD, GBPUSD, EURJPY, GBPJPY, CADCHF and USDCHF markets. The EA may enter and keep open trades as per the following pattern:

When Trade Entered on this Pair	Which Involves These Currencies	Then These Pairs are NOT Allowed for Trading	These Pairs ARE Allowed for Trading
EURUSD	EUR	EURJPY	GBPJPY CADCHF
	USD	GBPUSD USDCHF	
GBPUSD	GBP	GBPJPY	EURJPY CADCHF
	USD	EURUSD USDCHF	
EURJPY	EUR	EURUSD	GBPUSD
	JPY	GBPJPY	CADCHF USDCHF
GBPJPY	GBP	GBPUSD	EURUSD
	JPY	EURJPY	CADCHF USDCHF

When Trade Entered on this Pair	Which Involves These Currencies	Then These Pairs are NOT Allowed for Trading	These Pairs ARE Allowed for Trading
CADCHF	CAD CHF	- USDCHF	EURUSD GBPUSD EURJPY GBPJPY
USDCHF	USD CHF	EURUSD GBPUSD CADCHF	EURJPY GBPJPY

In short, the EA trades the pairs in such a way that each currency gets exposed not more than once across the open trades.

#### **Example - Stop Trading of Certain Pairs**

#### **Example - Stop Trading of Certain Pairs**

- Goal: I want to stop trading some of the JPY crosses even though I already have open trades on those JPY crosses. Currently my trading pairs list consists of the USDCHF GBPUSD AUDJPY EURUSD AUDUSD USDCAD NZDUSD EURAUD NZDJPY GBPJPY EURGBP EURJPY USDJPY markets but I only want to keep the USDJPY for trading and I want to get out on all other JPY crosses.
- How-to: Here is an example EA configuration how to achieve the above:
  - 1. Pairs to Trade = USDCHF GBPUSD EURUSD AUDUSD USDCAD NZDUSD EURAUD **EURGBP USDJPY**
  - 2. Pairs to Get Out = AUDJPY NZDJPY GBPJPY EURJPY
- Description: The EA manages existing trades, may enter new topup trades and close the open trades on the pairs USDCHF GBPUSD EURUSD AUDUSD USDCAD NZDUSD EURAUD EURGBP USDJPY as well as on the pairs AUDJPY NZDJPY GBPJPY EURJPY, observing the usual gap scaling, lots scaling, pair and portfolio targets (pips or amount), maximum traded pairs and currency exposure etc settings across all of these two lists of pairs. However, the EA will not enter new initial trade on the AUDJPY NZDJPY GBPJPY EURJPY pairs, the EA only enters initial trade on the USDCHF GBPUSD EURUSD AUDUSD USDCAD NZDUSD EURAUD EURGBP USDJPY pairs. Also, the EA automatically turns off hedged trading and allowing for only one direction trading for the AUDJPY NZDJPY GBPJPY EURJPY pairs, therefore the drawdown could be higher for some of those pairs.

#### **Example - Scale Price Gap Up by Rate**

#### **Example - Scale Price Gap Up by Rate**

- Goal: I want to start with 10 pips gap size and I want the EA to start scaling up the gap size when the price moves against the first trade by 2 or more price levels. In that case I want to make the gap sizes bigger by 50%, compounding for each subsequent level.
- **How-to:** Here is an example EA configuration how to achieve the above:
  - **1.** Price Gap = 10
  - 2. Gap Scaling Start Level = 2
  - **3.** Gap Scaling Rate = 150

Below shows the price gaps in pips to be used for the trade entries:

Price Level	Effective Gaps after BUY Initial Trade	Effective Gaps after SELL Initial Trade
Up 6	-	75.9
Up 5	-	50.6
Up 4	-	33.8

Price Level	Effective Gaps after BUY Initial Trade	Effective Gaps after SELL Initial Trade
Up 3	-	22.5
Up 2	-	15
Up 1	Exit at Closure Target	10
Initial Entry	10	10
Down 1	10	Exit at Closure Target
Down 2	15	-
Down 3	22.5	-
Down 4	33.8	-
Down 5	50.6	-
Down 6	75.9	-

# **Example - Scale Price Gap Down by Rate**

#### **Example - Scale Price Gap Down by Rate**

- Goal: I want to start with 10 pips gap size and I want the EA to start scaling down the price gap size when the price moves against the first trade by 2 or more price levels. In that case I want to make the gap sizes reduced to 80% of the gap (i.e. smaller by 20%), compounding for each subsequent level, however I do not want the gap size to become less than 5 pips.
- How-to: Here is an example EA configuration how to achieve the above:
  - **1.** Price Gap = 10
  - 2. Gap Scaling Start Level = 2
  - 3. Gap Scaling Rate = 80
  - 4. Minimum Gap Size = 5

Below shows the price gaps in pips to be used for the trade entries:

Price Level	Effective Gaps after BUY Initial Trade	Effective Gaps after SELL Initial Trade
Up 6	-	5
Up 5	-	5
Up 4	-	5.1
Up 3	-	6.4
Up 2	-	8
Up 1	Exit at Closure Target	10
Initial Entry	10	10
Down 1	10	Exit at Closure Target
Down 2	8	-
Down 3	6.4	-
Down 4	5.1	-
Down 5	5	-
Down 6	5	-

#### **Example - Same Initial Lots All the Time**

#### **Example - Same Initial Lots All the Time**

- Goal: I want the initial trades to use the same 0.01 lots all the time.
- **How-to:** Here is an example EA configuration how to achieve the above:
  - 1. Lots for Initial Trade Entry = 0.01
  - 2. Initial Lots Adjustment: Base Account Equity Amount = 0
- **Description:** The EA enters the initial trades with the 0.01 lots, regardless of the equity of the broker account.

#### **Example - Initial Lots Adjustment Upward Only**

# **Example - Initial Lots Adjustment Upward Only**

- Goal: My broker account equity currently is 10000 and I want to start trading with 0.01 lots for the initial trades. Then, every time when my account equity grows by 50% I want to scale up the initial trades' lots by 30%.
- **How-to:** Here is an example EA configuration how to achieve the above:
  - 1. Lots for Initial Trade Entry = 0.01
  - 2. Initial Lots Adjustment: Base Account Equity Amount = 10000
  - 3. Initial Lots Adjustment: Required Equity Change = 50
  - 4. Initial Lots Adjustment: Initial Lots Adjustment = 30
- **Description:** The below table shows the lots to be used for the initial trade entries:

P&L Progression	Base Equity	Current Equity	Lots for Initial Trade
	10 000	lower	always 0.01
3rd Losses of 50%	10 000	1 250	0.01
2nd Losses of 50%	10 000	2 500	0.01
1st Losses of 50%	10 000	5 000	0.01
Start of Trading	10 000	10 000	0.01
1st Profits of 50%	10 000	15 000	0.01
2nd Profits of 50%	10 000	22 500	0.02
3rd Profits of 50%	10 000	33 750	0.02
4th Profits of 50%	10 000	50 625	0.03
5th Profits of 50%	10 000	75 937	0.04
	10 000	higher	compounding 30%

This example assumes that the broker minimum lots requirement is 0.01 for the market. As a result the initial lots size is only ever adjusted upwards.

#### **Example - Initial Lots Adjustment Up & Down**

#### **Example - Initial Lots Adjustment Up & Down**

Goal: My broker account equity currently is 10000 and I want to start trading with 0.10 lots for the initial trades. Then, every time when my account equity grows or shrinks by 50% I want to scale up or down the initial trades' lots by 30%, correspondingly.

- How-to: Here is an example EA configuration how to achieve the above:
  - **1.** Lots for Initial Trade Entry = 0.10
  - 2. Initial Lots Adjustment: Base Account Equity Amount = 10000
  - 3. Initial Lots Adjustment: Required Equity Change = 50
  - **4.** Initial Lots Adjustment: Initial Lots Adjustment = 30
- **Description:** The below table shows the lots to be used for the initial trade entries:

P&L Progression	Base Equity	Current Equity	Lots for Initial Trade
	10 000	lower	drops to 0.01
3rd Losses of 50%	10 000	1 250	0.03
2nd Losses of 50%	10 000	2 500	0.05
1st Losses of 50%	10 000	5 000	0.07
Start of Trading	10 000	10 000	0.10
1st Profits of 50%	10 000	15 000	0.13
2nd Profits of 50%	10 000	22 500	0.17
3rd Profits of 50%	10 000	33 750	0.22
4th Profits of 50%	10 000	50 625	0.29
5th Profits of 50%	10 000	75 937	0.37
	10 000	higher	compounding 30%

### **Example - Same Position Size All the Time**

#### **Example - Same Position Size All the Time**

- Goal: I want all the trades to use the same 0.01 lots all the time.
- **How-to:** Here is an example EA configuration how to achieve the above:
  - **1.** Lots for Initial Trade Entry = 0.01
  - 2. Topup Lots Multiplier = 1.0
  - 3. Topup Lots Change by Lots = 0.0
- **Description:** The below table shows the lots to be used for the trade entries:

Price Level	Effective Lots after BUY Initial Trade	Effective Lots after SELL Initial Trade
Up	-	always 0.01
Up 6	-	0.01
Up 5	-	0.01
Up 4	-	0.01
Up 3	-	0.01
Up 2	-	0.01
Up 1	Exit at Initial's Target	0.01
Initial Entry	0.01	0.01
Down 1	0.01	Exit at Initial's Target
Down 2	0.01	-
Down 3	0.01	-

Price Level	Effective Lots after BUY Initial Trade	Effective Lots after SELL Initial Trade
Down 4	0.01	-
Down 5	0.01	-
Down 6	0.01	-
Down	always 0.01	-

# **Example - Scale Lots Up by Multiplier**

# **Example - Scale Lots Up by Multiplier**

- Goal: I want to start with 0.01 lots and scale up by 50% for each topup.
- **How-to:** Here is an example EA configuration how to achieve the above:
  - 1. Lots for Initial Trade Entry = 0.01
  - 2. Topup Lots Multiplier = 1.5
  - **3.** Topup Lots Change by Lots = 0.0
- **Description:** The below table shows the lots to be used for the trade entries:

Price Level	Effective Lots after BUY Initial Trade	Effective Lots after SELL Initial Trade
Up	-	growing
Up 7	-	0.17
Up 6	-	0.11
Up 5	-	0.08
Up 4	-	0.05
Up 3	-	0.03
Up 2	-	0.02
Up 1	Exit at Initial's Target	0.02
Initial Entry	0.01	0.01
Down 1	0.02	Exit at Initial's Target
Down 2	0.02	-
Down 3	0.03	-
Down 4	0.05	-
Down 5	0.08	-
Down 6	0.11	-
Down 7	0.17	-
Down	growing	-

# **Example - Scale Lots Down by Multiplier**

### **Example - Scale Lots Down by Multiplier**

• Goal: I want to start with 0.10 lots and scale down to 70% for each topup.

- How-to: Here is an example EA configuration how to achieve the above:
  - **1.** Lots for Initial Trade Entry = 0.10
  - 2. Topup Lots Multiplier = 0.7
  - **3.** Topup Lots Change by Lots = 0.0

This example assumes that the broker minimum lots requirement is 0.01 for the market.

• **Description:** The below table shows the lots to be used for the trade entries:

Price Level	Effective Lots after BUY Initial Trade	Effective Lots after SELL Initial Trade
Up	-	stays 0.01
Up 7	-	0.01
Up 6	-	0.01
Up 5	-	0.02
Up 4	-	0.02
Up 3	-	0.03
Up 2	-	0.05
Up 1	Exit at Initial's Target	0.07
Initial Entry	0.10	0.10
Down 1	0.07	Exit at Initial's Target
Down 2	0.05	-
Down 3	0.03	-
Down 4	0.02	-
Down 5	0.02	-
Down 6	0.01	-
Down 7	0.01	-
Down	stays 0.01	-

# **Example - Scale Lots Up by Amount**

#### **Example - Scale Lots Up by Amount**

- Goal: I want to start with 0.01 lots and scale up by 0.01 lots for each topup.
- **How-to:** Here is an example EA configuration how to achieve the above:
  - **1.** Lots for Initial Trade Entry = 0.01
  - 2. Topup Lots Multiplier = 0
  - 3. Topup Lots Change by Lots = 0.01
- **Description:** The below table shows the lots to be used for the trade entries:

Price Level	Effective Lots after BUY Initial Trade	Effective Lots after SELL Initial Trade
Up	-	growing
Up 7	-	0.08
Up 6	-	0.07
Up 5	-	0.06
Up 4	-	0.05

Price Level	Effective Lots after BUY Initial Trade	Effective Lots after SELL Initial Trade
Up 3	-	0.04
Up 2	-	0.03
Up 1	Exit at Initial's Target	0.02
Initial Entry	0.01	0.01
Down 1	0.02	Exit at Initial's Target
Down 2	0.03	-
Down 3	0.04	-
Down 4	0.05	-
Down 5	0.06	-
Down 6	0.07	-
Down 7	0.08	-
Down	growing	-

# **Example - Scale Lots Down by Amount**

### **Example - Scale Lots Down by Amount**

- Goal: I want to start with 0.10 lots and scale down by 0.02 for each topup.
- How-to: Here is an example EA configuration how to achieve the above:
  - 1. Lots for Initial Trade Entry = 0.10
  - 2. Topup Lots Multiplier = 0.0
  - **3.** Topup Lots Change by Lots = -0.02

This example assumes that the broker minimum lots requirement is 0.01 for the market.

**Description:** The below table shows the lots to be used for the trade entries:

Price Level	Effective Lots after BUY Initial Trade	Effective Lots after SELL Initial Trade
Up	-	stays 0.01
Up 7	-	0.01
Up 6	-	0.01
Up 5	-	0.01
Up 4	-	0.02
Up 3	-	0.04
Up 2	-	0.06
Up 1	Exit at Initial's Target	0.08
Initial Entry	0.10	0.10
Down 1	0.08	Exit at Initial's Target
Down 2	0.06	-
Down 3	0.04	-
Down 4	0.02	-
Down 5	0.01	-

Price Level	Effective Lots after BUY Initial Trade	Effective Lots after SELL Initial Trade
Down 6	0.01	-
Down 7	0.01	-
Down	stays 0.01	-

### **Example - Skip Topup and Scale Up by Multiplier**

#### **Example - Skip Topup and Scale Up by Multiplier**

- Goal: I want to start with 0.01 lots and scale up by 50% for each topup but skip the first topup
- **How-to:** Here is an example EA configuration how to achieve the above:
  - 1. Lots for Initial Trade Entry = 0.01
  - 2. Topup Lots Multiplier = 1.5
  - 3. Topup Lots Change by Lots = 0.0
  - 4. Topup Trades to Skip = 1
- **Description:** The below table shows the lots to be used for the trade entries:

Price Level	Effective Lots after BUY Initial Trade	Effective Lots after SELL Initial Trade
Up	-	growing
Up 7	-	0.17
Up 6	-	0.11
Up 5	-	0.08
Up 4	-	0.05
Up 3	-	0.03
Up 2	-	0.02
Up 1	Exit at Initial's Target	Trade Not Entered [0.02]
Initial Entry	0.01	0.01
Down 1	Trade Not Entered [0.02]	Exit at Initial's Target
Down 2	0.02	-
Down 3	0.03	-
Down 4	0.05	-
Down 5	0.08	-
Down 6	0.11	-
Down 7	0.17	-
Down	growing	-

# **Example - Skip Topups and Scale Down by Multiplier**

#### **Example - Skip Topups and Scale Down by Multiplier**

Goal: I want to start with 0.10 lots and scale down to 70% for each topup but skip the first two topup trades.

- **How-to:** Here is an example EA configuration how to achieve the above:
  - 1. Lots for Initial Trade Entry = 0.10
  - 2. Topup Lots Multiplier = 0.7
  - **3.** Topup Lots Change by Lots = 0.0
  - **4.** Topup Trades to Skip = 2

This example assumes that the broker minimum lots requirement is 0.01 for the market.

• **Description:** The below table shows the lots to be used for the trade entries:

Price Level	Effective Lots after BUY Initial Trade	Effective Lots after SELL Initial Trade
Up	-	stays 0.01
Up 7	-	0.01
Up 6	-	0.01
Up 5	-	0.02
Up 4	-	0.02
Up 3	-	0.03
Up 2	-	Trade Not Entered [0.05]
Up 1	Exit at Initial's Target	Trade Not Entered [0.07]
Initial Entry	0.10	0.10
Down 1	Trade Not Entered [0.07]	Exit at Initial's Target
Down 2	Trade Not Entered [0.05]	-
Down 3	0.03	-
Down 4	0.02	-
Down 5	0.02	-
Down 6	0.01	-
Down 7	0.01	-
Down	stays 0.01	-

### **Example - Skip Topup and Scale Up by Amount**

#### **Example - Skip Topup and Scale Up by Amount**

- Goal: I want to start with 0.01 lots and scale up by 0.01 lots for each topup but skip the first topup
- How-to: Here is an example EA configuration how to achieve the above:
  - 1. Lots for Initial Trade Entry = 0.01
  - 2. Topup Lots Multiplier = 0
  - **3.** Topup Lots Change by Lots = 0.01
  - 4. Topup Trades to Skip = 1
- **Description:** The below table shows the lots to be used for the trade entries:

Price Level	Effective Lots after BUY Initial Trade	Effective Lots after SELL Initial Trade
Up	-	growing
Up 7	-	0.08
Up 6	-	0.07

Price Level	Effective Lots after BUY Initial Trade	Effective Lots after SELL Initial Trade
Up 5	-	0.06
Up 4	-	0.05
Up 3	-	0.04
Up 2	-	0.03
Up 1	Exit at Initial's Target	Trade Not Entered [0.02]
Initial Entry	0.01	0.01
Down 1	Trade Not Entered [0.02]	Exit at Initial's Target
Down 2	0.03	-
Down 3	0.04	-
Down 4	0.05	-
Down 5	0.06	-
Down 6	0.07	-
Down 7	0.08	-
Down	growing	-

### **Example - Skip Topups and Scale Down by Amount**

# **Example - Skip Topups and Scale Down by Amount**

- Goal: I want to start with 0.10 lots and scale down by 0.02 lots for each topup but skip the first two topup trades.
- How-to: Here is an example EA configuration how to achieve the above:
  - 1. Lots for Initial Trade Entry = 0.10
  - 2. Topup Lots Multiplier = 0.0
  - 3. Topup Lots Change by Lots = -0.02
  - **4.** Topup Trades to Skip = 2

This example assumes that the broker minimum lots requirement is 0.01 for the market.

**Description:** The below table shows the lots to be used for the trade entries:

Price Level	Effective Lots after BUY Initial Trade	Effective Lots after SELL Initial Trade	
Up	-	stays 0.01	
Up 7	-	0.01	
Up 6	-	0.01	
Up 5	-	0.01	
Up 4	-	0.02	
Up 3	-	0.04	
Up 2	-	Trade Not Entered [0.06]	
Up 1	Exit at Initial's Target	Trade Not Entered [0.08]	
Initial Entry	0.10	0.10	
Down 1	Trade Not Entered [0.08]	Exit at Initial's Target	

Price Level	Effective Lots after BUY Initial Trade	Effective Lots after SELL Initial Trade	
Down 2	Trade Not Entered [0.06]	-	
Down 3	0.04	-	
Down 4	0.02	-	
Down 5	0.01	-	
Down 6	0.01	-	
Down 7	0.01	-	
Down	stays 0.01	-	

#### **Example - Closure at Profit Amount**

#### **Example - Closure at Profit Amount**

- Goal: I want to cash in profits on a market when \$3 profit is reached by the basket of the open initial and topup trades on that market.
- **How-to:** Here is an example EA configuration how to achieve the above:
  - 1. Pair: Target Closure \$ Amount = 3
  - 2. Pair: Target Profit Pips Closure = 0
- Description: The EA enters the initial trade and one or more topup trades on a market. When the combined profit of these open initial and topup trades becomes \$3 or more then the EA closes off all these initial and topup trades on that market. After the closure the EA monitors all the markets for a new initial entry as usual.

#### **Example - Closure at Pips Profit**

#### **Example - Closure at Pips Profit**

- Goal: I want to cash in profits on a market when 7 pips profit is reached by the basket of the open initial and topup trades on that market.
- How-to: Here is an example EA configuration how to achieve the above:
  - 1. Pair: Target Closure \$ Amount = 0
  - 2. Pair: Target Profit Pips Closure = 7
- Description: The EA enters the initial trade and one or more topup trades on a market. When the combined profit of these open initial and topup trades becomes 7 pips or more then the EA closes off all these initial and topup trades on that market. After the closure the EA monitors all the markets for a new initial entry as usual.

#### **Example - Closure at Portfolio Profit**

#### **Example - Closure at Portfolio Profit**

- Goal: I want to close all open trades across all the traded markets when \$1000 profit is reached by the basket of all the open initial and topup trades on all the markets combined. I want the EA to carry on with trading after the portfolio closure.
- **How-to:** Here is an example EA configuration how to achieve the above:
  - 1. Portfolio: Closure at Profit \$ Amount = 1000
  - 2. Portfolio: Reentry After Closure = Reentry Allowed
- Description: The EA enters initial and topup trades on multiple markets. When the combined profit & loss of all these open initial and topup trades becomes \$1000 or more profits then the EA closes off all those initial and topup trades on all the traded markets. After the closure the EA monitors all the markets for a new initial entry as usual.

#### **Example - Closure at Portfolio Loss**

#### **Example - Closure at Portfolio Loss**

- Goal: I want to close all open trades across all the traded markets when \$500 drawdown is reached by the basket of all the open initial and topup trades on all the markets combined. I want the EA to carry on with trading after the portfolio closure.
- **How-to:** Here is an example EA configuration how to achieve the above:
  - 1. Portfolio: Closure at Maximum Loss \$ Amount = 500
  - 2. Portfolio: Reentry After Closure = Reentry Allowed
- Description: The EA enters initial and topup trades on multiple markets. When the combined profit & loss of all these open initial and topup trades becomes \$500 or more losses then the EA closes off all those initial and topup trades on all the traded markets. After the closure the EA monitors all the markets for a new initial entry as usual.

#### **Example - Stop Trading After Portfolio Closure**

#### **Example - Stop Trading After Portfolio Closure**

- Goal: I want to close all open trades across all the traded markets when \$500 drawdown is reached by the basket of all the open initial and topup trades on all the markets combined. I want the EA to stop further trading after the closure of the portfolio.
- **How-to:** Here is an example EA configuration how to achieve the above:
  - 1. Portfolio: Closure at Maximum Loss \$ Amount = 500
  - 2. Portfolio: Reentry After Closure = Reentry Disabled
- Description: The EA enters initial and topup trades on multiple markets. When the combined profit & loss of all these open initial and topup trades becomes \$500 or more losses then the EA closes off all those initial and topup trades on all the traded markets. After the closure the EA stops further trading and displays a popup window with the details of the portfolio closure. This popup window must be dismissed to allow the EA to trade again.

#### **Example - Balanced Amount Pruning**

#### **Example - Balanced Amount Pruning**

- Goal: I want to close a pair of open trades with combined small amount of profit or loss when there are 5 or more open buy or sell trades on a pair. I do not want to use gap scaling.
- **How-to:** Here is an example EA configuration how to achieve the above:
  - 1. Start Pruning at Trade Count in a Pair Direction = 5
  - 2. Trade Pair Pruning Approach = Balanced Amount Pruning
  - 3. Gap Scaling Start Level = 0
- **Description:** When any pair listed for the Pairs to Trade or Pairs to Get Out has 5 or more open buy (or sell) trades and the last topup trade retraced to the previous level then the EA looks for a pair of buy (or sell) trades on that pair where that pair of trades could be closed out with a small profit or loss amount. If such a pair of trades was found then those two buy (or sell) trades get closed out.

#### **Example - First & Last Trades Pruning**

#### **Example - First & Last Trades Pruning**

Goal: I want to close the oldest and newest open trades when there are 6 or more open buy or sell trades on a pair. I do not want to use gap scaling.

- **How-to:** Here is an example EA configuration how to achieve the above:
  - 1. Start Pruning at Trade Count in a Pair Direction = 6
  - 2. Trade Pair Pruning Approach = First & Last Trades Pruning
  - 3. Gap Scaling Start Level = 0
- **Description:** When any pair listed for the Pairs to Trade or Pairs to Get Out has 6 or more open buy (or sell) trades and the last topup trade retraced to the previous level then the EA closes off the first and the last (i.e. the oldest and the newest) buy (or sell) trades on that pair.

#### **Example - Gap Pruning**

#### **Example - Gap Pruning**

- Goal: I want to do pruning when there are 5 or more open trades. I want to close the last topup trade when the scaled gap size is at least 4 times the size of the initial gap size. Otherwise I want to close a pair of open buy (or sell) trades with combined small amount of profit or loss. I want to scale up the gap by 20% from level 1.
- **How-to:** Here is an example EA configuration how to achieve the above:
  - 1. Gap Scaling Start Level = 1
  - 2. Gap Scaling Rate = 120
  - 3. Start Pruning at Trade Count in a Pair Direction = 5
  - 4. Trade Pair Pruning Approach = Balanced Amount Pruning
  - 5. Gap Pruning From This Scale of Initial Gap = 400
- Description: When any pair listed for the Pairs to Trade or Pairs to Get Out has 5 or more open buy (or sell) trades then the EA checks the last scaled gap size. If that is 4 times or more larger than the initial gap size and the last buy (or sell) topup trade retraced half way to the previous level then the EA closes off that last buy (or sell) topup trade. If the last scaled gap size is less than 4 times of the initial gap size and the last topup trade retraced to the previous level then the EA looks for and closes off a pair of buy (or sell) trades on that pair with a small profit or loss amount.

### **Example - FIFO Trading**

#### **Example - FIFO Trading**

- Goal: My broker mandates FIFO trading therefore I want the EA to enter and exit trades according to the FIFO rules. I want to use 25 pips for Take Profit for the initial trade.
- How-to: Here is an example EA configuration how to achieve the above:
  - 1. Initial: Take Profit = 0
  - 2. Initial: Hidden TP = 25
  - 3. Trailing Start at Profit = 0
  - 4. Allow Buy & Sell the Same Pair at the Same Time = Only One Direction Allowed on Same
  - **5.** Topup TP Mode = Hide Topup TP from Broker
  - **6.** Start Pruning at Trade Count in a Pair Direction = 0
- **Description:** Upon a new trade trigger on a not yet traded market the EA enters the initial trade. The EA does not set the 25 pips TP for the open initial trade on the broker server as that could violate the FIFO rules later on. The EA monitors the market price and closes off the initial trade when the price hits the 25 pips hidden TP. Should the market price move against the initial trade the EA enters 1 or more topups. The EA does not set the TP for the group of open trades as that could violate the FIFO rules. Instead, the EA monitors the market price and closes off all the open trades on that market in FIFO manner when the TP is reached.

Note: Do not trade the broker account manually and/or by other EAs along with the RSI ForexLiberator EA. Trading the same markets by multiple parties can result in demand to close a specific open trade first which is outside the control of the RSI ForexLiberator EA, i.e. blocking the trade executions and potentially causing losses.

# Chapter

# Knowledgebase

Frequently Asked Questions and other common use cases.

# 5.1 How to Download MT5

#### Question

How can I install the MT5 platform?

#### **Answer**

Please download the MT5 setup application directly from one of your preferred brokers web site, or from MetaQuotes website.


# 5.2 How to Download the Setup Application

#### Question

How to download the RSI ForexLiberator EA Setup application?

- 1. Visit the RSI ForexLiberator EA Web Support Centre page.
- 2. Read the Web Support Centre Terms and Conditions and Privacy Policy then tick the checkbox to accept them.





3. Click on the **Download EA Setup** button to download the EA setup for the MT5 terminal.


# 5.3 How to Install the RSI ForexLiberator EA

The RSI ForexLiberator EA comes with a setup application to provide a wizard based installation process to the selected MT5 terminal.

#### Before you start...

- Ensure that you have the login credentials to the Web Support Centre.
- Ensure that you have an MT5 terminal version 5.00 build 4260 or later installed.
- 1. Exit the MT5 if it was running.
- 2. Download the latest version of the RSI ForexLiberator EA for MT5 from the Web Support Centre page.
- 3. Run the downloaded setup application. Select the MT5 instance through the setup wizard pages to where you want the EA to be installed.
- 4. When the setup completes start the MT5 up. The RSI ForexLiberator EA entry should appear under the Expert Advisors node in the Navigator window (View > Navigator)

These pictures highlight the steps how to install the EA.




The setup application lists the available MT5 instances. Select one or multiple of them for installation target and click on the **Next**.


#### Note:

If you see an empty list then you probably need to install an MT5 first. In that case download and run the MT5 setup application from your preferred broker's web site. After that run again this EA setup application.

If you are an advanced user and you run the MT5 in portable mode from a custom location then copy this EA setup application into the Data Folder of the MT5, then run the EA setup application from that Data Folder. In order to find the Data Folder of the MT5 select the File > Open Data Folder in the MT5's menu.



When the installation is complete start the MT5 up and check that the EA appears in the **Navigator** window (**View** > **Navigator**):



Now everything is set up for the first activation of the RSI ForexLiberator Expert Advisor.

# 5.4 How to Upgrade the EA

#### Question

How to upgrade the RSI ForexLiberator EA?

#### **Answer**

In order to upgrade the EA please follow these steps:

1. Download the latest RSI ForexLiberator EA from the Web Support Centre. For detailed steps refer to the How to Download the Setup Application.

- 2. Exit the MT5 terminal if it was running.
- **3.** Execute the downloaded RSI ForexLiberator EA setup application. Follow through all of the wizard pages to complete the EA installation.
- **4.** Start up the MT5 terminal.

The upgraded RSI ForexLiberator EA will pick up and carry on managing any existing trades created by the previous EA version.

#### Related tasks

Step-by-step Installation of Expert4x EAs and Indicators on page 82 How to download an EA setup in VPS environment on page 87

#### **Related information**

How to Download the Setup Application on page 58


# 5.5 How to Attach the RSI ForexLiberator Expert Advisor to a Chart

Step by step guide to get the EA up and running on a chart for the first time.


The following pictures demonstrate the first time activation of the RSI ForexLiberator Expert Advisor in a few steps.

#### Attach the EA to a chart

 Drag & drop the RSI ForexLiberator Expert Advisor from the Navigator window (View > Navigator) to a chart window. In the appearing properties window select the Dependencies tab and tick the checkbox Allow DLL imports:



#### 2. Go to the Common tab and tick the checkbox Allow Algo Trading:




#### Note:

#### Ensure that the

- · Allow DLL imports and
- Allow Algo Trading

are **ticked** otherwise the RSI ForexLiberator EA is not able to start up.

#### 3. Select the Inputs tab:




This lists the parameters of the EA where the operational aspect of the RSI ForexLiberator EA can be set up. For more details see the RSI ForexLiberator EA Configuration Guide – for now click on the **OK** button and let the EA start up with default settings.

#### Note:


At the very first time the EA may prompt for the Access ID to verify that the usage of product is licensed.

The Access ID is pre-configured and is the same as the login name to the web support site. Feel free to change your Access ID at the Web Support Centre and ensure not to share it with anyone else. Enter the Access ID and click on the **Save** button:




### The RSI ForexLiberator EA is up and running

After successful authentication the RSI ForexLiberator EA starts up.



The RSI ForexLiberator Expert Advisor has been attached to the chart. The smiley face in the top-right corner shows that the initialisation of the RSI ForexLiberator Expert Advisor was successful and the EA is now looking for trading opportunities.

See the smiley face in the corner:



In case of a problem getting the EA up and running please refer to the Knowledgebase section.


# 5.6 RSI ForexLiberator Expert Advisor First Time Activation

Step by step guide to get the EA up and running on a chart for the first time.


The following pictures demonstrate the first time activation of the RSI ForexLiberator Expert Advisor in a few steps.

#### Attach the EA to a chart

 Drag & drop the RSI ForexLiberator Expert Advisor from the Navigator window (View > Navigator) to a chart window. In the appearing properties window select the Dependencies tab and tick the checkbox Allow DLL imports:



#### 2. Go to the Common tab and tick the checkbox Allow Algo Trading:




#### Note:

#### Ensure that the

- Allow DLL imports and
- Allow Algo Trading

are **ticked** otherwise the RSI ForexLiberator EA is not able to start up.

#### 3. Select the Inputs tab:




This lists the parameters of the EA where the operational aspect of the RSI ForexLiberator EA can be set up. For more details see the RSI ForexLiberator EA Configuration Guide – for now click on the **OK** button and let the EA start up with default settings.

#### Note:


At the very first time the EA may prompt for the Access ID to verify that the usage of product is licensed.

The Access ID is pre-configured and is the same as the login name to the web support site. Feel free to change your Access ID at the Web Support Centre and ensure not to share it with anyone else. Enter the Access ID and click on the **Save** button:




#### The RSI ForexLiberator EA is up and running

After successful authentication the RSI ForexLiberator EA starts up.



The RSI ForexLiberator Expert Advisor has been attached to the chart. The smiley face in the top-right corner shows that the initialisation of the RSI ForexLiberator Expert Advisor was successful and the EA is now looking for trading opportunities.

See the smiley face in the corner:




In case of a problem getting the EA up and running please refer to the Knowledgebase section.

# 5.7 Sign Instead of Sign After Attach

#### Issue


After attaching to chart the EA is not managing trades, a sign appears in the top right corner of the chart.



#### EA's common and dependencies parameters might be not enabled

The Allow Automated Trading and Allow DLL imports might be not enabled

 Press F7 key and verify that the Allow Automated Trading and Allow DLL imports are checked in the EA property dialog.



### Algo Trading is disabled

The Algo Trading might be disabled

Toolbar button when Expert Advisors disabled:



# 5.8 What is the Leverage of My Account

#### Question

What is the leverage of my MT5 broker account?

I am logged in to my demo or live MT5 account and want to know the leverage available on the account.

#### **Answer**

The RSI ForexLiberator EA displays the MT5 account leverage on its dashboard, at the section **Account Level Info**.

See the reported leverage value at the end of the first line:



In the above picture the leverage is reported as 400, which represents 400:1 account leverage.

# 5.9 How to Figure Out My Broker's GMT Offset?

The MT5 platform presents its chart using the time of its broker server. The various brokers configure their server time according to their own choice, many of them are in one of the European timezone ranging from GMT+0 to GMT+3, but some brokers opt to have their server in the US Estern timezone, which is GMT-5. These GMT offsets may get further adjusted for the daylight savings from March till October of every year.

The RSI ForexLiberator EA uses the time for trading decisions therefore its time input parameters need to be adjusted by the GMT offset of the broker's server. This article describes how to figure out the GMT offset specific to the MT5 broker account.

 The Market Watch window's header shows the broker's server time, press Ctrl+M in the MT5 terminal:



This time can be compared to the GMT+0 time to calculate the GMT offset of the broker, as per the next step.

- 2. In a web browser search for *gmt time* keywords to see the current GMT time.
- **3.** Calculate now the broker GMT offset = 'Market Wacth time' 'GMT time'.

For an example, assuming the following:

- Market Watch time: 18:29
- GMT time as per the search result: 15:29

Then the calculated GMT offset is 18:29 - 15:29 = 3:00 hours. In practice - in the limited context of the forex broker servers - it is sufficient to calculate the difference between the hour parts: 18 - 15 = 3 hours.

**Note:** For broker servers located in Europe the GMT offset is likely to be in the range of 0 and 3, i.e. a zero or positive number. For broker servers located in the US the GMT offset might be in the range of -5 and -6, i.e. a negative number. Keep in mind that these figures may get further adjusted by the daylight savings.

Based on past experience, with no guarantee that the information is correct, these are a few sample broker GMT offsets observed as of July 2015:

MT5 Terminal	Broker	GMT Offset
AxiTrader	AxiCorp Financial Services Pty Ltd	+3
IC Markets	International Capital Markets Pty Ltd	+3
InstaForex	InstaForex Companies Group	+3
FXCM	Forex Capital Markets Inc	+3
ThinkForex	TF Global Markets (Aust) Pty Ltd	+3
RoboForex EU	RoboForex (CY) Ltd	+3
Tallinex	Tallinex Ltd	0
Oanda	OANDA Corporation	-4
MB Trading FX	MB Trading Futures Inc	-4

# 5.10 EA Is Not Starting Up After Attach to Chart

#### Issue

The EA reports successful initialisation and advises about disabled Expert Advisors.

## Algo Trading is disabled

The Algo Trading might be disabled

• Verify that the toolbar button Algo Trading is pressed.

Toolbar button when Expert Advisors disabled:



# 5.11 No Updates to Chart


#### Issue

The RSI ForexLiberator EA does not update information on the chart for several minutes.

#### **Connection Lost**

MetaTrader should be connected to the broker's server.

1. Check the bottom right corner of MetaTrader, this is when it has lost connection to the server:




2. If connection is lost then login again or restart MT to force reconnection. Try again activating the RSI ForexLiberator EA when connection is back.

## Demo account is expired

MT5 will not be able to connect to the demo account if it's expired. In this case MT5 will keep asking for the login details and fail all login attempt.

When this happens open a new demo account (right click Accounts in Navigator window and select Open an Account).



#### Market is closed

New tick information and updates to chart happens when markets are open.

Double check that markets are meant to be open currently.

#### Disk is full

There should be at least 50MB free disk space available on the drive MetaTrader is installed on.

If the free disk space is low then free up space.

# 5.12 Prompted for Access ID at Service Access Settings


#### Issue

After attaching to chart the RSI ForexLiberator EA asks for my Access ID in the Service Access Settings window.

## Type in your Access ID

The RSI ForexLiberator EA checks that the usage of product is appropriately licensed. After product purchase a user profile is created on our web support site and the product can be downloaded from that web site. The support site allows to set up an Access ID which is required by the RSI ForexLiberator EA to validate the product licence. By default this Access ID is configured to be the same as your selected login name to the web support site.

When prompted, please enter your Access ID to the window and click Save:



**Tip:** If you do not remember your Access ID then click on the **Help! What is my Access ID?** to see it on your Web Support Centre user profile.

Please do not share out to others your Access ID. That is against the licence agreement terms and conditions and also all 3rd party usages will count when checking the number of EA copies being used. Sharing out your Access ID can result in licence check failure and the EA may stop functioning.

Keep your Access ID secure, change it away from the its default value at any time on the Web Support Centre site.

# 5.13 How to Edit the EA Input Values

#### Question

How can I edit or change the settings of the RSI ForexLiberator EA once it is attached to a chart?

#### **Answer**

In order to edit the input parameters of an EA which is already attached to a chart follow these steps

- 1. Select the chart with the EA: click inside the chart area which hosts the RSI ForexLiberator EA in your MT5 application.
- 2. Press **F7** on your keyboard, or alternatively double click on the (or ) icon in the top-right corner of the chart.
- **3.** Edit the RSI ForexLiberator EA input values in the appearing EA properties window: double-click on the current value you want to change then type in the new value.
- 4. Click **OK** when editing is complete

# 5.14 Not Enough Memory For Bar History Or Indicator

#### Issue

Some of the market bar history data or an indicator fails to load because the MT5 runs out of memory. An error message similar to the below is reported:

ERROR 85130:RSI indicator failed to load or fit in memory.

At Broker Time:2018.03.02 21:59:50 Local Time:2018.03.04 11:58:50 Count:1


MT4:4075 not enough memory for indicator

Bid:1.904380 Spread:27.9 StopLevel:0.1 Tradeable:Yes

#### Solution

The bar history data takes up too much memory when loaded into RAM and the charts. The MT5 application needs to be configured to keep less number of bars on the charts.

- 1. In the MT5 application menu select **Tools** > **Options** then select the **Charts** tab.
- 2. Enter 65000 into the edit box Max bars in chart:



3. Attach the EA to the chart now. If the issue is still there then go back to the previous step and enter half of the previous values. Keep repeating these two steps - halving the values every time - until the EA attaches successfully.

## 5.15 No Trades Due to Trade Disabled

#### Issue

The got attached to a chart, the EA is up and running. It keeps submitting market orders to the broker server. However, the broker's server does not execute these market orders, instead, the broker says the trade on this broker account is disabled:



The broker server reports the error code 133, which means that the **trade is disabled** on the account. This is not an EA issue, instead, this is an issue with the broker account. For some reason the broker account does not allow you to trade that market.

#### Solution

Go through the following checklist to resolve this issue:


1. Restart the terminal to see if the restart and reconnect to the broker resolves this: In the menu select **File** > **Exit**, wait 5 seconds then start the up again.

- 2. Identify another symbol for the same market which is enabled for trading: In the menu select View > Symbols and search for symbol with different/extra suffix in the name, like EURUSDecn. Add that symbol to the Market Watch window then attach the EA to this new symbol.
- **3.** Logging into your broker account with the **investor login** credentials disables trading. Ensure that you log in to your broker account with the **full trader login** credentials.
- 4. Create another demo account with the broker.
- 5. Contact your broker and ask their support team to enable trading on the symbol or account
  - a. Your broker account may have reached some trade limits (e.g. overall maximum lots).
  - **b.** Your broker may have put (temporarily) trading limitations on your account for some reason.
  - c. Your broker may have to enable trading by EAs.

# 5.16 Backtest In Visual Mode Not Working

#### Issue


In the **Strategy Tester** using the visual mode **DLL imports not allowed** message appears on the chart. No result after the **Strategy Tester** finished its run.



## Global Allow DLL imports is not enabled

You may need to enable the DLL imports in the MT5 for terminal global parameters to run the RSI ForexLiberator EA in the backtest environment.

- 1. Open the MT5 global Options by selecting Tools > Option (CTRL+O)
- 2. Select the Expert Advisors tab
- 3. Check the Allow DLL import




4. Restart the MT5: exit the MT5 application, wait 5 seconds then start it up again.

# 5.17 Backtest Not Working

#### Issue


After the backtest finished no result showing.



## Global Allow DLL imports is not enabled

You may need to enable the DLL imports in the MT5 for terminal global parameters to run the RSI ForexLiberator EA in the backtest environment.

- 1. Open the MT5 global Options by selecting **Tools** > **Option** (CTRL+O)
- 2. Select the Expert Advisors tab
- 3. Check the Allow DLL import



4. Restart the MT5: exit the MT5 application, wait 5 seconds then start it up again.

# 5.18 Connection Down Message

#### Issue

The RSI ForexLiberator EA got attached to a chart and the EA is up and running. The EA monitors the connection between the MT5 terminal and the broker server. When the MT5 loses connection to the broker server then the EA presents this Connection Down message in its dashboard - see the orange message as an example:

In the above screenshot the last connection issue happened at 14:19 broker server time (chart time).

This means that somewhere along the Internet connection path from your computer to the broker server, including your home networks, the Internet and your brokers remote networks, there was some temporary issue resulting in data transfer interruption.

During this time the RSI ForexLiberator EA cannot receive price feed from the broker, i.e. no ticks are coming in. This also means that, due to the lack of price feed and ticks, the EA is not activated and cannot perform trading or managing open trades. When the MT5 re-establishes the connection to the broker server and price feed comes in again then the EA automatically resumes its trading operations.

#### **Solution**

In order to minimize the downtime, please ensure the following:

- 1. Your computer is connected to your home networks over a wire, i.e. cabled to your modem or router. Note that wireless connectivity is more prone to connection issues.
- 2. Use a cable based Internet service provider, if feasible. Wireless based Internet service providers, like mobile or cellular based Internet providers could have more connectivity issues.
- 3. Turn off the sleep or hibernation mode on your computer. When your computer goes into sleep or hibernation the Internet connection would be lost.
- **4.** If in doubt, restart your home networks: shutdown your computer, turn off your modem or router, wait 10 seconds then turn back on the modem/router then your computer.

# 5.19 Computer Always-on

#### Question


How to ensure that Windows does not go into sleep or hibernation mode?

## **How to Turn off Sleep & Hibernation**

Ensure that your computer is turned on throughout the FOREX market hours from Monday to Friday, and your computer is running the MT5 application and the EA is attached to a chart. Simply leave your computer and the MT5 up and running at all times. Please ensure that your Windows does not go into sleep or hibernation mode:

1. Go to Start > Windows Settings > Power & Sleep


#### 2. Select Never in the dropdown:



# 5.20 No Trades During Backtesting

#### Issue

After the backtest finished no trades are showing.



If you see no trades during backtesting then usually it is down to EA settings issue.

## Run a Backtest in Visual Mode

In order to see any settings issue with the the RSI ForexLiberator EA I would suggest to run a backtest in Visual mode. This would give a chance to see the EA dashboard and any error message in it.

Go to the MT5 Strategy Tester window and tick the Visual mode box:



Now run the backtesting in visual mode: click on the Start button. The Visual mode would make visible any potential EA messages in the backtesting chart, giving hints for next steps.

Watch out for any red messages in the chart area.


You may find these knowledge based topics useful to resolve them:

- Backtest In Visual Mode Not Working, and
- Backtest Not Working

# 5.21 Visual Mode Checkbox Missing in Strategy Tester

## Issue


Visual mode checkbox is missing in the Strategy Tester.




#### Solution

The Strategy Tester window hides some control elements when the window itself is not tall enough, i.e. the **Optimization** dropdown and the **visual mode** checkbox could become hidden.

Scroll down the Strategy Tester window to make visible the **Optimization** dropdown and the **visual mode** checkbox controls:






# 5.22 Step-by-step Installation of Expert4x EAs and Indicators

In this tutorial the name of *MetaTrader* is used as an example. Replace the *MetaTrader* with your broker specific MetaTrader name.


1. Start your MT5 terminal and select the File > Open Data Folder menu



The menu opens a File Explorer.


2. Close your MT5

• If the File Explorer shows a folder like this one below



and you see the origin.txt or the origin file go to the standard installation page.

· If the File Explorer shows a folder like this one below




and you see the terminal.exe or terminal file go to the non-standard installation page.

# 5.22.1 Standard EA, Indicator installation


In the opened File Explorer the origin.txt or the origin file was found.

Please follow through the steps below to install the Expert4x EA or Indicator on your MT5


**1.** Double click the **origin.txt** file and take a note of the MetaTrader location.



2. Start the EA or indicator setup program. Follow through the setup until you reach the **Select Target MetaTrader Directory** window.



- In this window select your targeted MetaTrader's Data Folder, as per the origin.txt noted earlier, and click Next
- 4. Follow through the rest of the setup application.
- 5. In the end click Install




- 6. Check the EA or Indicator in the MetaTrader after installation
  - a. Start your MetaTrader
  - **b.** In the **Navigator panel** open the Expert Advisors section if you installed an EA or the Indicators section if you installed an Indicator and look for the EA or Indicator.

## 5.22.2 Non-standard EA, Indicator installation


In the opened File Explorer the terminal.exe or terminal file was found.

Please follow through the steps below to install the EA or Indicator on your MT5


- 1. Right click on the name of the Setup application
- 2. Select **Run as administrator** (You may get a few security warning or you may need to type in the Windows administrator password)



- 3. Follow through the application until you reach the Select Target MetaTrader Directory window.
- 4. Click Add target directory... button




5. Navigate to your MetaTrader folder




#### and click OK.

6. Scroll down to the end of the list. Select the target directory. Click Next.



**7.** Follow through the rest of the setup application.

#### 8. In the end click Install




- 9. Check the EA or Indicator in the MetaTrader after installation
  - a. Start your MetaTrader
  - **b.** In the **Navigator panel** open the Expert Advisors section if you installed an EA or the Indicators section if you installed an Indicator and look for the EA or Indicator.


# 5.23 How to download an EA setup in VPS environment

In this topic we guide you through the EA setup application download in VPS environment.


1. Start the File Explorer: Click the File Explorer




## 2. The File Explorer started.




3. Select the address bar section



4. Type in: https://my.eafactory.com/expert4x and press Enter to start the Internet Explorer



Did you get blank screen? As you see below:




If yes, please select the address bar in the Internet Explorer and type in: https:// my.eafactory.com/UserInterface/index.zul?p=1



If you got this message below you may need to adjust temporary your Internet security settings.


Sorry, JavaScript must be enabled. Change your browser options, then try again.

5. When the Web support Site is appeared please log in



6. Select the EA name from the Product List and click Product Download in the Release List

If you got this message below you may need to adjust temporary your Internet security settings to enable downloads.



#### Warning messages related to the download

Do you want to save RSI ForexLiberator EA\_v3.0.0\_Setup.exe ...?



Click Save to resolve this warning

If you use Internet Explorer 9.0 you may get this message:


## RSI ForexLiberator EA\_v3.0.0\_Setup.exe is not commonly downloaded and could harm your computer

This message is a new features in Internet Explorer 9.0. IE 9.0 has increased user security.

"When you download a program from the Internet, SmartScreen Filter will check the program against a list of programs that are downloaded by a significant number of other Internet Explorer users and a list of programs that are known to be unsafe. If the program you're downloading isn't on either list, SmartScreen Filter will display a warning that the file Source: http://windows.microsoft.com/en-US/windows7/SmartScreen-Filter-frequently-asked-questions-IE9?SignedIn=1

These are the steps if you'd like to continue installing the RSI ForexLiberator EA EA:

- a. Click the Action button in the displayed message
- **b.** In the dialog box click the **down arrow** to the left of More options, and click **Run anyway**
- 7. After the successful download the Internet Explorer may show this message



To start the installation process after the download click Run

8. Clean up after the download in the Internet Explorer

# 5.23.1 How to enable JavaScript in your Internet Explorer

#### Issue


I tried to load the Web Support Centre in the **Internet Explorer** But the following error message popped up.



## JavaScripts are disabled in the Internet Explorer


To load the Web Support Centre you may need to enable the usage of JavaScript in the **Internet Explorer** 

- 1. In the Inter Explorer click **Tools** icon
- 2. Select Internet options




3. Go to the Security tab

#### 4. Select Custom level




- 5. Scroll down until you see Scripting
- 6. Under the Active scripting select Enable

#### 7. Click OK



8. Click OK



9. Refresh the https://my.eafactory.com/UserInterface/index.zul?p=1 page ang login

# 5.23.2 How to Enable Download in your Internet Explorer


## Issue

I tried to download the EA setup application in the **Internet Explorer** But the following error message popped up.

## File download is disabled in the Internet Explorer


To download a file you may need to enable the Download in the Internet Explorer

- 1. In the Inter Explorer click **Tools** icon
- 2. Select Internet options




3. Go to the Security tab

#### 4. Select Custom level



- 5. Scroll down until you see Downloads
- 6. Under the File download select Enable

#### 7. Click OK



8. Click OK




9. click the Product Download button again

# 5.23.3 Clean up after the download in the Internet Explorer


In this topic we guide you through how to clean up after download in VPS environment.

1. In the Inter Explorer click Tools icon


## 2. Select Internet options




## 3. Go to the Security tab



#### 4. Click the Default level



#### 5. Click OK



# 5.24 How to enable JavaScript in your Internet Explorer

#### Issue

I tried to load the Web Support Centre in the Internet Explorer But the following error message popped up.




## JavaScripts are disabled in the Internet Explorer


To load the Web Support Centre you may need to enable the usage of JavaScript in the **Internet Explorer** 

1. In the Inter Explorer click Tools icon

#### 2. Select Internet options




- 3. Go to the Security tab
- 4. Select Custom level




- 5. Scroll down until you see Scripting
- 6. Under the Active scripting select Enable

#### 7. Click OK



8. Click OK




9. Refresh the https://my.eafactory.com/UserInterface/index.zul?p=1 page ang login

# 5.25 How to Enable Download in your Internet Explorer

#### **Issue**


I tried to download the EA setup application in the **Internet Explorer** But the following error message popped up.



## File download is disabled in the Internet Explorer


To download a file you may need to enable the Download in the Internet Explorer

- 1. In the Inter Explorer click **Tools** icon
- 2. Select Internet options




3. Go to the Security tab

#### 4. Select Custom level




- 5. Scroll down until you see Downloads
- 6. Under the File download select Enable

#### 7. Click OK



8. Click OK



9. click the Product Download button again

# Chapter

# 6

# **Operational Messages**

The RSI ForexLiberator EA operational messages and resolution guide.

## **Expert Advisors Operational Messages**

Observe the message number displayed in **red** in the EA dashboard. Find that EA code in the table below and click on that number to see the details and possible resolutions:



EA Code	Severity	Message	Description
1001	Error	Setup problem: DLL imports not allowed. Tick Allow DLL imports in Common tab of the properties window.	Configuration setting is missing to allow the EA to use dynamicaly loaded libraries (DLLs). Enable the load of DLLs and restart the EA.  More
1002	Error	Incomplete EA installation: Run setup application for MT5 instance " <mt5datapath>'s Data Folder"</mt5datapath>	Product installation is not complete or damaged. Run the setup application for the MT5 terminal instance as displayed. More
1006	Error	MT5 Expert Advisors are disabled: click AutoTrading icon on MT5 toolbar to execute the EA.	EA does not perform its operations, not monitoring nor reacting to price movements of the market. More
1007	Error	Live trading is not allowed ( sign): press F7 and tick Allow live trading box on Common tab.	The EA is unable to perform trading operations, there is a sign in the top right corner of the chart. More
1008	Error	Authentication failed or interrupted ( <stopped>, <status>, <response>, <reason>, <flipovercount>, <latency>)</latency></flipovercount></reason></response></status></stopped>	The EA is not able to authenticate the user access to the service at its start up time. More
1121	Error	Order close failed at bid <bid> for #<ticketno> <tickettype> cmnt:<ticketcomment> (<attemptno>, <ticketcount>/ <totalticketcount>, <latency>ms)</latency></totalticketcount></ticketcount></attemptno></ticketcomment></tickettype></ticketno></bid>	Attempt to close an open trade returned with error. More
1163	Warning	Connection - Down X times Last time	The MT5 lost connection to the broker's server. More
2101	Error	Initialization failed	Initialization failed More
2118	Error	Service access disabled ( <accessid>, <confirmationid>) - shutting down</confirmationid></accessid>	The user quits the authentication process, or the EA is not able to authenticate the user access to the service. More

# **6.1 Operational Messages**

Expert Advisor Operational Messages.

## **Expert Advisors Operational Messages**

Observe the message number displayed in **red** in the EA dashboard. Find that EA code in the table below and click on that number to see the details and possible resolutions:



EA Code	Severity	Message	Description
1001	Error	Setup problem: DLL imports not allowed. Tick Allow DLL imports in Common tab of the properties window.	Configuration setting is missing to allow the EA to use dynamicaly loaded libraries (DLLs). Enable the load of DLLs and restart the EA.  More
1002	Error	Incomplete EA installation: Run setup application for MT5 instance " <mt5datapath>'s Data Folder"</mt5datapath>	Product installation is not complete or damaged. Run the setup application for the MT5 terminal instance as displayed. More
1006	Error	MT5 Expert Advisors are disabled: click AutoTrading icon on MT5 toolbar to execute the EA.	EA does not perform its operations, not monitoring nor reacting to price movements of the market. More
1007	Error	Live trading is not allowed ( sign): press F7 and tick Allow live trading box on Common tab.	The EA is unable to perform trading operations, there is a sign in the top right corner of the chart. More
1008	Error	Authentication failed or interrupted ( <stopped>, <status>, <response>, <reason>, <flipovercount>, <latency>)</latency></flipovercount></reason></response></status></stopped>	The EA is not able to authenticate the user access to the service at its start up time. More
1121	Error	Order close failed at bid <bid> for #<ticketno> <tickettype> cmnt:<ticketcomment> (<attemptno>, <ticketcount>/ <totalticketcount>, <latency>ms)</latency></totalticketcount></ticketcount></attemptno></ticketcomment></tickettype></ticketno></bid>	Attempt to close an open trade returned with error. More
1163	Warning	Connection - Down X times Last time	The MT5 lost connection to the broker's server. More
2101	Error	Initialization failed	Initialization failed More
2118	Error	Service access disabled ( <accessid>, <confirmationid>) - shutting down</confirmationid></accessid>	The user quits the authentication process, or the EA is not able to authenticate the user access to the service. More

# 6.1.1 Message 1001

Code	Severity	Message	Description
1001	Error	Setup problem: DLL imports not allowed. Tick Allow DLL imports in Common tab of the properties window.	Configuration setting is missing to allow the EA to use dynamicaly loaded libraries (DLLs). Enable the load of DLLs and restart the EA.  More

## Setup problem: DLL imports not allowed

#### Issue

The EA is not able to start up when gets attached to a chart because some of its dependencies could not be loaded into memory. The EA requires some dynamically loaded libraries (DLL) to be loaded into memory from disks. When the EA configuration settings do not allow the load of DLLs then the EA cannot start up and reports this error message.


## Possible root cause

The EA configuration does not allow for the load of DLLs.

#### Resolution

Enable the load of DLLs in the EA configuration dialog.

- 1. Attach the EA to a chart, or if already attached then select the chart and
  - In case of an EA: press F7
  - In case of an indicator: press Ctrl+l and double-click the name of the indicator in the list.
- 2. Go to the **Dependencies** tab of the **Property** window.
- 3. Tick the checkbox Allow DLL imports.
- 4. Click OK.



# 6.1.2 Message 1002

Code	Severity	Message	Description
1002	Error	Incomplete EA installation: Run setup application for MT5 instance " <mt5datapath>'s Data Folder"</mt5datapath>	Product installation is not complete or damaged. Run the setup application for the MT5 terminal instance as displayed. More

## **Incomplete Installation**

#### Issue

The EA is not able to start up when gets attached to a chart because some of its dependencies could not be found on the file system.

#### Possible root cause

- The EA setup application was not able to perform all its steps, not completed in full.
- The product was installed manually and some of the steps were missed.
- The MT5 instance's file system got damaged, some files got corrupted or deleted.

#### Resolution

Download the EA setup application and execute it to get the product installed for the MT5 instance:

- 1. Download the setup application from Web Support Centre.
- **2.** Execute the setup application to get the product installed. For installation guide refer to any of the following:
  - Getting Started with the RSI ForexLiberator EA
  - · Step-by-step Installation of EAs and Indicators

# 6.1.3 Message 1006

Code	Severity	Message	Description
1006	Error	MT5 Expert Advisors are disabled: click AutoTrading icon on MT5 toolbar to execute the EA.	EA does not perform its operations, not monitoring nor reacting to price movements of the market. More

## **EA AutoTrading Disabled**

#### Issue

The EA is not responding to price movements, not performing its logic upon data ticks coming in from the broker. The MT5 toolbar button **AutoTrading** is disabled.

#### Possible root cause

• The AutoTrading button on the MT5 toolbar is disabled.



#### Resolution

Press the AutoTrading button on the MT5 toolbar.



# 6.1.4 Message 1007

Code	Severity	Message	Description
1007	Error	Live trading is not allowed ( sign): press F7 and tick Allow live trading box on Common tab.	The EA is unable to perform trading operations, there is a sign in the top right corner of the chart. More

### **Live Trading Not Allowed**

#### Issue

The EA is unable to perform trading operations, there is a property sign in the top right corner of the chart.


#### Possible root cause

• The **Allow live trading** checkbox is not ticked at the EA properties window.

#### Resolution

Enable live trading in the EA properties window.

- 1. Go to the chart and press F7.
- 2. Go to the **Common** tab of the Expert properties window.
- 3. Tick the checkbox Allow live trading.
- 4. Click OK



## 6.1.5 Message 1008

Code	Severity	Message	ToDo
1008	Error	Authentication failed or interrupted ( <stopped>, <status>, <response>, <reason>, <flipovercount>, <latency>)</latency></flipovercount></reason></response></status></stopped>	The EA is not able to authenticate the user access to the service at its start up time. More

#### **Failed Authentication**

#### Issue

The EA is not able to authenticate the user access to the service at attach or restart time and does not start up.

#### Possible root cause


The EA could not connect to the authentication server.

- The user guit the authentication process.
- There is a typo in the **Access ID** entered by the user.
- The RSI ForexLiberator EA is not yet purchased by the user.
- The RSI ForexLiberator EA was purchased, but not yet activated by the user.
- The RSI ForexLiberator EA was purchased or a trial started, but the licensed period (e.g. calendar days) has lapsed.
- The RSI ForexLiberator EA was purchased, but the licensed usage limit (e.g. number of parallel accesses) is breached by the user.

#### Resolution

Double check the following items to find resolution to the issue.

- 1. Ensure that the computer has working Internet connection. For example, go to the Web Support Centre and see if the page loads with no issues. When the Internet connection is working, restart the EA by pressing F7 and clicking the **OK** button of the **Expert** property window.
- 2. Ensure you enter the correct Access ID, case sensitive, without any typo, and click the **Save** button of the **Service Access Settings** authentication window.



- 3. Ensure you have purchased the product. Log in to the Web Support Centre and select the RSI ForexLiberator EA from the product list. If the product is **not** available for download then it is yet to be purchased at the Web Support Centre.
- **4.** Count the number of computers you are running the RSI ForexLiberator EA on. If it is more than what the purchased EA licence copies allow then either shut down on the excess number of the computers all the running RSI ForexLiberator instances, or purchase more licence at the Web Support Centre.

## 6.1.6 Message 1121

Code	Severity	Message	Description
1121	Error	Order close failed at bid <bid> for #<ticketno> <tickettype> cmnt:<ticketcomment> (<attemptno>, <ticketcount>/ <totalticketcount>, <latency>ms)</latency></totalticketcount></ticketcount></attemptno></ticketcomment></tickettype></ticketno></bid>	Attempt to close an open trade returned with error. More

#### Attempt to Close an Open Trade Failed

Issue

The EA requested to close an open trade but it returned back with error. The operation may or may not have closed out the open trade.

#### Possible root cause

- The trade got closed off in the meantime by the broker server due to reaching its take profit or stop loss limits.
- The trade got closed off by another EA.
- · The trade got closed off manually.
- The price quote changed slipping the close order outside of allowed range.
- The MT5 terminal lost its connection to the broker server.

#### Resolution

Typically this issue is temporary and the EA recovers from this issue automatically over the subsequent incoming data feed ticks. When this issue is reported only a few times there is no need for further attention. In order to double check that the trade got eventually closed off follow these steps:

- 1. Take a note of the ticket number reported by the message something like as #12345678.
- 2. Go to the **History** tab of the **Toolbox** window (press Ctrl+T).
- 3. Search for the ticket number noted above, in the column **Order**.

If the ticket is found in the **History** tab then it got closed off subsequently with success, and no further action is needed.

In the case of connection problems, refer to the Knowledgebase topic No Updates to Chart for resolution.

#### Related information


No Updates to Chart on page 73

## 6.1.7 Message 1163

Code	Severity	Message	Description
1163	Warning	Connection - Down X times Last time	The MT5 lost connection to the broker's server. More

#### Issue

The RSI ForexLiberator EA got attached to a chart and the EA is up and running. The EA monitors the connection between the MT5 terminal and the broker server. When the MT5 loses connection to the broker server then the EA presents this Connection Down message in its dashboard - see the orange message as an example:



In the above screenshot the last connection issue happened at 14:19 broker server time (chart time).

This means that somewhere along the Internet connection path from your computer to the broker server, including your home networks, the Internet and your brokers remote networks, there was some temporary issue resulting in data transfer interruption.

During this time the RSI ForexLiberator EA cannot receive price feed from the broker, i.e. no ticks are coming in. This also means that, due to the lack of price feed and ticks, the EA is not activated and cannot perform trading or managing open trades. When the MT5 re-establishes the connection to the broker server and price feed comes in again then the EA automatically resumes its trading operations.

#### Resolution

In order to minimize the downtime, please ensure the following:

- 1. Your computer is connected to your home networks over a wire, i.e. cabled to your modem or router. Note that wireless connectivity is more prone to connection issues.
- 2. Use a cable based Internet service provider, if feasible. Wireless based Internet service providers, like mobile or cellular based Internet providers could have more connectivity issues.
- **3.** Turn off the sleep or hibernation mode on your computer. When your computer goes into sleep or hibernation the Internet connection would be lost.
- **4.** If in doubt, restart your home networks: shutdown your computer, turn off your modem or router, wait 10 seconds then turn back on the modem/router then your computer.

**Note:** Even the best Internet connection could see a handful of connection issues on a daily basis. When you see more than a handful, like into 100 or more a day then your attention is needed.

#### Related information

No Updates to Chart on page 73


## 6.1.8 Message 2101

Code	Severity	Message	Description
2101	Error	Initialization failed	Initialization failed More

#### Initialization failed

#### Issue

The EA dashboard shows that Initialization failed.



#### Possible root cause

- Your computer slowed down for some reason, and the EA could not start up in a timely manner.
- The EA shut down itself in order to reduce the load on your computer, and allow you to gain back responsiveness of the computer, so you can free up some resources.

#### Resolution

Sometimes this can be associated with heavy swap usage by the operating system, which could be caused by RAM shortage, or cycles of hibernation (close the lid of the laptop). The best way to clean this up is to simply to reboot your computer: exit the MT5, shut your computer down and boot it up again. Do not start up any other application just the MT5 and see if the EA can start up now, after the reboot.

## 6.1.9 Message 2118

Code	Severity	Message	ToDo
2118	Error	Service access disabled ( <accessid>, <confirmationid>) - shutting down</confirmationid></accessid>	The user quits the authentication process, or the EA is not able to authenticate the user access to the service. More

#### **Aborted Authentication**

#### Issue

The EA is not able to authenticate the user access to the service at attach or restart time and does not start up.


#### Possible root cause

- The user quit the authentication process.
- The EA could not connect to the authentication server.
- There is a typo in the Access ID entered by the user.
- The RSI ForexLiberator EA is not yet purchased by the user.
- The RSI ForexLiberator EA was purchased, but not yet activated by the user.
- The RSI ForexLiberator EA was purchased or a trial started, but the licensed period (e.g. calendar days) has ellapsed.
- The RSI ForexLiberator EA was purchased, but the licensed usage limit (e.g. number of parallel accesses) is breached by the user.

#### Resolution

Double check the following items to find resolution to the issue.

- 1. Ensure that the computer has working Internet connection. For example, go to the Web Support Centre and see if the page loads with no issues. When the Internet connection is working, restart the EA by pressing F7 and clicking the **OK** button of the **Expert** property window.
- 2. Ensure you enter the correct Access ID, case sensitive, without any typo, and click the **Save** button of the **Service Access Settings** authentication window.



3. Ensure you have purchased the product. Log in to the Web Support Centre and select the RSI ForexLiberator EA from the product list. If the product is **not** available for download then it is yet to be purchased at the Web Support Centre.

4.	Count the number of computers you are running the RSI ForexLiberator EA on. If it is more than what the purchased EA licence copies allow then either shut down on the excess number of the computers all the running RSI ForexLiberator instances, or purchase more licence at the Web Support Centre.

# Chapter

7

# Support

## Index

Numerics	C
1001	Clean up after the download in the Internet Explorer
Message 106	Download 96
1002	Knowledgebase 96
Message 107 1006	Closeout Summary Text Colour
Message 108	Parameters 35, 35 Closeout Text Display
1007	Parameters 35, 35
Message 108	Combined Profit & Risk Settings
1008	parameters 38
Message 109	Computer Always-on
1121 Message 110	Knowledgebase 79 Configuration
1163	Configuration Principles 16
Message 111	Operation Principles 16
2101	Configuration Principles
Message 112	Configuration 16
2118 Message 113	Connection Down Message
Wessage 113	Knowledgebase 78 Copyright Notices
A	Copyright Notices 5
^	17 5
Access ID	D
Knowledgebase 74	Di e distribution
Account Type Requirements System Requirements 15	Direction of Initial Trade Entry
Activation	Parameters 17, 17 DLL Imports Not Allowed
Access ID 9, 62, 66	Knowledgebase 77
Attach 9, 62, 66	Visual Mode 77
First Time Activation 9, 62, 66	Download
MT5 Common Tab 9, 62, 66	Clean up after the download in the Internet Explorer 96
MT5 Inputs Tab 9, 62, 66	How to enable Download in your Internet Explorer 93,
Service Access Settings 9, 62, 66	101
Algo Trading Disabled  EA Not Starting Up 70	How to enable JavaScript in your Internet Explorer 91, 99
Allow buy & Sell the Same Pair at the Same Time	VPS 87
Parameters 26	
Allow Buy & Sell the Same Pair at the Same Time	E
Parameters 25, 25	-
Allow DLL Imports	EA Non-standard Installation
Backtest 78, 80 AutoTrading Disabled	Knowledgebase 85
EA Not Starting Up 70, 72	EA Not Starting Up Algo Trading Disabled 70
3 -1 -7	AutoTrading Disabled 70, 72
В	EA Standard Installation
	Knowledgebase 83
Backtest	ECN/STP Broker Accounts
Allow DLL Imports 78, 80	System Requirements 15
No Result 77, 78, 80 No Trades 80	Entry Window From Hour/Minute Parameters 34
BASKET OF TRADES MANAGEMENT	Entry Window Until Hour/Minute
Parameters 26	Parameters 34
Broker GMT Offset	Example - Balanced Amount Pruning
Knowledgebase 71	Parameters 55
BUY:Approx. Closeout Price Level Colour	Example - Closure at Pips Profit
Parameters 35, 36	Parameters 54  Example: Closure at Portfelia Loss
	Example - Closure at Portfolio Loss Parameters 55
	i didilicicis do

Example - Closure at Portfolio Profit	Friday Trade Entry
Parameters 54	Parameters 34
Example - Closure at Profit Amount	
Parameters 54	G
Example - Entry with TP and Hidden TP	•
Parameters 41	Gap Pruning From This Scale of Initial Gap
Example - Entry with TP Only	Parameters 30, 31
Parameters 41	Gap Scaling Rate
Example - Entry with TP, Hidden TP and Trailing	Parameters 17, 19
Parameters 42	
Example - FIFO Trading	Gap Scaling Start Level
•	Parameters 17, 19
Parameters 56	GMT Offset Of Broker
Example - First & Last Trades Pruning	Parameters 33
Parameters 55	Gray Sign
Example - Gap Pruning	Knowledgebase 70
Parameters 56	
Example - Initial Lots Adjustment Up & Down	Н
Parameters 46	11
Example - Initial Lots Adjustment Upward Only	Hardware Requirements
Parameters 46	System Requirements 14
Example - Normal Entry	HEDGE TRADES MANAGEMENT
Parameters 40	Parameters 25
Example - Reverse Entry	
Parameters 41	Hedging Support Requirements
Example - Same Initial Lots All the Time	Hedging Mode 14, 15
Parameters 46	Netting Mode 14, 15
	System Requirements 14
Example - Same Position Size All the Time	How to download an EA setup in VPS environment
Parameters 47	Knowledgebase 87
Example - Scale Lots Down by Amount	How to Download MT5
Parameters 50	Knowledgebase 58
Example - Scale Lots Down by Multiplier	How to Download the Setup Application from the Web
Parameters 48	Support Centre
Example - Scale Lots Up by Amount	Knowledgebase 58
Parameters 49	How to Edit the EA Input Values
Example - Scale Lots Up by Multiplier	Knowledgebase 75
Parameters 48	How to enable Download in your Internet Explorer
Example - Scale Price Gap Down by Rate	Downloadn 93, 101
Parameters 45	
Example - Scale Price Gap Up by Rate	Knowledgebase 93, 101
Parameters 44	How to enable JavaScript in your Internet Explorer
Example - Skip Topup and Scale Up by Amount	Downloadn 91, 99
Parameters 52	Knowledgebase 91, 99
Example - Skip Topup and Scale Up by Multiplier	How to Upgrade the EA
Parameters 51	Knowledgebase 61
Example - Skip Topups and Scale Down by Amount	
Parameters 53	1
Example - Skip Topups and Scale Down by Multiplier	
Parameters 51	Indicator Non-standard Installation
Example - Stop Trading After Portfolio Closure	Knowledgebase 85
Parameters 55	Indicator Standard Installation
	Knowledgebase 83
Example - Stop Trading of Certain Pairs	Initial Lots Adjustment: Base Account Equity Amount
Parameters 44	Parameters 22
Example - Trade Max 1 Pair Involving the Same Currency	Initial Lots Adjustment: Initial Lots Adjustment
Parameters 43	Parameters 23
Example - Trade Not More Than 2 Out of Multiple Markets	Initial Lots Adjustment: Required Equity Change
Parameters 42	Parameters 22
	Initial Lots Ajustment: Base Account Equity Amount
F	Parameters 17
	Initial Lots Ajustment: Initial Lots Adjustment
First Time Activation	Parameters 17
Activation 9, 62, 66	Initial Lots Ajustment: Required Equity Change
Forex Broker Requirements	Parameters 17
System Requirements 14	INITIAL TRADE MANAGEMENT
	Parameters 23

Initial Trade Trailing Stop Parameters 24 Initial: Hidden TP	Maximum Traded Markets Parameters 26 Maximum Traded Pairs
Parameters 23, 24	Parameters 29
Initial: Stop Loss	Message 105, 105, 106, 106
Parameters 23	1001 106
Initial: Take Profit	1002 107
Parameters 23, 23	1006 108
Install	1007 108
Non-standard Installation 85	1008 109
RSI ForexLiberator EA 6, 59	1121 110
Standard Installation 83	1163 111
	2101 112
K	2118 113
N .	MetaTrader (MT5) Requirements and Settings
Knowledgebase	System Requirements 14
Access ID 74	Minimum Gap Size
Broker GMT Offset 71	Parameters 17, 20
Clean up after the download in the Internet Explorer 96	Minimum Lot Size Requirements
Computer Always-on 79	System Requirements 15
Connection Down Message 78	MISCÉLLANEOUS
DLL Imports Not Allowed 77	Parameters 35
EA Non-standard Installation 85	Monday Sunday Trade Entry
EA Not Starting Up 72	Parameters 34, 34
EA Standard Installation 83	Monday Trade Entry
Gray Sign 70	Parameters 34
How to download an EA setup in VPS environment 87	
How to Download MT5 58	N
How to Download the Setup Application from the Web	
Support Centre 58	No Trades
How to Edit the EA Input Values 75	Knowledgebase 78
How to enable Download in your Internet Explorer 93,	No Trades Due to Trade Disabled
101	Knowledgebase 76
How to enable JavaScript in your Internet Explorer 91,	No Trades Since
99	Knowledgebase 76, 81
How to Upgrade the EA 61	No Updates to Chart
Indicator Non-standard Installation 85	Knowledgebase 73
Indicator Standard Installation 83	Non-FIFO Support Requirements
No Trades 76, 78, 81	System Requirements 15 Not Enough Memory For Bar History Or Indicator
No Trades Due to Trade Disabled 76	Knowledgebase 75
No Updates to Chart 73	Miowiedgebase 70
Not Enough Memory For Bar History Or Indicator 75	
Sadface 73, 79	0
Step-by-step Installation Guide 82	Operating System Requirements
Visual Mode Checkbox Missing in Strategy Tester 81	System Requirements 14
What is My Account Leverage 71	Operation Principles
	Configuration 16
L	3
	P
Lots for Initial Trade Entry	•
Parameters 17, 20	Pair Name Prefix & Suffix
	Parameters 35, 37
M	Pair: Target Closure \$ Amount
Manda Nicoshan	Parameters 26, 26
Magic Number	Pair: Target Profit Pips Closure
Parameters 35, 40	Parameters 26, 27
Maximum Currency Exposure Parameters 26, 29	Pairs to Get Out
Maximum Topup Trades per Market per Direction	Parameters 26, 28
Parameters 26	Pairs to Trade
Maximum Topup Trades per Pair per Direction	Parameters 26, 28
Parameters 29	parameters  Combined Profit & Rick Settings 38
	Combined Profit & Risk Settings 38

Tick Scaling for CFD Markets 38	Initial: Stop Loss 23
Parameters	Initial: Take Profit 23, 23
Allow buy & Sell the Same Pair at the Same Time 26	Lots for Initial Trade Entry 17, 20
Allow Buy & Sell the Same Pair at the Same Time 25,	Magic Number 35, 40
25	Maximum Currency Exposure 26, 29
BASKET OF TRADES MANAGEMENT 26	Maximum Topup Trades per Market per Direction 26
BUY:Approx. Closeout Price Level Colour 35, 36	Maximum Topup Trades per Pair per Direction 29
Closeout Summary Text Colour 35, 35	Maximum Traded Markets 26
Closeout Text Display 35, 35	Maximum Traded Pairs 29
Direction of Initial Trade Entry 17, 17	Minimum Gap Size 17, 20
Entry Window From Hour/Minute 34	MISCELLANEOUS 35
Entry Window Until Hour/Minute 34	Monday Sunday Trade Entry 34, 34
Example - Balanced Amount Pruning 55	Monday Trade Entry 34
Example - Closure at Pips Profit 54	Pair Name Prefix & Suffix 35, 37
Example - Closure at Portfolio Loss 55	
Example - Closure at Portfolio Profit 54	Pair: Target Closure \$ Amount 26, 26
Example - Closure at Profit Amount 54	Pair: Target Profit Pips Closure 26, 27
·	Pairs to Get Out 26, 28
Example - Entry with TP and Hidden TP 41	Pairs to Trade 26, 28
Example - Entry with TP Only 41	Portfolio: Closure at Maximum Loss \$ Amount 26, 27
Example - Entry with TP, Hidden TP and Trailing 42	Portfolio: Closure at Profit \$ Amount 26, 27
Example - FIFO Trading 56	Portfolio: Reentry After Closure 26, 27
Example - First & Last Trades Pruning 55	Price Gap 17, 19
Example - Gap Pruning 56	PRUNING OF TRADES 30
Example - Initial Lots Adjustment Up & Down 46	Reference Time Selection 32, 32
Example - Initial Lots Adjustment Upward Only 46	RSI Applied Price 17, 18
Example - Normal Entry 40	RSI OverBought/Sold Levels 17, 18
Example - Reverse Entry 41	RSI Period 17, 17
Example - Same Initial Lots All the Time 46	Saturday Trade Entry 34
Example - Same Position Size All the Time 47	SELL:Approx. Closeout Price Level Colour 35, 36
Example - Scale Lots Down by Amount 50	Start Pruning at Trade Count in a Pair Direction 30, 30
Example - Scale Lots Down by Multiplier 48	Sunday Trade Entry 34
Example - Scale Lots Up by Amount 49	Thursday Trade Entry 34
Example - Scale Lots Up by Multiplier 48	Tick Scaling for CFD Markets 35
Example - Scale Price Gap Down by Rate 45	TIME OF DAY FOR INITIAL ENTRY 32
Example - Scale Price Gap Up by Rate 44	Topup Lots Change by Lots 17, 21
Example - Skip Topup and Scale Up by Amount 52	Topup Lots Multiplier 17, 20
Example - Skip Topup and Scale Up by Multiplier 51	Topup TP Mode 26, 29
Example - Skip Topups and Scale Down by Amount 53	Topup Trades to Skip, Count 17, 22
Example - Skip Topups and Scale Down by Multiplier	TRADE ENTRY 17
51	Trade Pair Pruning Approach 30, 30
Example - Stop Trading After Portfolio Closure 55	Trailing SL 23, 24, 25
Example - Stop Trading of Certain Pairs 44	Trailing Start at Profit 23, 24, 24
Example - Trade Max 1 Pair Involving the Same	Trailing Stepping 23, 24, 25
Currency 43	Tuesday Trade Entry 34
Example - Trade Not More Than 2 Out of Multiple	Wednesday Trade Entry 34
Markets 42	Portfolio: Closure at Maximum Loss \$ Amount
Friday Trade Entry 34	Parameters 26, 27
Gap Pruning From This Scale of Initial Gap 30, 31	Portfolio: Closure at Profit \$ Amount
Gap Scaling Rate 17, 19	Parameters 26, 27
Gap Scaling Start Level 17, 19	Portfolio: Reentry After Closure
GMT Offset Of Broker 33	Parameters 26, 27
HEDGE TRADES MANAGEMENT 25	Price Gap
Initial Lots Adjustment: Base Account Equity Amount	Parameters 17, 19
22	PRUNING OF TRADES
Initial Lots Adjustment: Initial Lots Adjustment 23	Parameters 30
Initial Lots Adjustment: Required Equity Change 22	
Initial Lots Ajustment: Base Account Equity Amount 17	R
Initial Lots Ajustment: Initial Lots Adjustment 17	••
Initial Lots Ajustment: Required Equity Change 17	Reference Time Selection
INITIAL TRADE MANAGEMENT 23	Parameters 32, 32
Initial Trade Trailing Stop 24	RSI Applied Price
Initial: Hidden TP 23, 24	Parameters 17, 18

RSI ForexLiberator EA	V
Installation 6, 59	Visual Mode
RSI OverBought/Sold Levels Parameters 17, 18	DLL Imports Not Allowed 77
RSI Period	Visual Mode Checkbox Missing in Strategy Tester
Parameters 17, 17	Knowledgebase 81
,	VPS
S	Download 87
Sadface	W
Knowledgebase 73, 79	**
Saturday Trade Entry	Wednesday Trade Entry
Parameters 34	Parameters 34
SELL:Approx. Closeout Price Level Colour	What is My Account Leverage
Parameters 35, 36	Knowledgebase 71
Start Pruning at Trade Count in a Pair Direction Parameters 30, 30	
Step-by-step Installation Guide	
Knowledgebase 82	
Sunday Trade Entry	
Parameters 34	
Support	
Support 115	
System Requirements	
Account Type Requirements 15 ECN/STP Broker Accounts 15	
Forex Broker Requirements 14	
Hardware Requirements 14	
Hedging Support Requirements 14	
MetaTrader (MT5) Requirements and Settings 14	
Minimum Lot Size Requirements 15	
Non-FIFO Support Requirements 15	
Operating System Requirements 14	
<b>T</b>	
Т	
Thursday Trade Entry	
Parameters 34	
Tick Scaling for CFD Markets	
parameters 38	
Parameters 35 TIME OF DAY FOR INITIAL ENTRY	
Parameters 32	
Topup Lots Change by Lots	
Parameters 17, 21	
Topup Lots Multiplier	
Parameters 17, 20	
Topup TP Mode	
Parameters 26, 29 Topup Trades to Skip, Count	
Parameters 17, 22	
TRADE ENTRY	
Parameters 17	
Trade Pair Pruning Approach	
Parameters 30, 30	
Trailing SL	
Parameters 23, 24, 25 Trailing Stort at Profit	
Trailing Start at Profit Parameters 23, 24, 24	
Trailing Stepping	
Parameters 23, 24, 25	
Tuesday Trade Entry	
Parameters 34	