Maal Help

Your Warehouse. Under Control.

USER MANUAL

Warehouse Manager

Runs warehouse operations and staff: space, receiving, putaway, picking, packing, dispatch, transfers, counts and approvals of operational requests. No financial figures unless granted.

Version 1.0 · 25 October 2026

For Maal Help 1.0

About this manual

Item	Details
Product	Maal Help 1.0: *Your Warehouse. Under Control.*
Manual	Warehouse Manager User Manual
Role in the system	Warehouse Manager
Version / date	1.0 · 25 October 2026
Screenshots	Captured from the running application with the fictional demo company "ABC Trading & Warehousing"
Demo account for this role	`manager@example.com`. Development/demo environment only. The password is provided by your administrator and is never printed in manuals.

Contents

1. Introduction 2

Who this manual is for · What you can and cannot do

2. Access and navigation 3

Signing in · Finding your way around

3. Your home screen 5

4. Features step by step 6

Warehouses and the space map · Approvals · Stock transfers · Stock counts · Stock adjustments and status changes · Receiving goods (GRN) · Putaway · Picking · Packing station · Dispatch and delivery tracking · Customer returns · Products · Barcode labels and printing · Alert center · AI Copilot · Reports and exports

5. End-to-end workflows 31

Start of shift · Warehouse nearly full · Investigate a short pick

6. Reports, notifications and exceptions 32

Reports and exports · Notifications and alerts · When something is refused

7. FAQ and troubleshooting 33

Frequently asked questions · Troubleshooting

8. Glossary and quick reference 34

Quick reference · Glossary

1 Introduction

Who this manual is for

This manual is for people with the **Warehouse Manager** role in Maal Help. Runs warehouse operations and staff: space, receiving, putaway, picking, packing, dispatch, transfers, counts and approvals of operational requests. No financial figures unless granted.

Maal Help is a warehouse operating system: stock by warehouse, location, batch and owner on a permanent ledger, plus purchasing, sales and fulfilment, billing, reports and an AI Copilot that answers from your own data.

Your role can

- ✓ Manage warehouses, locations and products
- ✓ Approve adjustments, count variances and transfers (not your own)
- ✓ Assign and prioritise pick tasks and waves
- ✓ Run all floor operations and import data

Your role cannot

- ✗ See cost, value, margin or receivables (unless granted)
- ✗ Change company settings, users or approval rules

Screens show the fictional demo company **ABC Trading & Warehousing**. Your company's names and numbers will differ. Menus show only what your role is allowed to use.

2 Access and navigation

Signing in

Maal Help runs in any modern browser on a computer, tablet or Android phone. Your company administrator creates your account and gives you a temporary password.




Figure 1. The Maal Help sign-in page.

1. Open the Maal Help address your company gave you.
2. Enter your work email and password, then select **Sign in**.
3. The first time, change your temporary password: **Settings** → **My profile** → **Change password** (at least 10 characters with letters and numbers).
4. Forgot your password? Ask your company administrator to issue a temporary one (**Settings** → **Users** → **Reset password**).

> After 8 wrong passwords the account is locked for a short time. Wait, then try again.

> Sign out on shared computers. Sessions also expire automatically.

Finding your way around

The left sidebar shows only the screens your role may use. Counts next to a menu item (for example Putaway 2) show open work.




Figure 2. Press Ctrl + K anywhere to search products, orders, customers, locations and screens.

1. Use the **sidebar** to move between screens. Your name and role are at the bottom.
2. Use **Search anything...** at the top, or press **Ctrl + K**, then type a SKU, barcode, order number or name.
3. The **bell** opens your notifications. **Ask AI** opens the Copilot (if your role has it).
4. Tables support search, filters, sorting and paging. Click a row to open the record.

> If a screen or button you expect is missing, your role does not include that permission. Ask your administrator. The server enforces permissions, so hiding a menu is never the only control.

3 Your home screen




Figure 3. Warehouse Manager dashboard: operations without financial figures.

- Attention items focus on operations: capacity, delayed orders, putaway and dispatch backlogs, pending approvals.
- KPI cards show units rather than money.

4 Features step by step

Warehouses and the space map

Warehouses contain zones, aisles, racks, shelves and bins, plus receiving and dispatch docks. Capacity is tracked in units, m^3, kg and pallets.




Figure 4. Warehouses with capacity and utilisation.




Figure 5. The space map: colour shows how full each rack is. Drag racks to match your floor plan.

1. Open **Warehouses** and choose a warehouse.
2. Read the KPI cards: capacity used, free capacity, storage and empty locations, over/under-used and cubic utilisation.
3. **Space map**: drag racks and docks to match the floor, then **Save layout**. Click a rack to inspect its shelves and bins.
4. Tabs **Locations**, **Utilisation** and **Details** list every bin with barcode and capacity.
5. **Generate zone layout** creates zones, racks, shelves and bins in one step for a new warehouse.

Approvals

Adjustments, purchase orders, count variances, transfers and expenses above your company's thresholds wait here. Nothing is posted until it is approved.




Figure 6. Pending approval requests with summary, amount and requester.




Figure 7. Approving a stock adjustment with an optional comment.

1. Open **Approvals**.
2. Read the summary and amount. Open the record if you need more detail.
3. Select **Approve** or **Reject**. Add a comment, which is kept in the audit trail.
4. Approving posts the underlying transaction (for example the stock adjustment) immediately.

> You cannot approve your own request; only the Business Owner is exempt. Thresholds are set in **Settings → Approval rules**.

Stock transfers

Move stock warehouse to warehouse (with approval and in-transit tracking) or location to location within a site.




Figure 8. Transfers by status: To approve, To pick, In transit, Short received, Completed.




Figure 9. A transfer with its lines and progress.

1. Open **Transfers** → **New transfer**. Choose warehouse or location transfer, source and destination, products and quantities.
2. An approver approves it (if required).
3. The source team picks and **dispatches**: stock becomes **In transit** and cannot be sold.
4. The destination team **receives** it. Any shortage is recorded as *Short received* for investigation.

> You cannot approve a transfer you requested yourself.

Stock counts

Create a count, assign a counter, count, review the variance, approve and post. Significant variances always need approval.




Figure 10. Stock counts with progress and variance.




Figure 11. Count lines: expected versus counted.

1. **Stock counts** → **New count**: choose warehouse, type (cycle, full or blind) and scope.
2. Assign a counter. Counters count on the phone (**COUNT**): scan the location, then the product, and enter the counted quantity.
3. Review variances. Lines within tolerance post automatically; larger variances go for approval.
4. On approval, the difference posts as a count adjustment in the ledger.

> In a **blind count** the counter does not see the expected quantity.

> The tolerance % is set in **Settings** → **Inventory, notifications & AI**.

Stock adjustments and status changes

Record damage, loss, found stock or a status change (e.g. to quarantine) with a reason. Large adjustments wait for approval.

1. Open **Inventory**, find the product and location, and choose the adjustment action (or use the **Adjustments** tab).
2. Enter the quantity change (+ or −), a reason code and notes. Attach details in the notes for the approver.
3. If the value exceeds the threshold, the adjustment shows **Pending approval** and nothing changes until it is approved.

> Every adjustment is permanent history. To undo one, post an opposite adjustment with a reason.

Receiving goods (GRN)

1. Choose the delivery · 2. Scan each product · 3. Check quantities, batch and expiry · 4. Confirm.




Figure 12. Goods receipts (GRNs).




Figure 13. Receiving against a purchase order: expected quantity, damaged, quality, batch, expiry and location.




Figure 14. A posted goods receipt.

1. **Receiving → Receive goods**. Choose **Purchase order**, **Without PO** or **3PL client** (goods owned by a storage client).
2. Select the PO and warehouse; enter the delivery note and vehicle number.
3. Scan each product barcode (or type the SKU). Enter **Received** and **Damaged** quantities and set **Quality** (Passed / Hold (QC) / Failed → quarantine).
4. For batch or expiry items enter the batch and expiry date. For serial items scan every serial.
5. Leave the location empty to receive to the dock (a putaway task is created) or pick a bin.
6. Select **Confirm receipt**. Short and over deliveries are recorded automatically; more than 10% over the PO needs explicit confirmation.

> A supplier bill is created from the receipt for the accounts team.

> Damaged and quarantined units are kept separate and are never sold.

Putaway

Move received stock from the dock into storage. Maal Help recommends the best location and explains why.




Figure 15. Pending putaway tasks with the recommended location.




Figure 16. Ranked suggestions with reasons, or choose another location.

1. Open **Putaway** (or **PUTAWAY** on the phone).
2. Select **Put away** on a task. The top suggestion is marked **Recommended**, with reasons such as preferred zone, empty bin, or good fit.
3. Take the goods to the location and confirm. To use another bin, choose it and enter a reason; overrides are recorded.
4. Put away part of the quantity if needed. The rest stays on a new task.

> Stock at the dock cannot be sold until it is put away.

Picking

Tasks are ordered by priority, required date and walking sequence. Scan location and product to confirm. Wrong items are blocked.




Figure 17. Open pick tasks and waves (batch/zone).

1. Open **Picking**. Supervisors can assign tasks and group them into **Waves (batch / zone)**.
2. Pickers use **Mobile picker** (or PICK on the phone): go to the location, scan the location label, scan the product, enter the quantity.
3. If the stock is not there, use **Can't find it / short**. The missing quantity is blocked for a count and re-reserved elsewhere if possible.

> Errors you may see: *wrong location*, *wrong product*, *quantity exceeds the task*. Fix the scan and try again.

Packing station

Scan each picked item into the carton. The system confirms correct products and quantities before the carton can be closed.




Figure 18. An order ready to pack.




Figure 19. After a verification scan: GN-1004 1/2 confirmed.

1. Open **Packing** and choose the order (orders appear when all picks are finished).
2. Scan each item. Scan results show ✓ correct, or ✗ wrong product / excess quantity.
3. Add boxes and weights under **Packages**.
4. When all items are scanned, complete packing. Print the **Packing slip** and **Shipping labels**.
5. **Restart verification** clears the scans if you need to start the carton again.

Dispatch and delivery tracking

Hand packed orders to a vehicle or courier, then track delivery: Ready → Dispatched → In transit → Delivered.




Figure 20. Orders ready to dispatch.




Figure 21. Dispatch details: own vehicle or courier, vehicle, driver, freight cost.




Figure 22. Shipments and their delivery status.

1. Open **Dispatch → Ready to dispatch** and select **Dispatch** on an order.

2. Choose **Own vehicle / transporter** or **Courier**. Enter vehicle number, driver name and phone, and freight cost.
3. Confirm. Packed stock leaves inventory, the shipment is recorded and the sales invoice is issued.
4. In **Shipments**, update the status as the delivery progresses (In transit, Delivered).

> Courier connections in this version are demo (mock) connectors. Enter tracking numbers manually.

Customer returns

Receive returned goods and decide where each unit goes: back to stock, damaged, quarantine, repair or write-off.




Figure 23. Customer returns with reason, units and credit.

1. **Returns → Receive a return**: choose the customer and original order.
2. Enter quantities and the reason for each product, and inspect each unit.
3. Choose the outcome for each line. Only units returned to **available** can be sold again.
4. Confirm. Stock movements and any customer credit are recorded.

Products

The product master: SKUs, barcodes, units, dimensions, prices, reorder levels and tracking rules (batch, expiry, serial).




Figure 24. Product list with quick filters: Low stock, Out of stock, Overstock, In stock.




Figure 25. A product record with stock, barcodes and history.

1. Open **Products**. Use the filters or search.
2. **New product**: enter SKU, name, category, unit, barcode (or generate one), dimensions and weight, cost and selling price, tax, reorder level and quantity, and tracking rules.
3. **Import** loads many products from Excel/CSV (see Importing data).
4. Open a product to edit it, print labels or view stock and movements.

> Internal barcodes are EAN-13 numbers in the 29x in-store range, so they never clash with retail barcodes.

Barcode labels and printing

Print product, location and shipping labels from the browser.




Figure 26. Settings → Barcode, printing & billing: symbology, label size and paper.

1. Set defaults in **Settings** → **Barcode, printing & billing**: symbology (Code 128, EAN-13, QR), label size (50×25, 100×50, 100×150 mm) and paper (A4/Letter).
2. From a product, location or packing screen choose the label/print action, then print with your label printer selected in the browser print dialog.

> For thermal printers, set the printer's paper size to the label size and margins to none.

Alert center

Alerts tell you what needs action: low or out-of-stock items, expiring batches, full warehouses, delayed orders and overdue payments. You see only alerts your role may act on.




Figure 27. Alert center grouped by Critical, Warning and Info.

1. Open **Alerts** from the sidebar or the bell.
2. Filter by **Critical**, **Warning** or **Info**.
3. Use **Open** to go to the related record, **Read** to mark it seen, and **Resolve** when it is handled.
4. **Check now** re-evaluates alert conditions immediately (alerts are also checked automatically in the background).

AI Copilot

Ask questions in plain English. The Copilot looks up facts with read-only tools limited to what your role may see, and shows its sources. It can recommend; you decide.




Figure 28. An answer built from live data, with its data source and mode shown.

1. Open **AI Copilot** (or select **Ask AI**).
2. Type a question, for example *How much inventory do I have?*, *Which products are low?* or *Which customers owe me the most?*, or tap a suggestion.
3. Check the badge under the answer: **Mistral AI · from your data** or **Direct from your data (no AI model)**. Open *data sources* to see what was used.
4. Other tabs: **Daily briefing**, **Smart reorder**, **Stock intelligence**, **Anomalies**, **Space**, **Documents**, **Monthly report**.

> The AI never changes stock, approves anything or posts financial entries. Suggested purchase orders open as drafts that a person must review and save.

> If your company has not configured the AI model, answers are assembled directly from your data and are clearly labelled.

> Anomalies are flags for review, never accusations. Write your findings when you mark one reviewed.

Reports and exports

35 reports in five groups: Inventory, Warehouse, Sales, Purchasing and Financial. Every report supports filters, search, sorting, paging, Excel/CSV/PDF export and printing.




Figure 29. The report library.




Figure 30. Inventory valuation with filters and export.

1. Open **Reports** and choose a report. You see only reports your role may view.
2. Set filters (dates, warehouse, product, customer…) and search or sort the table.
3. Export with **Excel**, **CSV** or **PDF**, or print. PDFs carry the Maal Help letterhead.
4. **AI monthly report** gives a written business summary for a month.

5 End-to-end workflows

Start of shift

1. Check the dashboard for putaway, picking and dispatch backlogs.
2. In **Picking**, create waves and assign pickers.
3. Clear operational **Approvals**.

Warehouse nearly full

1. Open the warehouse **Space map**; find red/amber racks.
2. Open **AI Copilot** → **Space** for consolidation and slotting suggestions.
3. Create location transfers to consolidate part-empty bins.

Investigate a short pick

1. The short-picked quantity is blocked automatically.
2. Create a cycle count for that location.
3. Review the variance and approve or escalate.

6 Reports, notifications and exceptions

Reports and exports

Location and warehouse utilisation, Receiving/Picking/Dispatch performance, Inventory accuracy, Stock variance, Expiry.

Open **Reports**, choose a report, set filters and export to Excel, CSV or PDF, or print. You see only the reports your role may view.

Notifications and alerts

Capacity ≥85%, delayed orders, pending putaway/dispatch and expiring batches.

The bell at the top right lists new notifications. In-app alerts are always on; email and WhatsApp alerts depend on your company's settings.

When something is refused

Message	Meaning	What to do
Insufficient stock	Not enough *available* units at that place	Check reserved, quarantine or dock stock; choose another location or wait
Wrong location / wrong product	The scan does not match the task	Go to the right place or item and scan again
Quantity exceeds the task	More than required	Enter the task quantity
Pending approval	Above the company threshold	An approver must approve; nothing is posted yet
You don't have permission	Your role lacks the action	Ask your administrator
Credit limit exceeded	Customer balance too high	Collect payment or ask the owner

7 FAQ and troubleshooting

Frequently asked questions

Why can’t I approve my own transfer?

Segregation of duties: another approver (or the owner) must approve it.

Why can’t I see a menu or button?

Your role does not include that permission. Ask your administrator. Permissions are checked by the server.

Can I edit or delete a posted stock movement?

No. History is permanent. Corrections are new transactions (an adjustment or reversal) with a reason, so the audit trail stays complete.

Why does the screen say stock is not available?

It may be reserved for another order, in quarantine, damaged, expired, in transit or still at the receiving dock waiting for putaway.

Is my data visible to other companies?

No. Every company’s data is isolated, and requests for another company’s records are refused.

Troubleshooting

Problem	Solution
Putaway suggests no location ("Choose manually")	No bin in the preferred zone has room. Pick a location manually and give a reason, or free space.
“Missing anti-forgery header” or 403 when saving	Refresh the page. If it persists, you may lack permission for the action.
Account locked	Too many wrong passwords. Wait a few minutes or ask your administrator to reset your password.

> Still stuck? Note the screen, the record number (for example SO-10245) and the exact message, and contact your company administrator.

8 Glossary and quick reference

Quick reference

I want to...	Go to
Assign picks	**Picking → Waves**
Space map	**Warehouses → (warehouse)**
Approve	**Approvals**
Count a location	**Stock counts → New count**
Search anything	**Ctrl + K**

Glossary

Term	Meaning
SKU	Stock-keeping unit: one product code.
GRN	Goods received note: the record of a delivery received.
PO	Purchase order to a supplier.
SO	Sales order from a customer.
Putaway	Moving received goods from the dock into a storage location.
FEFO	First-expiry-first-out: older-expiry batches are reserved and picked first.
Reserved	Units promised to a confirmed order; not available for other orders.
Quarantine	Units held for inspection; not sellable.
In transit	Units dispatched on a transfer but not yet received.
Ledger	The permanent, append-only list of every stock movement.
Wave	A group of pick tasks picked together (batch or zone).
Back-order	The part of an order that could not be reserved yet.
3PL / storage client	A business whose goods you store and bill for storage and handling.
NTN / STRN	Pakistan national tax number / sales tax registration number.
Blind count	A count where the counter does not see the expected quantity.