Tungsten Printix

Capture Connector API - Network Share Sample Connector (Python)

TUNGSTEN AUTOMATION

© 2011–2025 Tungsten Automation. All rights reserved.

Tungsten and Tungsten Automation are trademarks of Tungsten Automation Corporation, registered in the U.S. and/or other countries. All other trademarks are the property of their respective owners. No part of this publication may be reproduced, stored, or transmitted in any form without the prior written permission of Tungsten Automation.

Table of Contents

Introduction....4
Prerequisites....5
Configuration settings....6
server_port....6
use_ssl....6
invalid_file_name_characters (array)....6
profiles (array)....6
Run the connector....10

Introduction

This document describes how to configure the sample connector written in Python, which this document is packaged together with. The sample connector is used to integrate applications with Printix Capture to process and deliver documents and metadata to custom systems.

The connector stores the captured document and the metadata retrieved from Printix on a pre-configured network share.

The connector's source code shows how to implement custom connectors for the Printix Capture Connector API using Python.

For detailed information on how the connector communicates with Printix, see "How to get started with Capture Connector API" in the *Printix Administrator Help*.

Prerequisites

Before you run the connector, ensure that:

- Python 3.10 or a newer version is installed and python.exe is added to the PATH environment variable.
- A virtual environment is created and activated, and the requirements are installed (see requirements.txt).
- The computer, where the connector will be running, is a member of a domain.
- At least one instance of the Printix Client is running on the same network as the computer where the connector will be running.
- This network is selected as the network of the connector destination profile in Printix Administrator.

Configuration settings

The connector configuration settings are stored in the appconfig.json file. To modify the connector configuration settings, open the file and modify the following settings as needed.

server_port

This setting indicates the port on which the connector listens for incoming requests.

The default port is 5555.

use_ssl

- To configure the connector to communicate on a secure channel, use this setting:

  ```
  "use_ssl": "true",
  ```

- To configure the connector to communicate on an unsecured channel, use this setting:

  ```
  "use_ssl": "false",
  ```

For secure communication, the connector automatically generates a self-signed certificate when it is started.

> We highly recommend configuring the connector with secure communication.

invalid_file_name_characters (array)

Array of invalid file name characters.

The connector removes these characters from the file name received in the FileDeliveryJobReady event from Printix to ensure that the file name is compatible with the target system or network share.

profiles (array)

You can configure one or more profiles for the connector. A connector profile determines how and where the captured document is stored and with which metadata. Profiles enable configuring different connector destination profiles with the same connector on the Capture workflows page in Printix Administrator, by specifying different profile IDs in the Connector URL.

The following settings can be configured for a profile:

- **id**

  The unique identifier of the profile. It must be a valid UUID.

  Must be part of the Connector URL configured in a connector destination profile in Printix Administrator.

  - If the connector listens on a secure channel, the Connector URL format must be as follows:

    https://{FQDN}:{port}/networkshare/{profileId}
  - If the connector listens on an unsecured channel, the Connector URL format must be as follows:

    http://{FQDN}:{port}/networkshare/{profileId}
    - **{FQDN}** is the fully qualified domain name of the computer where the connector is running.
    - **{port}** is the value configured in the server_port setting.
    - **{profileId}** is the value of the profile's id property under the profiles setting.

  Example:

  https://myserver.mydomain.local/networkshare/123e4567-e89b-42d3-a456-556642440000
- **secret_keys**

  One or more shared secret keys of type HMAC SHA-256 or HMAC SHA-512, generated by Printix, to ensure the authenticity of incoming and outgoing requests on both the connector and the Printix side.

  After creating a connector destination profile at Printix side, configuring its Connector URL, and generating shared secret keys of type HMAC SHA-256 or HMAC SHA-512 for the destination profile, these secret keys should be pasted as the value of this setting. The secret keys must be separated by comma.

  Example:

  ```
  "secret_keys": [
    "ZRgdknI+3vjYfPkJEak3hU3+X77OaV7xEzQ1RYormrw=",
    "McUCaLAZ6hRq18FycASoOml0DSY0Ez0ftpXvER5GDZA="
  ],
  ```
- **tokens**

  One or more shared secret keys of the Connector Token type, generated by Printix, to ensure the authenticity of incoming and outgoing requests on both the connector and the Printix side.

  After creating a connector destination profile at Printix side, configuring its Connector URL, and generating shared secret keys of the Connector Token type for the destination profile, these secret keys should be pasted as the value of this setting. The tokens must be separated by comma.

  Example:

  ```
  "tokens": [
    "0PIoJi2Ftvpyoy87MhhJNuAfO1xn+BPA2N6e1SU5gY2y3VjWAgW4Fsdp1/
  qvvlU0fwuAC0vl1ld0F9oujO8yoA==",
    "Abe6HO5Z/FaKfznisosnIJYCbQDMoSZsYGQ+LUL2jDe752rTKSfAR9Dn/CWe2d05PPn/
  yV7O53O0vJJHddTGgw=="
  ],
  ```
- **path**

  A valid path of a network share where the connector stores the captured document, and optionally, the metadata file.

  Example:

```
"path": "\\\\myfileserver.mydomain.local\\Invoices",
```

The user running the connector must have write permission on this network share.

- **metadata-format**

  The format in which the connector queries metadata from Printix.

  Possible values:

  - **List** (default): Used for querying metadata in JSON array (list) format.
  - **Object**: Used for querying metadata in JSON object format.

  If not defined, the connector queries metadata in JSON array (list) format.

  Example:

```
"metadata-format": "Object",
```

- **index_field_option**

  An option that specifies which metadata should be queried by the connector.

  Possible values:

  - **Configured** (default): Used for querying metadata configured in the **index_fields** configuration setting (see below).
  - **AllCustom**: Used for querying all custom metadata configured for the capture workflow.

    The **index_fields** configuration setting is ignored, and the connector uses Printix names to write the queried metadata to the metadata file.

    If a custom metadata has the Lookup type, the connector queries all properties of the metadata value and writes them to the metadata file with name in "*<metadata name>_<property name>*" format.

    Example: Project_key, Project_value

    In the example, "Project" is the metadata name, while "key" and "value" refer to the Key and Value properties of the metadata value.
  - **All**: Used for querying all system and custom metadata configured for the capture workflow.

    The **index_fields** configuration setting is ignored, and the connector uses Printix names to write the queried metadata to the metadata file.

    If a custom metadata has the Lookup type, the connector queries all properties of the metadata value and writes them to the metadata file with name in "*<metadata name>_<property name>*" format.

    Example: Project_key, Project_value

    In the example, "Project" is the metadata name, while "key" and "value" refer to the Key and Value properties of the metadata value.

  If not defined, the connector queries metadata configured in the **index_fields** configuration setting.

- **index_fields (array)**

  Multiple metadata belong to the captured document, which can be stored in the location specified in the **path** setting. With index fields, you can configure which metadata should be stored.

To define an index field, the following properties must be specified:

- **Id**

  The name of the index field written into the metadata file.

- **metadata_name**

  The name of the metadata at Printix side, which the connector writes as the value of the index field in the metadata file.

  If a custom metadata has the Lookup type, you must specify the Key or Value property of the metadata value in "*<metadata name>_<key or value>*" format to write that key or value into the metadata file.

  Example: Project_key or Project_value

  In the example, "Project" is the metadata name, while "key" and "value" refer to the Key and Value properties of the metadata value.

  For supported system metadata names, see the "Querying metadata" section of "How to get started with Capture Connector API" in the *Printix Administrator Help*.

By default, the appconfig.json file contains more example profiles: One with more index fields and another one without any index fields.

Run the connector

To launch the connector, activate the virtual environment and run `python app.py`.

The connector starts listening on the configured port and waiting for Printix notifications about documents being captured to process and deliver them.