Cabin Lifecycle DFDs

Leon Starr
2026-4-18/ v0.10

Copyright © 2025-2026, Leon Starr at
MODEL INTEGRATION, LLC

A28

Changing destination

```
~.Go to floor( Dest floor: ^new dest )? {
   Cabin redirected( Updated dest: ^new dest ) -> /R53/Transfer
   Change requested -> me
}
```



Copyright © 2025-2026, Leon Starr at Model Integration, LLC

A27

Update location

&R43 /R2/R28/Shaft Level(1, ^floor)
New location(^floor) -> ~UI
Location updated -> me

We require the explicit 1 cardinality in the Shaft Level selection even though it could be derived. But the populate isn't smart enough to do that yet. It should be seeing that since we traverse from a single instance of Cabin to a single instance of Shaft to many instances of Shaft Level and that the identifier of Shaft Level is Shaft + Floor with Shaft implicitly provided by the navigation with a single value of Floor specified that we are, effectively, selecting on an identifier. For now, cardinality must be explicit unless a full identifier is supplied in the select expression.



A30

READY TO GO

Ready to go -> /R53/Transfer



Copyright © 2025-2026, Leon Starr at Model Integration, LLC

A31

SECURING DOORS

```
my door .= /R4/Door
my door.Lock requested.set
Lock -> my door
```



By assigning the traversal result to a labeled flow, we avoid specifying two identical traverse actions as we do with the alternate action language (see next page).

Of course we could post process the action recognizing and replacing the duplicate actions. And in the future, we should definitely perform flow graph optimizations prior to execution. For now, let's just simplify the action language we write.

Copyright © 2025-2026, Leon Starr at Model Integration, LLC

A38

Requesting transport

Go to floor(dest floor: /R53/Transfer.Destination floor) -> ~TRANS
Transport in progress -> me

Copyright © 2025-2026, Leon Starr at Model Integration, LLC

A32

SECURING DOORS

/R4/Door.Lock requested.set
Lock -> /R4/Door



Copyright © 2025-2026, Leon Starr at Model Integration, LLC

A32

Are we already there?

/R53/Transfer.Destination floor == /R43/Shaft Level.Floor ?
Already there -> : Prepare to move -> me



Copyright © 2025-2026, Leon Starr at Model Integration, LLC

A34

PICKUP DROPOFF

Cabin at destination -> /R53/Transfer
Unlock -> /R4/Door
! /R2/Shaft.In service ? Take out of service -> me



Copyright © 2025-2026, Leon Starr at Model Integration, LLC

A35



Copyright © 2025-2026, Leon Starr at Model Integration, LLC

A36

Copyright © 2025-2026, Leon Starr at Model Integration, LLC