aramis™
ENTERPRISE SOLUTIONS

FUNCTIONAL REQUIREMENTS SPECIFICATION

Dynamic Dimension Mapping & Hierarchy Visualization

Dimension Management Module

Document Type	Functional Requirements Specification (FRS)
Module	Dimension Management
Version	2.5
Date	06 October 2026
Prepared By	Aramis Enterprise Solutions

TABLE OF CONTENTS

Contents

1. Introduction 3

1.2 Scope 3

2. Pre-Configured Dimensions 4

3. Dimension Mapping 4

4. Functional Requirements 5

4.1 Each Dimension Shows Its Own Tree View 5

4.2 Adding a Value Must Follow the Mapping 10

4.3 One Combined Organization Tree 12

5. Business Rules 13

1. Introduction

This document explains, in plain terms, a new way of displaying and managing the dimension structures already available in the Workmate HCM Dimension Management Module. It is written for the project team and for anyone approving the design before it is built.

1.2 Scope

- A hierarchy designer that allows to define relationships between different dimensional master tables.
- All dimensional master tables, e.g. Business Unit, Division, Branch, Department, Position (Organization Role), should appear as separate menu items.
- Each dimension, e.g. Department, can have unlimited records created.

  Step 1. Allow dimension records to be linked to its own parent dimension (e.g. Lahore branch mapped to Branch Dimension)

  Step 2. Allow the created record to be mapped to the parent nodes in the hierarchy (e.g. Branch record to Division dimension)
- Each dimension table can be viewed in a tree structure showing links/relations between one another.
- One combined tree that shows the full organization structure, built automatically based on every dimension's mapping/linking.
- Each dimension record should have effective start/end date. Effective Start date must be mandatory and effective end date must be optional.
- Positions are linked to the Organization Structure hierarchy. Based on the linking, when a position role is assigned to the employee, the employee becomes part of the organization structure (e.g. which division, department, Cost Centre, Grade, the employee belongs to).
- Role Structure (Position) will have its own tree structure.
- Employee Master setup needs to be re-aligned as per the modifications made to the Organizational Structure setup.
- Every dimension, pre-configured or custom, must have its own hierarchy (tree) view.
- A tree view only shows the values that belong to that one dimension.
- If a dimension is mapped to more than one parent dimension, every new value must be assigned to one value from each mapped parent before it can be saved.
- If a dimension has no mapped parent, the parent-assignment step is skipped.
- The combined organization tree is generated from the existing linking of dimensions; it does not require separate configuration.
- Renaming a dimension's label updates its name everywhere, including both its own tree view and the main organization structure tree.

***Feedback Note:** As per our discussion in the demo, the Org. Role setup is equivalent to Positions masters. The system should maintain Positions as the main master and not duplicate/separate out from the Org. Role Setup.

2. Pre-Configured Dimensions

The system already ships with a ready-made list of dimensions, shown below. Each one can be renamed, and new custom dimensions (such as Branch in these examples) can be added alongside them.




Figure 2. *The pre-configured dimension list inside the Dimension Management Module.*

This list is the starting point for configuration. The next section explains how these dimensions are connected to one another.

3. Dimension Mapping

Any dimension can be mapped to one parent dimension, or to more than one. This is what allows the same structure to fit different organizations without changing the system itself.




Figure 3. *Branch mapped to two independent parent dimensions — Division and Department.*

In the example above, Business Unit, Division, Department and Cost Center are independent, pre-configured dimensions. Branch is a custom dimension that has been mapped to both Division and Department, which means every Branch value must belong to one value from each. Business Unit and Cost Center are not mapped to Branch in this example, which is why they are shown on their own, with no arrows connecting them.

4. Functional Requirements

4.1 Each Master/Table Shows Its Own Tree View

Today, only Business Unit has a hierarchy (tree) view. This requirement gives every dimension the same kind of view, built only from that dimension's own values and its own parent-child levels.

- Each dimension opens its own tree screen, independent of any other dimension.
- Values are shown indented under their own parent value, with expand/collapse controls.
- The same columns and layout are reused for every dimension, so the screen stays familiar.

Three examples are shown below — Business Unit, Department, and Branch — each built only from that one dimension's own values.

There are two views to switch in-between:

4.1.1 Tree Hierarchy View of Dimensions





Figure 4. *Example hierarchy view for the Business Unit dimension.*

4.1.2 Flat List Structure

Flat list layout (no tree indentation) with Code, Name, Alias, and a new Status column (Active/Inactive badges), plus the tree/list toggle icons in the top-right corner.

EACH DIMENSION CAN ALSO BE VIEWED AS A LIST

a toggle in the top-right corner switches between Tree View and List View



4.1.3 Department Tree View




Figure 5. *Example hierarchy view for the Department dimension.*

4.1.3 Branch Tree View





Figure 6. *Example hierarchy view for the Branch dimension.*

4.1.4 Position Tree View



4.2 Adding a Value Must Follow the Mapping

When a dimension is mapped to one or more parent dimensions, adding a new value for it must ask which parent value(s) it belongs to. The value cannot be saved on its own; it must be anchored to its mapped parent(s) at the moment it is created.

The creation screen therefore works in two steps.




Figure 7. *Step 1 — the value's own details are entered first: Code, Branch Name (English), Branch Name (Arabic), and Alias.*


Figure 8. *Step 2 — the value is assigned to each mapped parent dimension, one group at a time.*

Because Branch is mapped to both Division and Department, step 2 lists both as separate, stacked groups — Division first, then Department — rather than side-by-side columns. Each group is numbered and shows only that parent dimension's own values with a checkbox to select one. This group-by-group layout is used instead of a fixed two-

column layout because a dimension may be mapped to more than two parents; a two-column layout would not scale, while an added group simply appears below the ones before it. A dimension mapped to only one parent would show only one group on this step; a dimension with no mapped parent would skip step 2 entirely.

5. Enquiry Report of Organization Structure (No Data Entry!)

In addition to each dimension's own tree, the system shows one combined tree which is an **"Enquiry Report"** that follows every mapping from top to bottom — Business Unit, Division, Department, Branch, Position, and Employee. This gives a single, end-to-end picture of the organization without any extra setup, because it is generated from the mappings already configured.






Figure 9. *The complete organization tree, generated from every dimension's mapping.*

6. Business Rules

Rule 1 — Every dimension, pre-configured or custom, must have its own hierarchy (tree) view.

Rule 2 — A tree view only shows the values that belong to that one dimension.

Rule 3 — If a dimension is mapped to more than one parent dimension, every new value must be assigned to one value from each mapped parent before it can be saved.

Rule 4 — If a dimension has no mapped parent, the parent-assignment step is skipped.

Rule 5 — The combined organization tree is generated from the existing linking of dimensions; it does not require separate configuration.

Rule 6 — Renaming a dimension's label updates its name everywhere, including both its own tree view and the main organization structure tree.