
Chapter 3: Processes





Chapter 3: Processes

- Process Concept
- Process Scheduling
- Operations on Processes
- Inter process Communication






Objectives


- To introduce the notion of a process -- a program in execution, which forms the basis of all computation
- To describe the various features of processes, including scheduling, creation and termination, and communication
- To explore interprocess communication using shared memory and message passing
- To describe communication in client-server systems





Process Concept

- An operating system executes a variety of programs:
 - Batch system jobs
 - Time-shared systems user programs or tasks
- Textbook uses the terms job and process almost interchangeably
- Process a program in execution; process execution must progress in sequential fashion
- Multiple parts
 - The program code, also called text section
 - Current activity including program counter, processor registers
 - Stack containing temporary data
 - Function parameters, return addresses, local variables
 - Data section containing global variables
 - Heap containing memory dynamically allocated during run time




Process Concept (Cont.)

- Program is passive entity stored on disk (executable file), process is active
 - Program becomes process when executable file loaded into memory
- Execution of program started via GUI mouse clicks, command line entry of its name, etc
- One program can be several processes
 - Consider multiple users executing the same program






Process in Memory






Process: program in execution



(currently used portion of the address space must be in memory)



Multiple Processes

one program counter

Process
A

what is happening physically


Process

В


Process

Process A Process C

Conceptual model of three different processes



one process executing at a time





Process State

- As a process executes, it changes state
 - new: The process is being created
 - running: Instructions are being executed
 - waiting: The process is waiting for some event to occur
 - ready: The process is waiting to be assigned to a processor
 - terminated: The process has finished execution








Diagram of Process State








Process Control Block (PCB)

Information associated with each process (also called task control block)

- Process state running, waiting, etc
- Program counter location of instruction to next execute
- CPU registers contents of all processcentric registers
- CPU scheduling information- priorities, scheduling queue pointers
- Memory-management information memory allocated to the process
- Accounting information CPU used, clock time elapsed since start, time limits
- I/O status information I/O devices allocated to process, list of open files

process state process number program counter registers memory limits list of open files





Process Control Block (PCB)

Process management

Registers

Program Counter (PC)

Program status word (PSW)

Stack pointer

Process state

Priority

Scheduling parameters

Process ID

Parent Process

Time when process started

CPU time used

Children's CPU time

Memory management

Pointer to text segment info Pointer to data segment info Pointer to stack segment info


File management

Root directory
Working directory
File descriptors
User ID
Group ID


.....more

a PCB of a process may contain this information






PCBs



Kernel mains a PCB for each process. They can be linked together in various queues.



CPU Switch From Process to Process








Process Queues and Scheduling







Process Scheduling

- Maximize CPU use, quickly switch processes onto CPU for time sharing
- Process scheduler selects among available processes for next execution on CPU
- Maintains scheduling queues of processes
 - Job queue set of all processes in the system
 - Ready queue set of all processes residing in main memory, ready and waiting to execute
 - Device queues set of processes waiting for an I/O device
 - Processes migrate among the various queues






Ready Queue And Various I/O Device Queues






Schedulers

- Long-term scheduler (or job scheduler) selects which processes should be brought into the ready queue
- Short-term scheduler (or CPU scheduler) selects which process should be executed next and allocates CPU






Addition of Medium Term Scheduling









Representation of Process Scheduling

Queueing diagram represents queues, resources, flows








Schedulers

- Short-term scheduler (or CPU scheduler) selects which process should be executed next and allocates CPU
 - Sometimes the only scheduler in a system
 - Short-term scheduler is invoked frequently (milliseconds) ⇒ (must be fast)
- Long-term scheduler (or job scheduler) selects which processes should be brought into the ready queue
 - Long-term scheduler is invoked infrequently (seconds, minutes) ⇒
 (may be slow)
 - The long-term scheduler controls the degree of multiprogramming
- Processes can be described as either:
 - I/O-bound process spends more time doing I/O than computations, many short CPU bursts
 - CPU-bound process spends more time doing computations; few very long CPU bursts

<u>CPU burst</u>: the execution of the program in CPU between two I/O requests (i.e. time period during which the process wants to continuously run in the CPU without making I/O) We may have a <u>short</u> or <u>long</u> CPU burst.



Context Switch

- When CPU switches to another process, the system must save the state of the old process and load the saved state for the new process via a context switch
- Context of a process represented in the PCB
- Context-switch time is overhead; the system does no useful work while switching
 - The more complex the OS and the PCB → the longer the context switch
- Time dependent on hardware support
 - Some hardware provides multiple sets of registers per CPU
 - → multiple contexts loaded at once






Operations on Processes


- System must provide mechanisms for:
 - process creation,
 - process termination,
 - and so on as detailed next






Process Creation

- Parent process create children processes, which, in turn create other processes, forming a tree of processes
- Generally, process identified and managed via a process identifier (pid)
- Resource sharing alternatives:
 - Parent and children share all resources
 - Children share subset of parent's resources
 - Parent and child share no resources
- Execution alternatives:
 - Parent and children execute concurrently
 - Parent waits until children terminate





A Tree of Processes in Linux








Process Creation (Cont)


Child's address space?

Child has a new address space.

Child's address space can contain:


- 1) the copy of the parent (at creation)
- 2) has a new program loaded into it






- UNIX examples
 - fork system call creates new process
 - exec system call used after a fork to replace the process' memory space with a new program





Process Creation (Cont.)

- Address space
 - Child duplicate of parent
 - Child has a program loaded into it
- UNIX examples
 - fork() system call creates new process
 - exec() system call used after a fork() to replace the process' memory space with a new program







C Program Forking Separate Process

```
#include <sys/types.h>
#include <stdio.h>
#include <unistd.h>
int main()
pid t pid;
   /* fork a child process */
   pid = fork();
   if (pid < 0) { /* error occurred */
      fprintf(stderr, "Fork Failed");
     return 1:
   else if (pid == 0) { /* child process */
      execlp("/bin/ls", "ls", NULL);
   else { /* parent process */
      /* parent will wait for the child to complete */
      wait (NULL);
      printf("Child Complete");
   return 0;
```

Silberschatz, Galvin and Gagne ©2013



Creating a Separate Process via Windows API

```
#include <stdio.h>
#include <windows.h>
int main(VOID)
STARTUPINFO si:
PROCESS_INFORMATION pi;
   /* allocate memory */
   ZeroMemory(&si, sizeof(si));
   si.cb = sizeof(si);
   ZeroMemory(&pi, sizeof(pi));
   /* create child process */
   if (!CreateProcess(NULL. /* use command line */
     "C:\\WINDOWS\\system32\\mspaint.exe", /* command */
    NULL, /* don't inherit process handle */
    NULL, /* don't inherit thread handle */
    FALSE. /* disable handle inheritance */
    0, /* no creation flags */
    NULL, /* use parent's environment block */
    NULL, /* use parent's existing directory */
     &si,
     &pi))
      fprintf(stderr, "Create Process Failed");
      return -1:
   /* parent will wait for the child to complete */
   WaitForSingleObject(pi.hProcess, INFINITE);
   printf("Child Complete");
   /* close handles */
   CloseHandle(pi.hProcess);
   CloseHandle(pi.hThread);
```






Process Termination

- Process executes last statement and then asks the operating system to delete it using the exit() system call.
 - Returns status data from child to parent (via wait())
 - Process' resources are deallocated by operating system
- Parent may terminate the execution of children processes using the abort() system call. Some reasons for doing so:
 - Child has exceeded allocated resources
 - Task assigned to child is no longer required
 - The parent is exiting and the operating systems does not allow a child to continue if its parent terminates





Process Termination

- Some operating systems do not allow child to exists if its parent has terminated. If a process terminates, then all its children must also be terminated.
 - cascading termination. All children, grandchildren, etc. are terminated.
 - The termination is initiated by the operating system.
- The parent process may wait for termination of a child process by using the wait() system call. The call returns status information and the pid of the terminated process

```
pid = wait(&status);
```

- If no parent waiting (did not invoke wait()) process is a zombie
- If parent terminated without invoking wait, process is an orphan






Multiprocess Architecture – Chrome Browser

- Many web browsers ran as single process (some still do)
 - If one web site causes trouble, entire browser can hang or crash
- Google Chrome Browser is multiprocess with 3 different types of processes:
 - Browser process manages user interface, disk and network I/O
 - Renderer process renders web pages, deals with HTML,
 Javascript. A new renderer created for each website opened
 - Runs in sandbox restricting disk and network I/O, minimizing effect of security exploits
 - Plug-in process for each type of plug-in






Interprocess Communication


- Processes within a system may be independent or cooperating
- Cooperating process can affect or be affected by other processes, including sharing data
- Reasons for cooperating processes:
 - Information sharing
 - Computation speedup
 - Modularity
 - Convenience
- Cooperating processes need interprocess communication (IPC)
- Two models of IPC
 - Shared memory
 - Message passing





Communications Models

(a) Message passing. (b) shared memory.





Cooperating Processes

- Independent process cannot affect or be affected by the execution of another process
- Cooperating process can affect or be affected by the execution of another process
- Advantages of process cooperation
 - Information sharing
 - Computation speed-up
 - Modularity
 - Convenience






Producer-Consumer Problem

- Paradigm for cooperating processes, producer process produces information that is consumed by a consumer process
 - unbounded-buffer places no practical limit on the size of the buffer
 - bounded-buffer assumes that there is a fixed buffer size





Bounded-Buffer – Shared-Memory Solution

Shared data


```
#define BUFFER_SIZE 10

typedef struct {
    . . .
} item;


item buffer[BUFFER_SIZE];
int in = 0;
int out = 0;
```


Solution is correct, but can only use BUFFER_SIZE-1 elements






Bounded-Buffer – Producer





Bounded Buffer – Consumer






Interprocess Communication – Shared Memory

- An area of memory shared among the processes that wish to communicate
- The communication is under the control of the users processes not the operating system.
- Major issues is to provide mechanism that will allow the user processes to synchronize their actions when they access shared memory.
- Synchronization is discussed in great details in Chapter 5.






Interprocess Communication – Message Passing

- Mechanism for processes to communicate and to synchronize their actions
- Message system processes communicate with each other without resorting to shared variables
- IPC facility provides two operations:
 - send(message)
 - receive(message)
- The message size is either fixed or variable






Message Passing (Cont.)

- If processes P and Q wish to communicate, they need to:
 - Establish a communication link between them
 - Exchange messages via send/receive
- Implementation issues:
 - How are links established?
 - Can a link be associated with more than two processes?
 - How many links can there be between every pair of communicating processes?
 - What is the capacity of a link?
 - Is the size of a message that the link can accommodate fixed or variable?
 - Is a link unidirectional or bi-directional?





Message Passing (Cont.)

- Implementation of communication link
 - Physical:
 - Shared memory
 - Hardware bus
 - Network
 - Logical:
 - Direct or indirect
 - Synchronous or asynchronous
 - Automatic or explicit buffering



End of Chapter 3

