# BTCPay Server: one command to set up plugin auto-installs

For the system administrator of the BTCPay Server host. Takes about 2 minutes. BTCPay restarts once, for a few seconds, so pick a quiet moment.

Aviv sends you, together with this file, one line of text that starts with `ssh-ed25519`. You paste it into the command in step 2. Nothing else is needed; no GitHub account, no other downloads.

## Step 1

Log in to the BTCPay Server host over SSH as a user that can use sudo.

## Step 2

Run this one command. Replace the part between the quotes with the line you received, keeping the quotes:

```
curl -fsSL https://raw.githubusercontent.com/mokokolalala/btcpayserver-plugin-fiatramp/master/deploy/setup-server.sh | sudo bash -s -- "ssh-ed25519 AAAA...paste the whole line here..."
```

It prints what it does. The last lines look like this:

```
info: BTCPayServer.Plugins.PluginManager: Running plugin BTCPayServer.Plugins.FiatRamp - 0.2.2.0
[install-plugin] OK

==> DONE. Send this back:
   host: 203.0.113.10   (use the public address if this one is private)
   ssh port: 22
   user: btcpaydeploy
   setup OK
```

## Step 3

Copy those last four lines and send them to Aviv. Done.

## If it stops with an error

- Send Aviv the whole output; that is enough to sort it out.
- The most likely one: `BTCPay container 'generated_btcpayserver_1' not found`. Run `docker ps` to see the real name and run the command again with `BTCPAY_CONTAINER=<that name>` inserted right after `sudo` , i.e. `sudo BTCPAY_CONTAINER=<name> bash -s -- "..."`.
- Running the command again is safe; it redoes everything from the start.

## What this did

- Created a user `btcpaydeploy` that can do exactly one thing: install this plugin into BTCPay (the same thing BTCPay's own "Upload plugin" button does) and restart the BTCPay container. It has no sudo and no shell access; its SSH key is locked to that one script.
- From now on, new versions arrive from Aviv's build system over SSH, without anyone logging in. Each install restarts BTCPay for a few seconds.
- The host needs to accept SSH from the internet on the port above (the build runners have changing IP addresses). If SSH is restricted to an allowlist, tell Aviv.
- To switch it off later: `sudo userdel -r btcpaydeploy`. The plugin itself is removed in BTCPay under Server Settings > Plugins.

> Nothing in this setup needs access to GitHub afterwards; the files are pushed to the server, not pulled by it.