

Wireless and Cellular Networks



Tecnologie e Servizi di Rete
Computer Network Technologies and Services



1859

Mario Baldi, Claudio Casetti, Guido Marchetto, Fulvio Valenza

*part of the slides adapted from material by Carla Fabiana Chiasserini, Jim Kurose, Keith Ross



Copyright Notice

- This set of transparencies, hereinafter referred to as slides, is protected by copyright laws and provisions of International Treaties. The title and copyright regarding the slides (including, but not limited to, each and every image, photography, animation, video, audio, music and text) are property of the authors specified on page 1.
- The slides may be reproduced and used freely by research institutes, schools and Universities for non-profit, institutional purposes. In such cases, no authorization is requested.
- Any total or partial use or reproduction (including, but not limited to, reproduction on magnetic media, computer networks, and printed reproduction) is forbidden, unless explicitly authorized by the authors by means of written license.
- Information included in these slides is deemed as accurate at the date of publication. Such information is supplied for merely educational purposes and may not be used in designing systems, products, networks, etc. In any case, these slides are subject to changes without any previous notice. The authors do not assume any responsibility for the contents of these slides (including, but not limited to, accuracy, completeness, enforceability, updated-ness of information hereinafter provided).
- In any case, accordance with information hereinafter included must not be declared.
- In any case, this copyright notice must never be removed and must be reported even in partial uses.




Wireless and Mobile Networks: context


- more wireless (mobile) phone subscribers than fixed (wired) phone subscribers (10-to-1 in 2019)!
- more mobile-broadband-connected devices than fixed-broadband-connected devices (5-1 in 2019)!
 - 4G/5G cellular networks now embracing Internet protocol stack, including SDN
- two important (but different) challenges
 - **wireless**: communication over wireless link
 - **mobility**: handling the mobile user who changes point of attachment to network




Elements of a wireless network




Elements of a wireless network



Elements of a wireless network



Elements of a wireless network




wireless link



- typically used to connect mobile(s) to base station, also used as backbone link
- multiple access protocol coordinates link access
- various transmission rates and distances, frequency bands




Elements of a wireless network



infrastructure mode

- base station connects mobiles into wired network
- handoff: mobile changes base station providing connection into wired network

Elements of a wireless network



ad hoc mode

- no base stations
- nodes can only transmit to other nodes within link coverage
- nodes organize themselves into a network: route among themselves


Wireless link characteristics (1)

- *important* differences from wired link
 - **decreased signal strength:** radio signal attenuates as it propagates through matter (path loss)
 - **interference from other sources:** wireless network frequencies (e.g., 2.4 GHz) shared by many devices (e.g., WiFi, cellular, motors): interference
 - **multipath propagation:** radio signal reflects off objects ground, arriving at destination at slightly different times
- make communication across (even a point to point) wireless link much more “difficult”



Wireless link characteristics (2)

- SNR: signal-to-noise ratio
 - larger SNR – easier to extract signal from noise (a “good thing”)
- SNR versus BER tradeoffs
 - given physical layer: increase power $\rightarrow$ increase SNR $\rightarrow$ decrease BER
 - given SNR: choose physical layer that meets BER requirement, giving highest throughput
 - SNR may change with mobility: dynamically adapt physical layer (modulation technique, rate)




- QAM256 (8 Mbps)
- - - QAM16 (4 Mbps)
- BPSK (1 Mbps)




Wireless link characteristics (3)

Multiple wireless senders, receivers create additional problems (beyond multiple access):



Hidden terminal problem

- B, A hear each other
- B, C hear each other
- A, C can not hear each other means A, C unaware of their interference at B



Signal attenuation:

- B, A hear each other
- B, C hear each other
- A, C can not hear each other interfering at B



Cellular Networks




Definitions

- Cellular network

- Network where a geographical area is covered by tassellation through adjacent or overlapping areas, called *cells*
- User terminals can move form one cell to another without communication disruption (*handover*)




Cellular coverage – In theory...




- Base station at the center of the cell, equipped with isotropic antenna
- Cells: regular exagonal shape

Cellular coverage – In theory...



- 3 directional antennas with a 120° opening, located at one extreme of each cell
- 3 co-located antennas

Cellular coverage – In practice...




Cells


- Cells are not regular hexagon and do not have the same size
- Cell shape and size are determined by:
 - Power emitted at the antenna
 - Antenna height
 - Antenna gain
 - Morphology of the geographical area (in urban areas: buildings height and shape)
 - Fading (multiple copies of the signal)
 - Propagation conditions
- Macrocells vs microcells
 - Different size, depending on the specific needs




Example: macrocell




Macrocell: received power levels



Example: microcell



Microcell: received power levels



Channel access

- *Multiple user channel access*: wireless channel is a common resource that has to be shared among multiple users
- Possible techniques to share resources:
 - FDMA (Frequency Division Multiple Access)
 - TDMA (Time Division Multiple Access)
 - CDMA (Code Division Multiple Access)
 - SDMA (Space Division Multiple Access)



FDMA with frequency reuse


- Given the limited number of available resources, we need to:
 - Ensure coverage
 - Serve a high number of users

Reuse the same frequencies at
different locations

- We define as cluster the set of G adjacent cells that use all the frequencies available to one




3-Cell cluster




- Green, pink and light blue cells use disjoint sets of channels
- Cells of the same color are called “co-channel” cells

7-cell cluster




Fixing G and varying the cell size R



Given a cluster size, the *system capacity* increases as the cell radius (i.e., cell size) decreases




Fixing G and varying the cell size R



- Given G :
 - The smaller the R , the larger the capacity
 - The smaller the R , the larger the number of antennas needed to ensure same total coverage



Fixing R and varying the cluster size G



- Given R (i.e., given the cell size):
 - The larger the G , the smaller the number of channels per cell, the lower the system capacity
 - The larger the G , the larger *the distance between co-channel cells*, the less the interference, the better the quality



Frequency reuse

- Some techniques reduce interference and increase capacity
 - Splitting
 - Sectoring
 - Tilting
 - Creating femtocells




Splitting

- Split large cells into a set of small cells
- Coexistence between
 - Microcells: small cells in highly populated areas with high traffic density (large cities). Transmit power at the base station ≈ 3 W
 - Macrocells: large cells in areas with low traffic density (rural areas). Transmit power at the base station ≈ 20 -60 W



Splitting




- Each large cell is replaced by a group of small cells

Cell shaping


- It is possible to use directional antennas to have cells with an ad-hoc size and shape
- It is possible to create multi-layer cell coverage (umbrella coverage)
- Microcells that follow the user as she moves



Cell shaping




Cell shaping



Power control

- Needed to reduce:
 - Interference
 - Energy consumption
- Open/ closed control



Power control strategies

- In uplink:
 - Closed loop power control
 - Open loop power control
 - Outer loop power control
- In downlink:
 - Downlink power control



Power control: open loop (uplink)

- The user terminal controls itself
- 2-phase mechanism:
 - User measures the quality of the signal received from the BS (downlink signal)
 - The user employs an algorithm to set the transmit power to be used in uplink so that the estimated SINR is above a given threshold
- “Open Loop” since there is no feedback
- Not very accurate as uplink and downlink transmissions typically occur on different channels
 - Other techniques more accurate but more complex (e.g., closed loop)




Frequency allocation

- Fixed Channel Allocation (FCA)
 - Based on the concept of cluster
 - Frequencies are assigned in a static way
 - Frequency plan is changed only rarely to improve performance and adapt to slow variations in user traffic
- Dynamic Channel Allocation (DCA)
 - Resources assigned to cells by a central controller when needed
 - Frequency plan changes over time to adapt to the system status
- Hybrid Channel allocation Scheme (HCS)
 - One portion is statically allocated (FCA)
 - One portion is dynamically allocated (DCA)



Network architecture



Basic procedures: Registration

- It allows a mobile terminal:
 - to connect with the network
 - to identify and authenticate itself
- It is performed:
 - When a terminal is switched on and has to associate with the network
 - Whenever a user wants to access a service (es. start a call)
 - Periodically



Basic procedures: Mobility management

- Mobility support characterizes cellular networks
- We need procedures to handle mobility
 - Roaming
 - Location updating
 - Paging
 - Handover




Roaming

- The user position has to be *traceable* even if she moves over the network area
- The system has to store the user position in a database to locate users whenever needed
- To store user positions, the network area is divided into *location areas (LAs)*, i.e., groups of cells



Roaming

- Each location area has an ID: *location area identifier (LAI)*



Location updating

- Procedure through which the user position is updated
- A control channel is periodically broadcasted in each cell of an LA
- When the mobile terminal receives an LAI different from the one previously stored, the user starts a location updating procedure in order to update her position in the database



Paging

- Procedure through which the system notifies a mobile terminal about an incoming call/data delivery
- The system broadcasts a paging message within the LA where the user is



Handover

- Procedure that enables the transfer of an active connection from one cell to another, while the mobile terminal moves over the network area
- Complex procedure that poses constraints on the network architecture, protocols and signaling




Handover classification

- Intra vs. Inter Cell
 - It indicates whether the handover is between frequencies within the same cell or different cells
- Soft vs. Hard
 - It indicates whether during handover both radio channels are active (soft) or only one at the time is active (hard)
- MT vs. BS initiated
 - It indicates whether the first control message to start a handover is sent by the mobile terminal (MT initiated) or by the BS (BS initiated), i.e., which entity performs measurements to understand where and when a handover has to be executed
- Backward vs. Forward
 - It indicates whether handover signaling occurs via the origin BS (backward) or the destination BS (forward)



Cellular network evolution



1G: First generation

- *Analog technology*
- FDMA
- Voice traffic only
- Low service quality
- Low efficiency in frequency reuse, and low network capacity
- TACS:
 - 900 MHz
 - Channel width=25 kHz
 - In Italy, service stopped (TIM) on 31/12/05



2G: Second generation

- Main change: *from analog to digital*
- Advantages:
 - Integration of different services (e.g., SMS)
 - Cryptography
 - Advanced voice coding to reduce bandwidth requirements
- FDMA/TDMA in Europe, CDMA in the U.S.
- Frequency bands: 850, 900, 1800, 1900 MHz
- Active networks:
 - IS-95 in USA
 - GSM in Europe
 - PDC in Japan



2.5G: Extended second generation

- GPRS/EDGE in Europe, IS-95B in USA
- Introduction of data service
 - Packet switched
 - 170 kb/s in GPRS, 384 kb/s in EDGE
 - Traffic-based instead of time-based billing



3G: Third generation

- Improvement of data service (multimedia services)
- CDMA
- Exploit spatial diversity (simultaneous transmissions with multiple BSs) to improve quality
- High data rate (up to 2 Mb/s)
- Handover between different networks (2G-3G) is possible (vertical handover)
- Networks:
 - UMTS (Universal Mobile Telecommunication System) in Europe and Japan
 - CDMA2000 (IS-95C) in USA



3.5G: Extended third generation

- Evolution of UMTS
 - HSPA (High-Speed Packet Access), composed of HSDPA and HSUPA (downlink/uplink)
 - HSPA+ (Evolved High-Speed Packet Access)
- Mainly changes at the UMTS physical layer
- Data rates up to:
 - 56 Mb/s DL
 - 22 Mb/s UL



4G: Fourth generation

- Known as LTE (Long Term Evolution)
- Data rate up to 250 Mb/s
- Uses MIMO and high-performance modulations
- All – IP
- Initially only data service (now also voice with *VoLTE*)
- Standardization
 - “4G” has to satisfy ITU requirements for “IMT Advanced” (high spectrum efficiency, minimum data rate of 1 Gb/s for fixed users and 100 Mb/s for mobile users)
 - LTE does not meet such constraints yet, the right name would be “3.9 G”
 - LTE-Advanced (standard since 2011) meets such requirements



5G: Fifth generation

- Integrates different technology over the wireless segment (mainly, further evolution of LTE-A, WiFi and mmWave communications)
 - NR = New Radio is the “official” name of the transmission technology
- Exploit the SDN (*Software Defined Networking*) paradigm for network control and operation
- Exploits the NFV (*Network Function Virtualization*) paradigm for service implementation



GSM: the 2nd Generation



1859



GSM in today's mobile networks

- Operators made huge investments in the '90s to create the GSM infrastructure
- Although a 30+ year-old technology, it is still viable for voice communication
- Using GSM today for phone calls frees up "precious" frequencies that can be used for data in 4G and 5G




Services offered by GSM

- Voice full rate (13 kbit/s), half rate (6.5 kbit/s)
- SMS
- Supplementary services (call forward, recall on busy tone,....)



GSM network architecture



Mobile Station (MS)

- User Equipment
- several types depending on the application, e.g.:
 - Mobile phones
 - Mobile devices (e.g., laptop, tablet, etc.)
 - Antennas on vehicles
- Different transmitted power at the antenna
 - Up to 2W for mobile phones
 - Up to 8W for mobile devices
 - Up to 20W for car antennas



Subscriber Identity Module (SIM)

- MS is “hardware” only, to connect to the network it needs a SIM



- SIM=Smart card with processor and memory (to be inserted in the SIM reader)
- SIM stores (encrypted) user information: phone no., accessible services, security parameters, ecc.

Base Station Subsystem (BSS)

- Base Station (BS)

- Base Transceiver Station (BTS)

- Physical interface in charge of transmission and reception
 - Point of access for the MT
 - Unlike other signal sources (e.g. radio, TV), BTSs transmit signal only towards users that are active
 - Up to 32 FDM channels per BTS (half uplink, half downlink)


- Base Station Controller (BSC)

- Resource control on the radio interface: BSCs and BTSs communicate over a wired link
 - A BSC controls a high number of BTSs: from *tens* to *hundreds*
 - Typically, BSCs are collocated with one MSC, instead of being located near the BTSs
 - BSC main functions:
 - Voice transcoding 13 kb/s ↔ 64 kb/s
 - Paging
 - Radio resource control: dynamic frequency assignment to BTSs
 - Signal quality measurement
 - Management of handover between BTSs controlled by the same BSC




Network and Switching Subsystem (NSS)

- Main functions:
 - Call handling
 - Service support
 - Mobility support
 - Authentication



Network and Switching Subsystem (NSS)

- Main functions:
 - Call handling
 - Service support
 - Mobility support
 - Authentication



Home Location Register


Database storing:

- Permanent user data: id, enabled services, security parameters
- Dynamic data to handle user mobility (e.g., VLR identifier)



Network and Switching Subsystem (NSS)

- Main functions:
 - Call handling
 - Service support
 - Mobility support
 - Authentication



Visitor Location Register


Database storing:

- Information related to MTs currently in the area controlled by the MSC:
IDs, on/off status, LAI, routing information, security



Network and Switching Subsystem (NSS)

- Main functions:
 - Call handling
 - Service support
 - Mobility support
 - Authentication




Authentication Center

Authentication based on challenge & response protocol
Generations of encryption keys for over-the-air communication


Network and Switching Subsystem (NSS)

- Main functions:
 - Call handling
 - Service support
 - Mobility support
 - Authentication



GSM frequencies (Europe)

- Allocated frequencies: 850, 900, 1800, 1900 MHz
- FDD (Frequency Division Duplex) system
 - different frequencies for UL and DL




GSM physical channels

- Channel access: FDMA/TDMA
 - Frequency spectrum divided into FDM channels, each 200 kHz wide
 - Each FDM channel is divided into TDM frames
 - Each TDM frame is divided into 8 slots
- $\Rightarrow$ *Frequency + time slot = physical channel*
- Transmission organized into “bursts”, i.e., blocks of data that are transmitted on a physical channel
 - Bursts are similar to packets...But it is still circuit switching!
 - Transmission speed = 271 kbit/s




Channel access – Summary of FDM/TDM schema

- Slot time = 0.577 ms
 - 1 slot carries 156.25 bits (i.e., 0.577×271 kbps)
- Each time slot carries 1 transmission burst
- Slots are grouped into TDM frames, of 8 slots each
 - Frame = 4.615 ms




Channel access – GSM frame

- Circuit-switched network
 - Each call @full rate (13kb/s) is assigned 1 slot per frame in UL and 1 slot per frame in DL
- Each MT transmits on a carrier for one time slot, i.e., one burst of data, and remains silent during the other 7 slots
- Frames on UL and DL are synchronized on a time slot basis and shifted by 3 slots
- Separating UL/DL transmissions in frequency and time allows the use of one transceiver only




Channel access – Timing advance

- Non-zero propagation times
 - Bursts transmitted by MTs might arrive at the BTS when the slot is already finished
 - Possible collisions
- Solution: *timing advance*
 - Transmission at the MT starts *before* the real timeslot beginning



“Regular” burst structure



GSM Logical channels

- Physical channels
 - Combination of timeslot and carrier
 - 8 physical channels per carrier: timeslots 0 - 7
- Logical channels
 - Carry useful information, i.e., specify “*what*” is transmitted
 - Mapped into physical channels according to proper criteria
- Two types of logical channels
 - *Control channels*
 - Carry control information (related to user or network)
 - *Traffic channels*
 - Carry user information



Control channels

- Network signaling
 - Cell parameters
 - Synchronization
 - Receiver tuning
- User signaling
 - Call control
 - Signal quality control (measurement delivery)



LTE: the 4th Generation



1859




LTE

- First release by 3GPP as Release 8, known as LTE-Advanced since Rel. 10
- Speeds up to 300 Mb/s DL - 50 Mb/s UL with modulations up to 64 QAM
- 10-ms data latency
- Replaces WCDMA with OFDMA (DL) and SC-FDM (UL)
- Leverages high-order MIMO
- Up to 20 MHz channels
- Scalable frequency bands from 1.4MHz to 20 MHz
- “All-IP” HSDPA core network

	Release 8 LTE	
	Downlink	Uplink
Peak data rate	300 Mbps (4x4 MIMO) 150 Mbps (2x2 MIMO)	75 Mbps (1x2 SIMO)
Bandwidth	Up to 20 MHz	Up to 20 MHz
Peak Spectrum efficiency	≈ 16.3 bit/s/Hz	≈ 4.3 bit/s/Hz (1x2 SIMO)
Average Spectrum efficiency [bit/s/Hz/cell]	1.69 (2x2 MIMO) 1.87 (4x2 MIMO) 2.67 (4x4 MIMO)	0.74 (1x2 SIMO)
Latency	Data plane : 10 ms (round trip delay) Control plane : 100 ms (idle to active state)	



Usage of Frequency Bands



2600 MHz

Used to **maximize capacity**

1800 MHz

Band with **high capacity**,
and **limited interference**


800 MHz

Band with **high coverage**
and interference



LTE Terminology

- **Downlink (DL):** data going from the network to the user device
- **Uplink (UL):** data going from the user device to the network
- **User plane:** all the operations related to the transport of user data in DL and UL
- **Control plane:** all operations related to the set-up, control and maintenance of communications between user and network




ACCESS STRATUM




NON ACCESS STRATUM

LTE Architecture



- **Radio Access Network (RAN):** it includes all the devices involved with the direct interaction with user devices
 - In LTE, it is called the E-UTRAN
- **Core Network (CN):** it includes all the devices responsible for the transport of data to/from the Internet or toward other user devices
 - In LTE, it is called EPC

LTE Architecture



EPC – Design Principles

- Clean-slate design
- Packet-switched transport for traffic belonging to all QoS classes including conversational, streaming, real-time, non-real-time, and background
- Radio resource management for: end-to-end QoS, transport for higher layers, load sharing/balancing, policy management/enforcement across different radio access technologies
- Integration with existing 3GPP 2G and 3G networks




EPC – Functions

- **Network access control**, including network selection, authentication, authorization, admission control, policy and charging enforcement, and lawful interception
- Packet **routing** and transfer
- **Security**, including ciphering, integrity protection, and network interface physical link protection
- **Mobility management** to keep track of the current location of the UE
- **Radio resource management** to assign, reassign, and release radio resources taking into account single and multi-cell aspects
- **Network management** to support operation and maintenance
- IP networking functions, connections of eNodeBs, E-UTRAN sharing, emergency session support, among others




EPC - Components

- Mobility Management Entity (MME)
 - Resides in the Control Plane
 - Supports user equipment context, identity, authentication, and authorization
 - Mainly perform Non Access Stratum procedures, consisting of two main groups
 - Functions related to *bearer* management
 - *Bearer can be seen as a logical communication tunnel*
 - Functions related to connection and mobility management




EPC - Components

- Serving Gateway (S-GW)
 - Resides in the User Plane
 - Receives and sends packets between the eNodeB and the core network
 - Perform packet routing and forwarding within EPC
 - Anchor point for intra LTE-mobility
 - Lawful intercept




EPC - Components

- Packet Data Network Gateway (P-GW)
 - Resides in the User Plane
 - Connects the EPC with external networks/Internet
 - Basically, a router that performs UE IP assignment, per user packet filtering and NAT services
 - Anchor point for mobility with non-3GPP access network and visited networks
 - Lawful intercept




EPC - Components

- Home Subscriber Server (HSS)
 - Database of user-related and subscriber-related information
 - Used for authentication (together with MME) and authorization
 - Similar to HLR in GSM architecture




The LTE Bearers

- Think of a *bearer* as a pipe (tunnel) that carries data from the UE to other elements of the LTE architecture (e.g., the P-GW)
- one *default bearer* is established to the P-GW whenever the UE is activated
- the UE can establish other *dedicated bearers* to other networks, based on quality-of-service (QoS) requirements
 - e.g., viewing a streaming video over the Internet can be done over a dedicated bearer
 - dedicated bearers can use a bandwidth guarantee (a guaranteed bit rate, or GBR) tunnel




The LTE Bearers

- The bearer is a concatenated tunnel consisting of three portions established in the following order:
 - **The S5 bearer** — connects the Serving Gateway (S-GW) to the P-GW. (The tunnel can extend from P-GW to the Internet -- called **S8** bearer in this case)
 - **The S1 bearer** — connects the eNodeB with the S-GW. Handover establishes a new S1 bearer for end-to-end connectivity.
 - **The radio bearer** — connects the UE to the eNodeB. This bearer follows the mobile user under the direction of the MME as the radio network performs handovers when the user moves from one cell to another



E-UTRAN

- Mainly consists of the eNodeB
- An interface X2 interconnects between eNodeB
 - Consists of two types : X2 control and X2 user
- Main functions
 - Radio resource management: related to the radio bearer such as radio bearer control, radio mobility control, scheduling and dynamic allocation of radio resource at uplink and downlink
 - Header compression
 - Security
 - Connectivity to EPC




LTE Data Plane/Control Plane



1859




LTE data plane control plane separation



control plane

- new protocols for mobility management, security, authentication




data plane

- new protocols at link, physical layers
- extensive use of tunneling to facilitate mobility



LTE data plane protocol stack: first hop




LTE radio access network:

- **downstream channel:** FDM, TDM within frequency channel (OFDM - orthogonal frequency division multiplexing)
 - “orthogonal”: minimal interference between channels
- **upstream:** FDM, TDM similar to OFDM
- each active mobile device is allocated two or more 0.5-ms time slots over 12 frequencies
 - scheduling algorithm not standardized – up to operator
 - 100's Mbps per device possible



LTE data plane protocol stack: first hop



LTE link layer protocols:

- Packet Data Convergence: header compression, encryption
- Radio Link Control (RLC) Protocol: fragmentation/reassembly, reliable data transfer
- Medium Access: requesting, use of radio transmission slots



LTE data plane protocol stack: Physical Channels

- Transmitted bits fit into the frame structure according to predefined subdivisions called **Physical Channels**
- Each channel conveys specific information related to: user data, TX/RX parameters, eNB identity, network control etc., as well as to the format of the channel itself (i.e., FDD or TDD)
- Each physical channel is mapped into a portion of the LTE subframe
- Physical channels are divided into Downlink and Uplink Channels
 - Each U/D channel is further divided into Data and Control



LTE Physical Downlink Channels

- Physical Broadcast Channel (PBCH)
 - MIB (Master Information Block) and RACH parameters (Radio Access Channel)
- Physical Control Format Indicator Channel (PCFICH)
 - Details on PDCCH format (e.g., number of symbols used)
- Physical Hybrid ARQ Indicator Channel (PHICH)
 - Ack/Nack to uplink frame transmission
- Physical Downlink Control Channel (PDCCH)
 - Downlink resource scheduling
 - Uplink power control instructions
 - Uplink resource grant
 - Indication for paging or system information
- Physical Downlink Shared Channel (PDSCH)
 - User data and SIB (System Information Block) for cell information

control

data



LTE Physical Uplink Channels (control)

- Physical Random Access Channel (PRACH)
 - It carries the random access preamble a UE sends to access the network in non-synchronized mode
 - used to allow the UE to synchronize timing with the eNodeB
- Physical Uplink Control Channel (PUCCH)
 - Signaling includes HARQ ACK/NACK, channel quality indicators (CQI), MIMO feedback and scheduling requests for uplink transmission




LTE Physical Uplink Channels (data)

- Physical Uplink Shared Channel (PUSCH)
 - It carries user data
 - The uplink scheduling TTI is 1 ms; it is possible to 'bundle' a group of 4 TTIs to improve performance at cell edge and reduce higher-layer protocol overhead



LTE data plane protocol stack: packet core




tunneling:

- mobile datagram encapsulated using GPRS Tunneling Protocol (GTP), sent inside UDP datagram to S-GW
- S-GW re-tunnels datagrams to P-GW
- supporting mobility: only tunneling endpoints change when mobile user moves




LTE data plane: associating with a BS



- ① BS broadcasts primary synch signal every 5 ms on all frequencies
 - BSs from multiple carriers may be broadcasting synch signals
- ② mobile finds a primary synch signal, then locates 2nd synch signal on this freq.
 - mobile then finds info broadcast by BS: channel bandwidth, configurations; BS's cellular carrier info
 - mobile may get info from multiple base stations, multiple cellular networks
- ③ mobile selects which BS to associate with (e.g., preference for home carrier)
- ④ more steps still needed to authenticate, establish state, set up data plane



LTE mobiles: sleep modes



as in WiFi, Bluetooth: LTE mobile may put radio to “sleep” to conserve battery:

- **light sleep**: after 100's msec of inactivity
 - wake up periodically (100's msec) to check for downstream transmissions
- **deep sleep**: after 5-10 secs of inactivity
 - mobile may change cells while deep sleeping – need to re-establish association



Mobility



Contacting a mobile friend:

Consider friend frequently changing locations, how do you find him/her?

- search all phone books?
- expect her to let you know where he/she is?


- call his/her parents?
- Facebook!

The importance of having a “home”:

- a definitive source of information about you
- a place where people can find out where you are



Home network, visited network: 4G/5G



home network:


- (paid) service plan with cellular provider, e.g., TIM, Orange
- home network HSS stores identify & services info

visited network:


- any network other than your home network
- service agreement with other networks: to provide access to visiting mobile



Home network, visited network: generic



Registration: home needs to know where you are!




end result:


- visited mobility manager knows about mobile
- home HSS knows location of mobile



Mobility in 4G networks: major mobility tasks



Configuring LTE control-plane elements




- Mobile communicates with local MME via BS control-plane channel
- MME uses mobile's IMSI info to contact mobile's home HSS
 - retrieve authentication, encryption, network service information
 - home HSS knows mobile now resident in visited network
- BS, mobile select parameters for BS-mobile data-plane radio channel



Configuring data-plane tunnels for mobile


■ Solution 1: Home-Routed Roaming

- The visited network provides radio and transport network resources
 - actual data session is anchored back at the home PGW
- ### ■ S-GW to home P-GW tunnel:
- UE connects to SGW and MME in visited network, which routes traffic back to the home PGW using the **S8 bearer**.
- ### ■ Home network manages user authentication, data billing, and IP address allocation
- user's data session and policies are consistent with their home subscription.




Configuring data-plane tunnels for mobile

- Solution 2: **Local Breakout**
- S-GW to Visited P-GW tunnel: The UE's data traffic exits *locally* within the visited network
- Visited network handles both the control and user planes, including IP address allocation and data traffic, through own PGW and **S5 bearer**
 - useful for applications requiring low latency or for offloading data traffic to reduce network load on home operator
 - Home network might lose some control over QoS policies or billing



Handover between BSs in same cellular network



① current (source) BS selects target BS, sends Handover Request message to target BS

② target BS pre-allocates radio time slots, responds with HR ACK with info for mobile


③ source BS informs mobile of new BS

- mobile can now send via new BS - handover looks complete to mobile

④ source BS stops sending datagrams to mobile, instead forwards to new BS (who forwards to mobile over radio channel)



Handover between BSs in same cellular network



- ⑤ target BS informs MME that it is new BS for mobile
- MME instructs S-GW to change S1 bearer endpoint to be (new) target BS

- ⑥ target BS ACKs back to source BS: handover complete, source BS can release resources

- ⑦ mobile's datagrams now flow through new tunnel from target BS to S-GW

5G Networks



5G objectives

- 5G will meet the requirements of a highly mobile, fully connected society.
 - proliferation of connected objects and devices
 - wide range of new services and associated business models
 - automation in various industry sectors and vertical markets (e.g. energy, e-health, smart city, connected cars, industrial manufacturing, etc.).
 - more pervasive human centric applications, e.g., virtual and augmented reality augmentation, 4k video streaming, etc.
- 5G networks will support the coexistence of
 - human-centric
 - machine type applications
- 5G networks will have to support very diverse functional and KPI/performance requirements



5G Key Requirement

Unlike previous generations of mobile networks, 5G will require not only improved networking solutions but also a sophisticated integration of massive computing and storage infrastructures.




5G Ecosystem

- Operators will have to deploy **orchestrator functions** that will allocate appropriate computing and logical network resources to services
- These logical networks, called **network slices**, will contain specialized networking and computing functions that meet the desired performance of the service providers
- 5G networks will support **cross-domain orchestration** of services and resources over multiple administrative domains (multiple operators) allowing flexible sharing schemes
- The implementation of these schemes will also require interworking among operators in the network function layer as well (e.g., setting up SDN rules).



5G use cases

- Enhanced Mobile Broadband (eMBB)
- Massive Machine Type Communication (mMTC)
- Ultra-Reliable Low-Latency Communication (URLLC)



5G technologies in the Radio Access



Advanced waveforms

- Alternatives to pure OFDM such as RBF-OFDM, FBMC, GFDM, and UPMC



Advanced MIMO

- Both co-located and distributed architectures are envisaged, with co-located massive MIMO particularly appealing to high frequency bands



Millimeter Wave

- Millimeter Wave spectrum (20-80GHz) offers large chunks (up to 2GHz) of contiguous bandwidth, for ultra-high throughput and low latency scenarios.



5G technologies in the Core Network



Software Defined Networking

- SDN is an approach to networking in which routing control is *centralized* and decoupled from the physical infrastructure (data plane), which is *distributed*.



Network Function Virtualization

- NFV moves network services (firewall, load balancing, access control) from hardware to software, creating *virtual building blocks* that can be easily connected (NFV chaining)




SDN/NFV Orchestration

- Aka. the new *network operating system*: it manages function lifecycle, resources, policies and it provides system analytics



5G Architecture



- **Radio Access Network (RAN):** it includes all the devices involved with the direct interaction with user devices
 - In 5G, base stations are called gNodeB
- **Edge Network (MEC):** it hosts computing and storage elements for local services
- **Core Network (CN):** it includes all the devices responsible for the transport of data to/from the Internet or toward other user devices

Main differences between 4G and 5G networks

■ Nomenclature

- Radio Interface E-UTRA → New Radio (NR)
- Radio access network: E-UTRAN → 5G-RAN
- Core Network: EPC → 5GC

■ Data and Control Plane split

- LTE → have a bit mixed CP and UP functions between different network nodes;
- In 5G → full CP/UP split

■ Brand-new functionalities

- network slicing implying different configurations of RAN
- new QoS framework with flows instead of end-to-end bearers
- new approach to 5GC using Service Based Architecture (SBA) concept



5G CORE NETWORK




1859



5G Service Based Architecture (SBA)

AMF=Access & mobility
Management Function


5G evolution of MME



5G Service Based Architecture (SBA)

SMF=Session Management Function

5G evolution of control plane of SGW and PGW




5G Service Based Architecture (SBA)

UPF=User Plane Function

5G evolution of data plane

Performs traffic steering



5G EDGE NETWORK




1859




Multiaccess Edge Computing

- Edge Network infrastructure providing IT service environment and cloud-computing capabilities at the edge of the mobile network, in close proximity to mobile subscribers
- Standardization begun in 2014 («Mobile Edge Computing»)
 - First set of specifications published in 2017
- Expected benefits:
 - ultra-low latency
 - high bandwidth
 - real-time access to radio network
 - contextual information
 - location awareness
 - flexible and extendable framework for services




MEC Architecture



MEC host contains the MEC platform and a virtualization infrastructure which provides compute, storage, and network resources for the MEC applications.


MEC Architecture



The **MEC platform** offers an environment where the MEC applications can discover, advertise, consume and offer MEC services

MEC Architecture

MEC applications are running as virtual machines (VM) on top of the virtualization infrastructure provided by the MEC host, and can interact with the MEC platform to consume and provide MEC services



5G RADIO ACCESS NETWORK




1859



5G New Radio - Overview

- Flexible slot-based framework
 - Variable number of slots per subframe
 - Transmissions can start in any part of the slot
- Different subcarrier spacing (“numerology”): shorter slots for higher spacing
- Supports slot aggregation for data-heavy transmissions



Source: Qualcomm




5G New Radio – Frequency bands

	<1GHz	3GHz	4GHz	5GHz	24-28GHz	37-40GHz	64-71GHz	>95GHz
	600MHz (2x35MHz)	2.5/2.6GHz (B41/n41)	3.45-3.55GHz 3.55-3.7GHz 3.7-4.2GHz	5.9-7.1GHz	24.25-24.45GHz 24.75-25.25GHz 27.5-28.35GHz	37-37.6GHz 37.6-40GHz 47.2-48.2GHz	64-71GHz	>95GHz
	600MHz (2x35MHz)		3.55-3.7 GHz		26.5-27.5GHz 27.5-28.35GHz	37-37.6GHz 37.6-40GHz	64-71GHz	
	700MHz (2x30 MHz)		3.4-3.8GHz	5.9-6.4GHz	24.5-27.5GHz			
	700MHz (2x30 MHz)		3.4-3.8GHz		26GHz			
	700MHz (2x30 MHz)		3.4-3.8GHz		26GHz			
	700MHz (2x30 MHz)		3.46-3.8GHz		26GHz			
	700MHz (2x30 MHz)		3.6-3.8GHz		26.5-27.5GHz			
	700MHz	2.5/2.6GHz (B41/n41)	3.3-3.6GHz	4.8-5GHz	24.75-27.5GHz	37-42.5GHz		
	700/800MHz	2.3-2.39GHz	3.4-3.42GHz 3.42-3.7GHz 3.7-4.0GHz	5.9-7.1GHz	25.7-26.5GHz 26.5-28.9GHz 28.9-29.5GHz	37.5-38.7GHz		
			3.6-4.1GHz	4.5-4.9GHz	26.6-27GHz 27-29.5GHz	39-43.5GHz		
	700MHz		3.3-3.6GHz		24.25-27.5GHz 27.5-29.5GHz	37-43.5GHz		
			3.4-3.7GHz		24.25-27.5GHz	39GHz		


5G New Radio – Massive MIMO

- MIMO (Multiple Input Multiple Output): both the base station and UE have multiple antenna ports and antennas, and multiple data streams are transmitted simultaneously to the UE using same time/frequency resources, doubling (2×2 MIMO), or quadrupling (4×4 MIMO) the peak throughput of a single user
- Massive MIMO (mMIMO) is a system where the number of antennas exceeds the number of users
- Although not part of the first release, 5G NR will support distributed-MIMO, where a user can receive different parts of the same data stream from multiple sites.



5G New Radio - Beamforming

- Beamforming is the manipulation of the signals fed to and received from complex antennas to create beams in space that focus power in a particular direction
- LTE applies it only to data, 5G also to control
- At high frequencies beamforming will mostly be used to increase range by energy focus,
- At the mid and low bands below 6GHz, where attenuation is less of a problem, beamforming will be a key part of MIMO



Wireless LANs




IEEE 802.11 Wireless LAN

IEEE 802.11 standard	Year	Max data rate	Range	Frequency
802.11b	1999	11 Mbps	30 m	2.4 Ghz
802.11g	2003	54 Mbps	30m	2.4 Ghz
802.11n (WiFi 4)	2009	600	70m	2.4, 5 Ghz
802.11ac (WiFi 5)	2013	3.47Gpbs	70m	5 Ghz
802.11ax (WiFi 6)	2021	14 Gbps	70m	2.4, 5 Ghz
802.11af	2014	35 – 560 Mbps	1 Km	unused TV bands (54-790 MHz)
802.11ah	2017	347Mbps	1 Km	900 Mhz

- all use CSMA/CA for multiple access, and have base-station and ad-hoc network versions



802.11 LAN architecture




- wireless host communicates with base station
 - base station = access point (AP)
- Basic Service Set (BSS) (aka “cell”) in infrastructure mode contains:
 - wireless hosts
 - access point (AP): base station
 - ad hoc mode: hosts only

802.11: Channels, association

- spectrum divided into channels at different frequencies
 - AP admin chooses frequency for AP
 - interference possible: channel can be same as that chosen by neighboring AP!
- arriving host: must **associate** with an AP
 - scans channels, listening for *beacon frames* containing AP's name (SSID) and MAC address
 - selects AP to associate with
 - then may perform authentication
 - then typically run DHCP to get IP address in AP's subnet




802.11: passive/active scanning



passive scanning:

- (1) beacon frames sent from APs
- (2) association Request frame sent: H1 to selected AP
- (3) association Response frame sent from selected AP to H1




active scanning:

- (1) Probe Request frame broadcast from H1
- (2) Probe Response frames sent from APs
- (3) Association Request frame sent: H1 to selected AP
- (4) Association Response frame sent from selected AP to H1

IEEE 802.11: multiple access

- avoid collisions: 2⁺ nodes transmitting at same time
- 802.11: CSMA - sense before transmitting
 - don't collide with detected ongoing transmission by another node
- 802.11: *no* collision detection!
 - difficult to sense collisions: high transmitting signal, weak received signal due to fading
 - can't sense all collisions in any case: hidden terminal, fading
 - goal: *avoid collisions*: CSMA/CollisionAvoidance



IEEE 802.11 MAC Protocol: CSMA/CA

802.11 sender

1 if **sense channel idle** for DIFS then transmit entire frame (no CD)

2 if **sense channel busy** then

start random backoff time

timer counts down while channel idle


transmit when timer expires

if no ACK, increase random backoff interval, repeat 2

802.11 receiver

if **frame received OK**

return ACK after SIFS (ACK needed due to hidden terminal problem)




Avoiding collisions (more)

idea: sender “reserves” channel use for data frames using small reservation packets


- sender first transmits *small* request-to-send (RTS) packet to BS using CSMA
 - RTSs may still collide with each other (but they’re short)
- BS broadcasts clear-to-send CTS in response to RTS
- CTS heard by all nodes
 - sender transmits data frame
 - other stations defer transmissions



Collision Avoidance: RTS-CTS exchange



802.11 frame: addressing



Address 1: MAC address of wireless host or AP to receive this frame


Address 2: MAC address of wireless host or AP transmitting this frame

Address 3: MAC address of router interface to which AP is attached


Address 4: used only in ad hoc mode



802.11 frame: addressing




802.11 frame: addressing



802.11: mobility within same subnet


- H1 remains in same IP subnet: IP address can remain same
- switch: which AP is associated with H1?
- self-learning; switch will see frame from H1 and “remember” which switch port can be used to reach H1



802.11: advanced capabilities

Rate adaptation

- base station, mobile dynamically change transmission rate (physical layer modulation technique) as mobile moves, SNR varies
 1. SNR decreases, BER increase as node moves away from base station
 2. When BER becomes too high, switch to lower transmission rate but with lower BER



802.11: advanced capabilities

power management

- node-to-AP: “I am going to sleep until next beacon frame”
 - AP knows not to transmit frames to this node
 - node wakes up before next beacon frame
- beacon frame: contains list of mobiles with AP-to-mobile frames waiting to be sent
 - node will stay awake if AP-to-mobile frames to be sent; otherwise sleep again until next beacon frame

