431 Class 21

thomase love. github. io/431

2020-11-10

Today's Agenda

- Type I and Type II Error
- Power and Sample Size Considerations
 - When Comparing Two Means
 - With power.t.test for balanced designs (independent & paired)
 - With the pwr package for unbalanced designs
 - When Comparing 3+ Means with ANOVA
 - With power.anova.test for balanced designs
 - When Comparing Proportions using Independent Samples
 - With power.prop.test for balanced designs
 - With the pwr package for unbalanced designs

Today's Setup

```
knitr::opts_chunk$set(comment = NA)
library(pwr) # new today
```

No data today, so no tidyverse!

Types of Errors

In a hypothesis testing structure, we have a null hypothesis H_0 and an alternative hypothesis H_A .

- α is the probability of rejecting H_0 when H_0 is true.
 - So 1α , the confidence level, is the probability of retaining H_0 when that's the right thing to do.
 - Rejection of H_0 when H_0 is true is referred to as a **Type I error**.
 - ullet So α is the probability of Type I error, associated with our scenario.
- β is the probability of retaining H_0 when H_A is true.
 - So 1β , the power, is the probability of rejecting H_0 when that's the right thing to do.
 - Retaining H_0 when H_A is actually true is referred to as a **Type II error**.
 - So β is the probability of Type II error, associated with our scenario.

Error Types, Confidence, Power, α and β

- α is the probability of rejecting H_0 when H_0 is true.
 - So 1α , the confidence level, is the probability of retaining H_0 when that's the right thing to do.
- β is the probability of retaining H_0 when H_A is true.
 - So $1-\beta$, the power, is the probability of rejecting H_0 when that's the right thing to do.

_	<i>H_A</i> is True	H ₀ is True
Test Rejects H ₀	Correct Decision (1 - β)	Type I Error (α)
Test Retains H_0	Type II Error (β)	Correct Decision (1 - α)

Most common (not necessarily sensible) approach

- Pre-specify the significance level α to be 0.05.
- Pre-specify the power (1β) to be 0.80.

How Big A Sample Size Do I need?

- What is the budget?
- What are you trying to compare?
- What is the study design?
- How big an effect size do you expect (hope) to see?
- What was that budget again?
- OK, tell me the maximum allowable rates of Type I and Type II error that you want to control for. Or, if you like, tell me the confidence level and power you want to have.
- And what sort of statistical inference do you want to plan for?

Comparing Two Means (with Paired or Independent Samples)

Using power.t.test

What will we need to specify to the machine?

Measure	Paired Samples	Independent Samples
type =	"paired"	"two.sample"
n	# of paired diffs	# in each sample
δ	true mean of diffs	true diff in means
s = sd	true SD of diffs	true SD, either group
$\alpha = sig.level$	max. Type I error rate	Same as paired.
$1-\beta=power$	power to detect effect δ	Same as paired.

Specify alt = "greater" or alt = "less" for a 1-sided comparison.

 Note that in independent samples, we're assuming a balanced design, and it's common to use as our estimate of the pooled SD the larger of the two sample SDs we observe.

Sample Size & Power: Pooled t Test

For an independent-samples t test, with a balanced design $(n_1 = n_2)$ then R can estimate any one of the following elements, given the other four, using the power.t.test function, for a one-sided or two-sided t test.

- $n = n_1 = n_2$ = the sample size in each of the two groups being compared
- ullet $\delta=$ delta = the true difference in means between the two groups
- s = sd = the true standard deviation of the individual values in each group (assumed to be constant, since we assume equal population variances)
- $\alpha = \text{sig.level} = \text{the significance level for the comparison (maximum acceptable risk of Type I error)}$
- \bullet 1 $\beta=$ power = the power of the t test to detect the effect of size δ

If you want a two-sample power calculation for an unbalanced design, you will need to use a different package and function in R.

A Small Example: Studying Satiety

- I want to compare people eating meal A to people eating meal B in terms of impact on satiety, as measured on a 0-100 scale. I'm interested in a two-sided test, since I don't know which will be better in advance.
- I can afford to enroll 160 people (or, more specifically, prepare 160 meals) in the study.
- I expect that a difference that's important will be about 10 points on the satiety scale.
 - Perhaps this is because I saw a 17 point difference in a pilot study.
- I don't know the standard deviation, but the whole range (0-100) gets used, so I'll estimate the SD conservatively with (range/4) or 25.

The Key Questions

- How many should eat meal A and how many meal B to maximize my power to detect such a difference?
- And how much power will I have if I use a 90% confidence level?

Satiety Example: Power

- n = the sample size in each of the two groups being compared
- ullet $\delta=$ delta = the true difference in means between the two groups
- s = sd = the true standard deviation of the individual values in each group (assumed to be constant, since we assume equal population variances)
- $\alpha=$ sig.level = the significance level for the comparison (maximum acceptable risk of Type I error)
- \bullet 1 $\beta=$ power = the power of the t test to detect the effect of size δ

What do I know?

Satiety: Assumption Set 1

Let's go with:

- Independent Samples, so test type = "two.sample"
- Total sample size I can afford = 160, so a balanced design gives 80 in each group.
- ullet $\delta = \text{smallest difference I want to be sure I detect} = 10 points.$
- standard deviation of satiety scores is unknown, but we'll guess 25 (since range/4 = 25).
- we'll use alpha = .10 (90% confidence) and a two-sided test.

Satiety Example Calculation

Two-sample t test power calculation

```
n = 80
delta = 10
sd = 25
sig.level = 0.1
power = 0.8089716
alternative = two.sided
```

NOTE: n is number in *each* group

What happens if you change something else?

If we start with n = 80, δ = 10, sd = 25, α = 0.10, that yields power 0.809.

To increase the power to 0.90, what can we do?

- 1 Increase the sample size, *n* to 108 in each group
 - If n = 108 instead, power is now 0.90
- ② or Increase the minimum detectable effect size δ to 11.7
- 3 or Reduce the standard deviation to 21.5
- **1** or Increase α (willingness to tolerate Type I error) to 0.215
 - So confidence level would 79.5% instead of 90%.
- or Switch from independent to matched/paired samples.
 - Even if we leave sd alone, 55 matched differences yields 90% power

What if we use a paired samples design instead?

- Paired samples, so test type = "paired"
- \bullet Total = 160 meals, so that's n = 80 paired differences (each subject eats A and B, in a random order)
- standard deviation of *differences* in satiety will be smaller than 25; let's be very conservative and say 20.
- \bullet δ remains 10 points, two-sided test with 90% confidence.

So, we want...

Any guesses?

Satiety: Paired Samples Estimated Power (Results)

Paired t test power calculation

```
n = 80
delta = 10
sd = 20
sig.level = 0.1
power = 0.9973528
alternative = two.sided
```

NOTE: n is number of *pairs*, sd is std.dev. of *differences*

Note: If sd = 25 with paired samples, power = 0.971.

What if 32 people ate both meals (different times?)

Impact on standard deviation? Let's say $\sigma_d = 15...$

Paired t test power calculation

```
n = 32
delta = 10
    sd = 15
sig.level = 0.1
    power = 0.979437
alternative = two.sided
```

NOTE: n is number of *pairs*, sd is std.dev. of *differences*

Power for an unbalanced design

- If you have independent samples, the most powerful design for a given total sample size will always be a balanced design.
- If you must use an unbalanced design in setting up a sample size calculation, you typically have meaningful information about the cost of gathering samples in each group, and this may help you estimate the impact of Type I and Type II errors so you can trade them off appropriately.

The pwr package function to do this is pwr.t2n.test.

- Must specify both n_1 and n_2
- Instead of specifying δ and sd separately, specify their ratio, d.

Satiety Example with an Unbalanced Design?

If we can only get 40 people in the tougher group to fill, how many people would we need in the easier group to get at least 80% power to detect a difference of 10 points, assuming a standard deviation of 25, and using 90% confidence.

Remember that we met this standard with 80 people in each group using a balanced design. . .

So we have $n_1=$ 40, d = 10/25 (δ / sd), sig.level $\alpha=$ 0.1 and power (1 - β) = 0.8

• What's your guess, before I show you the answer, as to the number of people I'll need in the easier group?

Satiety Example, Unbalanced Design

t test power calculation

```
n1 = 40

n2 = 1174.101

d = 0.4

sig.level = 0.1

power = 0.8

alternative = two.sided
```

- OK. So use balanced samples when planning a study.
- What's next?

Designing an ANOVA?

Power/Sample Size for designing an ANOVA study

Is there a power.anova.test approach in R?

Sure.

- groups = number of groups
- n = number of observations per group
- between.var = between-group variance
- within.var = within-group variance
- sig.level = α (significance level)
- power = 1β

Specify five, and the computer will calculate the sixth. This does require a **balanced design**.

So, what do we use for between.var and within.var?

Determining between.var and within.var

- If you have prior knowledge of what you expect the true group means to be, then you can take their variance to get the between.var value.
- The within.var value is the within-group variance. To get that, realize that ANOVA assumes that each group will have the same standard deviation of outcome values. Square that "within-group standard deviation" you estimate to obtain the within-group variance.

Powering an ANOVA study, Setup

PI wants to plan a study:

- to compare four groups, and she wants to be sure she can detect a difference if the means turn out to be any more different than they would be if they were 560, 585, 610 and 625.
- ullet using a balanced design, 90% power and lpha=0.05
- where she thinks that the standard deviation in each group of the scores will be 80.

power.anova.test needs five of these six things:

- groups = number of groups
- n = number of observations per group
- between.var = between-group variance
- within.var = within-group variance
- sig.level = α (significance level)
- power = 1β

Powering an ANOVA study, Results

Balanced one-way analysis of variance power calculation

```
groups = 4

n = 38.01195

between.var = 816.6667

within.var = 6400

sig.level = 0.05

power = 0.9
```

NOTE: n is number in each group

Is there a power and sample size approach for unbalanced ANOVA?

Not a straightforward one, and not within the pwr package, no.

• This is a good time for us to mention that the number one place where Ph.D. statisticians get involved in grant proposals is when people realize they need a non-standard power calculation.

Comparing Proportions (using Independent Samples)

Tuberculosis Prevalence Among IV Drug Users

Suppose we are investigating factors affecting tuberculosis prevalence among intravenous drug users.

We collect the following information:

- Among 97 individuals who admit to sharing needles,
 - 24 (24.7%) had a positive tuberculin skin test result.
- Among 161 drug users who deny sharing needles,
 - 28 (17.4%) had a positive test result.

What does the 2x2 table look like?

Tuberculosis Prevalence Among IV Drug Users

Among 97 individuals who admit to sharing needles, 24 (24.7%) had a positive tuberculin skin test result; among 161 drug users who deny sharing needles, 28 (17.4%) had a positive test result.

The 2x2 Table is...

- rows describe needle sharing, columns describe TB test result
- row 1 people who share needles: 24 TB+, and 97-24 = 73 TB-
- ullet row 2 people who don't share: 28 TB+ and 161-28 = 133 TB-

twobytwo (with Bayesian Augmentation)

To start, we'll test the null hypothesis that the population proportions of intravenous drug users who have a positive tuberculin skin test result are identical for those who share needles and those who do not.

```
H_0: \pi_{share} = \pi_{donotshare}
H_A: \pi_{share} \neq \pi_{donotshare}
```

We'll use the Bayesian augmentation.

Two-by-Two Table Result

Outcome : TB test+

Comparing : Sharing vs. Not Sharing

```
TB test+ TB test- P(TB test+) 95% conf. int. Sharing 25 74 0.2525 0.1767 0.3471 Not Sharing 29 134 0.1779 0.1265 0.2443
```

95% conf. interval

Relative Risk: 1.4194 0.8844 2.2779

Sample Odds Ratio: 1.5610 0.8520 2.8603

Conditional MLE Odds Ratio: 1.5582 0.8105 2.9844

Probability difference: 0.0746 -0.0254 0.1814

Exact P-value: 0.1588 Asymptotic P-value: 0.1495

What conclusions should we draw?

Designing a New TB Study

PI:

- OK. That's a nice pilot.
- We saw $p_{nonshare} = 0.18$ and $p_{share} = 0.25$ after your augmentation.
- Help me design a new study.
 - This time, let's have as many needle-sharers as non-sharers.
 - We should have 90% power to detect a difference as large as what we saw in the pilot, or larger, so a difference of 7 percentage points.
 - We'll use a two-sided test, and $\alpha = 0.05$, of course.

What sample size would be required to accomplish these aims?

How power.prop.test works

power.prop.test works much like the power.t.test we saw for means.

Again, we specify 4 of the following 5 elements of the comparison, and ${\sf R}$ calculates the fifth.

- The sample size (interpreted as the # in each group, so half the total sample size)
- The true probability in group 1
- The true probability in group 2
- The significance level (α)
- The power (1β)

The big weakness with the power.prop.test tool is that it doesn't allow you to work with unbalanced designs.

Using power.prop.test for Balanced Designs

To find the sample size for a two-sample comparison of proportions using a balanced design:

- we will use a two-sided test, with $\alpha = .05$, and power = .90,
- we estimate that non-sharers have probability .18 of positive tests,
- and we will try to detect a difference between this group and the needle sharers, who we estimate will have a probability of .25

Finding the required sample size in R

Any guess as to needed sample size?

Results: power.prop.test for Balanced Design

Two-sample comparison of proportions power calculation n=721.7534 p1=0.18, p2=0.25 sig.level = 0.05, power = 0.9, alternative = two.sided NOTE: n is number in *each* group

So, we'd need at least 722 non-sharing subjects, and 722 more who share needles to accomplish the aims of the study, or a total of 1444 subjects.

Another Scenario

Suppose we can get 400 sharing and 400 non-sharing subjects. How much power would we have to detect a difference in the proportion of positive skin test results between the two groups that was identical to the data above or larger, using a *one-sided* test, with $\alpha=.10$?

```
Two-sample comparison of proportions power calculation n=400, p1=0.18, p2=0.25 sig.level = 0.1, power = 0.8712338 alternative = one.sided NOTE: n is number in *each* group
```

We would have just over 87% power to detect such an effect.

Using the pwr package to assess sample size for Unbalanced Designs

The pwr.2p2n.test function in the pwr package can help assess the power of a test to determine a particular effect size using an unbalanced design, where n_1 is not equal to n_2 .

As before, we specify four of the following five elements of the comparison, and R calculates the fifth.

- n1 = The sample size in group 1
- n2 = The sample size in group 2
- sig.level = The significance level (α)
- power = The power (1β)
- h =the effect size h, which can be calculated separately in R based on the two proportions being compared: p_1 and p_2 .

Calculating the Effect Size h

To calculate the effect size for a given set of proportions, use ES.h(p1, p2) which is available in the pwr package.

For instance, in our comparison, we have the following effect size.

$$ES.h(p1 = .18, p2 = .25)$$

[1] -0.1708995

Using pwr.2p2n.test in R

Suppose we can have 700 samples in group 1 (the not sharing group) but only 400 in group 2 (the group of users who share needles).

How much power would we have to detect this same difference (p1 = .18, p2 = .25) with a 5% significance level in a two-sided test?

R Command to find the resulting power

```
pwr::pwr.2p2n.test(h = ES.h(p1 = .18, p2 = .25),

n1 = 700, n2 = 400, sig.level = 0.05)
```

Results of using pwr.2p2n.test

difference of proportion power calculation for binomial distribution (arcsine transformation)

```
h = 0.1708995, n1 = 700, n2 = 400
sig.level = 0.05, power = 0.7783562
alternative = two.sided
NOTE: different sample sizes
```

We will have just under 78% power under these circumstances.

Comparison to Balanced Design

How does this compare to the results with a balanced design using 1100 drug users in total, i.e. with 550 patients in each group?

which yields a power estimate of 0.809. Or we could instead have used...

which yields an estimated power of 0.808.

Each approach uses approximations, and slightly different ones, so it's not surprising that the answers are similar, but not identical.

What haven't I included here?

- 1 Some people will drop out.
- What am I going to do about missing data?
- What if I want to do my comparison while adjusting for covariates?

How Big A Sample Size Do I need?

- What is the budget?
- 2 What are you trying to compare?
- What is the study design?
- How big an effect size do you expect (hope) to see?
- What was that budget again?
- OK, tell me the maximum allowable rates of Type I and Type II error that you want to control for. Or, if you like, tell me the confidence level and power you want to have.
- And what sort of statistical inference do you want to plan for?