

Docker for SLAM

Saturday, April 18, 2020 9:48 AM

image ≈ class

Container ≈ class instance

Install Docker for Ubuntu.

Go to Dockerhub, find paopaorobot, docker pull the relevant one.

Can use 16.04, 18.04... and kinetic, melodic...

docker image ls : Shows image in local.

docker run -it (image name) : creates a container for the image.

In the container, use cat /etc/issue to check the version.

exit : exit from container.

docker run -it -p 5900:5900 (image name) : Use vnc to visualize,

5900 is the port name.

open vnc viewer, enter :5900, then can see the desktop.

If use the ros version:

docker run -it -p 5900:5900 paopaorobot/ros-vnc .

then we can run roscore and rviz in vnc.

docker run -it -p 5900:5900 -e RESOLUTION=1920x1200 paopaorobot/ubuntu-xfce-vnc .

docker run -it -p 2222:22 paopaorobot/ubuntu-openbox-vnc : this enables the ssh.

Open another terminal, use

ssh -o 'UserKnownHostsFile=/dev/null' root@localhost -p 2222

2222 is port name, this means do not save key.

docker run -it -p 2222:22 -e SSHPW=abc123 paopaorobot/ubuntu-openbox-vnc .

SSHPW sets the password for SSH.

docker run -it -p 5900:5900 -p 2222:22 -v /.../test:/home/test test:paopao

then we can use both ssh and vnc.

Demo:

docker pull paopaorobot/dvo

docker run -it -p 5900:5900 -v local data path: container data path paopaorobot/dvo
we use -V to mount data in container ↑

in vnc, use

ros launch dvo_benchmark benchmark.launch dataset:=/root/data

docker file:

FROM paopaorobot/ros-vnc:fuerte base on which image

COPY . /root/fuerte_workspace/dvo/

RUN rosdep init ~ /fuerte_workspace /opt/ros/fuerte \

&& cd ~ /fuerte_workspace \

&& rosdep set -y ~ /fuerte_workspace/dvo \

&& /bin/bash -l -c "source ~ /fuerte_workspace/setup.bash && \

cd ~ /fuerte_workspace && \

ros make dvo_core dvo_ros dvo_benchmark" newer ros uses catkin make

RUN /bin/bash -c "echo 'source ~ /fuerte_workspace/setup.bash' >> ~ / .bashrc" Source Setup

Alternatively, can create a container, e.g paopaorobot/ros-vnc:fuerte, and setup the dvo, then save the container as an image.

How to use Docker for development:

IDE is VS code.

1. Connect to Docker:

use remote-containers plugin.

docker run -it paopaorobot/ubuntu-xfce-vnc:latest

-v path to code; code in container

We need to mount the code to the container

In VS code, use remote-containers : attach to running container.

then select the container currently running.

To open the code, open the path in container in VS.

Since we have the environment, we can have the auto completion now.

2. Use SSH.

In VS, use remote-ssh.

add -P 2222:22 to docker run.

In VS, use remote-ssh, container to host, add new SSH host

then enter:

ssh -o 'UserKnownHostsFile=/dev/null' root@localhost -P 2222

How to create the image:

Dockerfile:

FROM ubuntu:latest base on a ubuntu official image

ENV HOME /root

ENV DEBIAN_FRONTEND noninteractive

RUN apt-get update \

&& apt-get install -y supervisor \} for ssh

openssh-server vim-tiny \}

openbox \ openbox

X11vnc xvfb \ vnc, Xvfb is virtual display

firefox \

rngen \ password generation for ssh.

&& apt-get autoremove \ } delete extra stuff.

&& apt-get autoclean \ } to decrease the docker size.

&& rm -rf /var/lib/apt/lists/* also the fewer the command like

WORKDIR /root FROM ENV, ADD... the better

ADD startup.sh ./ \} copy these to root

ADD supervisord.conf ./ \}

EXPOSE 5900 \} open ports

EXPOSE 22 \}

ENTRYPOINT [./startup.sh] \} exe. this script when start

Startup.sh:

mkdir -p /var/run/sshd

sed -i '/PermitRootLogin/c PermitRootLogin yes' /etc/ssh/sshd_config allow root login

if [! \$SSHPW]; then

SSHPW='`pwgen -c -n -l 12`'

fi

echo "root:\$SSHPW" | chpasswd

echo "ssh login password:\$SSHPW"

if [-n "\$RESOLUTION"]; then

sed -i "s/1024x768/\$RESOLUTION/" /root/supervisord.conf \} set resolution.

fi

/usr/bin/supervisord -c /root/supervisord.conf \} start vnc, display, etc.

/bin/bash, start shell

Supervisor can manage several processes, edit the supervisord.conf to set.

If we want to use Cuda, we need to use nvidia-docker

-P 2222:22 sets the port. manually we can use -P to auto-assign port.

then use

docker port (container id) 22 (or 5900)