

Configuring

[Configuring](#) / [Preparing to use workflows](#) / Replacing your control files with the sample files

Replacing your control files with the sample files

When you install a new version of RICOH ProcessDirector, the installer automatically adds new sample control files to the `/aiw/aiw1/samples` directory and copies them to your control files directory, `/aiw/aiw1/control_files`. It does not overwrite any of your customized control files in `/aiw/aiw1/control_files`. You can use the `copyConfigurationFiles` script to install the default control files or to overwrite your customized control files.

Replacing your control files requires Perl to run. Before replacing your control files, make sure a Perl interpreter is installed.

To replace your control files with the sample files:

1. Log in to the primary computer as the RICOH ProcessDirector system user (`aiw1` is the default).
2. On the command line, enter this command:

```
/opt/infoprint/ippd/bin/copyConfigurationFiles.pl
```

You can add these optional parameters to the `copyConfigurationFiles` command:

```
[-r [-b]] [-w forceReplaceFile] [samplesDirectoryconfigurationFilesDirectory] [[-o differencesOutputFile] [-c]] [-v] [-help]
```

-r

The script overwrites existing files in the `/aiw/aiw1/control_files` directory.

-b

The script backs up each file it replaces. The backup files are called `replaced_file.bak`. It does not back up files unless they are being replaced by a different version of that file.

-w forceReplaceFile

The script overwrites a specific set of files. List the file paths to overwrite in the `forceReplaceFile` file.

samplesDirectory

The directory where the sample files are located. The default is `/aiw/aiw1/samples`.

configurationFilesDirectory

The directory where the control files are located. The default is `/aiw/aiw1/control_files`.

-o differencesOutputFile

The script writes any file names where there are different versions of a file in the samples and control_files directories. The different version file names are written to the `differencesOutputFile` file.

-c

The script compares the files in the `/aiw/aiw1/samples` and `/aiw/aiw1/control_files` directories and prints a list of which files are in both directories but have different content. Running the script with this parameter does not do the normal copying and replacing.

-v

The script displays additional file information while copying files.

-help

The script displays help and syntax information.

New versions of RICOH ProcessDirector might add new functions that require updated control files. To move your customized content from the old control files to the new control files:

1. Generate a list of which files have new versions. Enter this command:

```
copyConfigurationFiles.pl -o /tmp/differencesOutputFile
```

2. Copy the new control files. Enter this command:

```
copyConfigurationFiles.pl -r -b -w /tmp/differencesOutputFile
```

Specifying the `-b` causes the script to back up files before overwriting them.

3. Copy your customized content from the `replaced_file.bak` backup files to the corresponding control file.

★ Important:

- We recommend using the **Migration Assistant** when upgrading to a different computer to copy objects from one system to another. For additional information see [Using the Migration Assistant](#).

Parent topic: [Preparing to use workflows](#)