

Configuring

[Configuring](#) / [Defining input devices](#) / Using supplied input devices

Using supplied input devices

RICOH ProcessDirector provides several predefined input devices. If your print environment is simple and does not require many input devices, you can modify the properties of the predefined input devices and use them in your environment.

To modify and use a supplied input device:

1. Click the **Administration** tab.
2. In the left pane, click **Devices** \Rightarrow **Input Devices**.
3. Select the input device that you want to modify.
4. Click **Properties**.
5. On all the tabs, change the required and optional properties that need to be adjusted to match your environment. Each input device must have a unique path for its **Folder location** and **Staging location** properties.

 **Note:**

- If you have the AFP Support feature installed and submit jobs to Download input devices:
 - More than one Download input device can use the same port number, but you can only enable one of the input devices with the common port number at any time.
 - When Download for z/OS is running in multiple data set mode with Exit 15, each Download input device can receive jobs from only one Download for z/OS functional subsystem application (FSA).

6. Determine how you want the input device to assign the workflow for each job.

When using **SubmitInputFiles** as the submit step for the input device, you can select one of these:

- Set the **Child workflow initialization step** property to **Not set** and set the **Child workflow** property to the name of an existing workflow to assign the same workflow to every job that this input device processes.
- Set the **Child workflow initialization step** property to **SetJobTypeFromRules** and use the **Child workflow parsing rules** property to specify the name of the control file that can set the workflow from a value of an option of the print command.
RICOH ProcessDirector provides a sample control file that is used to set the workflow: `receive_lpd_pdf_jobtype.cfg`. The AFP Support feature provides these sample control files that are used to set the workflow: `receive_jcl_jobtype.cfg` and `receive_lpd_jobtype.cfg`. The sample control files are installed in the `/aiw/aiwl/samples/rules/` directory. You can copy a sample control file to the `/aiw/aiwl/control_files/rules/` directory and modify it to meet your needs, then update the value of the **Child workflow parsing rules** property to point to your file.
- Set the **Child workflow initialization step** property to **SetJobTypeFromFile** and use the **Child workflow pattern** property to specify the string that RICOH ProcessDirector should look for in the input file name and use as the workflow name. If you use this method, you must make sure that a workflow with the corresponding name exists.

7. Click **OK**.

8. To use the modified input device, select it and click **Enable**, then select it again and click **Connect**.

Parent topic: [Defining input devices](#)