

# Weizenbier

Wheat malt and European hops create the recipe for this easy-drinking summertime classic. Light-bodied with a smooth finish, our Weizenbier features an authentic dry wheat yeast.

 IBUs: 6 - 10
 OG: 1.047 - 1.051
 FG: 1.011 - 1.015

 ABV: 4.5% - 4.75%
 Difficulty: Easy
 Color: Deep Gold

#### **Contents**

- Ingredients
   Priming Sugar
- Grain Bag(s) Bottle Caps

Brewing Procedures

Hops may vary due to availability.

### Glossary

OG

Original Gravity

SG

Specific Gravity

FG

Final Gravity

CO2 Carbon Dioxide DME

Dried Malt Extract

**LME** 

Liquid Malt Extract

**IBU** 

International Bittering Units (Tinseth)

**ABV** 

Alcohol by Volume

### **Ingredients**

**FERMENTABLES** 

6.6 lb. Wheat LME (2 cans)

HOPS

1 oz. AU Helga

.5 oz. German Hallertau

YEAST

1 Sachet

# **Recommended Procedures**

NOTE: This recipe incorporates late malt additions to ensure the lightest color possible for this beer style. Refer to BREW DAY SCHEDULE.

BREW DAY (DATE 12,13)

#### 1. READ

Read all of the recommended procedures before you begin.

#### 2. SANITIZE

Thoroughly clean and sanitize ALL brewing equipment and utensils that will come in contact with any ingredients, wort or beer with a certified sanitizer, e.g., Star San or IO Star.

#### 3. START BOIL

Pour 2.5 gallons of clean water into your brew pot and begin to heat<sup>1</sup>. Bring your water to a gentle, rolling boil. Add **ONLY one of the 3 lb. cans of Wheat LME** to the boiling water<sup>2</sup>. Continuously stir the extract into the wort as it returns to a gentle, rolling boil<sup>3</sup>. Your water is now wort.

#### 4. FOLLOW SCHEDULE<sup>6</sup>

As directed on the BREW DAY SCHEDULE (right), slowly sprinkle the hops into the boiling wort. Be careful not to let the wort boil over the pot. Using the provided BREW DAY SCHEDULE, note the time the hops were added to help keep your brew on schedule. The BREW DAY SCHEDULE will guide you through the remaining addition of ingredients. Continue the gentle, rolling boil until the boil is complete.

# Find us on Facebook

## Recommended Brew Day Equipment

- 4 Gallon Brew Pot (or larger)
- 6.5 Gallon Fermenter
- Airlock
- · Long Spoon or Paddle
- Hydrometer
- ThermometerNo-Rinse Sanitizer
- Cleanser

#### **Brew Tips**

<sup>1</sup>We suggest doing a 2.5 gallon boil at minimum. If you have the equipment to boil more than 2.5 gallons feel free to do so. There is no need to change the amount of any of the ingredients.

<sup>2</sup>Run canisters of LME under hot water to allow the extract to pour easier

<sup>3</sup>Pay careful attention that the extract does not accumulate and caramelize on the bottom of your brew pot.

<sup>4</sup>When consumed, hops can cause malignant hyperthermia in dogs, sometimes with fatal results. Even small amounts, including "spent" hops from brewing, can trigger a deadly reaction.

# **BREW DAY SCHEDULE**

1. Add 1 oz. of AU Helga hops

2:07<sub>(time)</sub>

2. Boil 40 minutes

3. Add remaining 3.3 lb. LME

1.47 (time)

4. Boil 15 minutes

5. Add .5 oz. German Hallertau hops

2 47<sub>(time)</sub>

6. Boil final 5 minutes

7. Terminate boil

3 07<sub>(time)</sub>

Total Boil Time: 60 Minutes
Continue to Step #5

# Recommended Procedures (continued)

#### 5. COOL WORT & TRANSFER

Cool the wort down to approximately 70°F by placing the brew pot in a sink filled with ice water<sup>7</sup>. Pour or siphon wort into a sanitized fermenter. Avoid transferring the heavy sediment (trub) from the brew pot to the fermenter.

#### 6. ADD WATER

Add enough clean water (approx. 64° - 72°F) to the fermenter to bring your wort to approximately 5 gallons. Thoroughly stir the water into the wort. Be careful not to add a volume of water that will cause the wort to fall outside of the OG range specified in the BREW STATS<sup>8</sup>. Once you are satisfied your wort is at the proper volume and within the OG range, record the OG in the ABV% CALCULATOR (right).

#### 7. PITCH YEAST

Sprinkle the contents of the yeast sachet over top of the entire wort surface (DO NOT RE-HYDRATE) and stir well with sanitized spoon or paddle. Firmly secure the lid onto the fermenter. Fill your airlock halfway with water and gently twist the airlock into the grommeted lid. Move the fermenter to a dark, warm, temperature-stable area (approx. 64° - 72°F).

## **FERMENTATION**

#### 8. MONITOR & RECORD

The wort will begin to ferment within 24 hours and you will notice CO2 releasing (bubbling) out of the airlock. Within 4 - 6 days the bubbling will slow down until you see no more CO2 being released. When fermentation is complete (no bubbles for 48 hours) take a FG reading with a sanitized hydrometer and record it in your ABV% CALCULATOR.<sup>9</sup>

### BOTTLING DAY (DATE / / )

#### 9. READ

Read all of the recommended procedures before you begin.

#### 10. SANITIZE

Thoroughly clean and sanitize ALL brewing equipment, utensils, and bottles that will come in contact with any ingredients, wort or beer with a certified sanitizer, e.g., Star San or IO Star.

#### 11. PREPARE PRIMING SUGAR

In a small saucepan dissolve 5 oz. of priming sugar into 2 cups of boiling water for 5 minutes. Pour this mixture into a clean bottling bucket. Carefully siphon beer from the fermenter to a bottling bucket. Avoid transferring any sediment. Stir gently for about a minute. 1 oz. of priming sugar is equal to 2.5 tablespoons.

#### 12. BOTTLE

Using your siphon setup and bottling wand, fill the bottles<sup>10</sup> to within approximately one inch of the top of the bottle. Use a bottle capper to apply sanitized crown caps.

#### 13. BOTTLE CONDITION

Move the bottles to a dark, warm, temperature-stable area (approx. 64° - 72°F). Over the next two weeks the bottles will naturally carbonate. Carbonation times vary depending on the temperature and beer style, so be patient if it takes a week or so longer.

CHILL & ENJOY YOUR TASTY BREW AND THANK YOU FOR CHOOSING BREWER'S BEST® PRODUCTS.

#### **Brew Tips**

<sup>5</sup>To avoid bacteria growth do this as rapidly as possible. Do not add ice directly to the wort. Alternatively, you can use a brewing accessory like a Wort Chiller.

<sup>6</sup>Use a sanitized hydrometer while adding water to monitor the SG.

<sup>7</sup>Consider transferring your beer to a secondary carboy, see "Two-Stage (Secondary) Fermentation" sidebar below.

<sup>8</sup>Use standard crown bottles, preferably amber color. Make sure bottles are thoroughly clean. Use a bottle brush if necessary to remove stubborn deposits. Bottles should be sanitized prior to filling.

#### Two-Stage (Secondary) Fermentation

Brewer's Best® recommends home brewers employ the practice of a two-stage fermentation. This will allow your finished beer to have more clarity and an overall better, purer flavor. All you need is a 5-gallon carboy, drilled stopper, airlock and siphon setup to transfer the beer. You will also need to monitor and record the SG with your hydrometer when the beer is in the 'primary'. When the fermentation slows (5-7 days), but before it completes, simply transfer the beer into the carboy and allow fermentation to finish in the 'secondary'. Leave the beer for about two weeks and then proceed to Bottling Day. Consult your local retailer to learn more about this technique.

(SECONDARY RACK DATE \_\_\_/\_\_)

# Recommended Bottling Day Equipment

- 6.5 Gallon Bottling Bucket
   Bottle Brush
- Siphon Setup
- Capper
- Bottle Filling Wand
- Sanitizer
- 12 oz. Bottles (approx. 53)
- · Brewer's Best® Crown Caps

## **ABV% Calculator**

(OG - FG) x 131.25 = ABV%

\_\_\_\_\* - \_\_\_\_\*\*) x 131.25 = \_\_\_\_%

\*OG from Step #8
\*\*FG from Step #10

