Module – 1

Introduction: System Software Vs. Application Software, Different System Software—Assembler, Linker, Loader, Macro Processor, Text Editor, Debugger, Device Driver, Compiler, Interpreter, Operating System(Basic Concepts only)

SIC & SIC/XE Architecture, Addressing modes, SIC & SIC/XE Instruction set, Assembler Directives and Programming.

1.1 System Software Vs. Application Software

- Computer softwares are divided into 2 types :
 - 1. Application software
 - 2. System software

Application software

- An application program is primarily concerned with the solution of some problem, using the computer as a tool.
- The focus is on the application, not on the computing system.
- Purpose is supporting or improving the software user's work
- Employs the capabilities of computer directly to a dedicated task that the user wishes to perform
- Types of application software are as follows:
 - Word processing S/W MS word, Notepad, WordPad
 - O Database S/W Oracle, MS Access
 - o Spreadsheet S/W Excel, Lotus, Apple Numbers
 - o Multimedia S/W Real Player, Media Player
 - o Presentation Graphics S/W -MS PowerPoint


System software

- System software consists of a variety of programs that support the operation of a computer.
- Acts as an intermediary b/w computer hardware & application programs
- This software makes it possible for the user to focus on an application or other problem to be solved, without needing to know the details of how the machine works internally.
- Controls the computer system & enhances its performance
- System programs are intended to support the operation and use of the computer itself, rather than any particular application.
- For this reason, they are usually related to the architecture of the machine on which they are run.
- Focus is on the system
- Examples : Assembler , Loader / Linker, Macro processor ,Text Editor, Debugger ,Device driver, Compiler, Interpreter ,Operating system
- The characteristic in which system software differs from application software is machine dependency.

1.2 Different System Softwares

1. Assembler


- Programmers found it difficult to write or read programs in machine language.
- In a quest for a convenient language, they began to use a mnemonic (symbol) for each machine instructions which would subsequently be translated into machine language. Such a mnemonic language is called Assembly language.
- Programs known as Assemblers are written to automate the translation of assembly language into machine language.



- Fundamental functions:
 - 1. Translating mnemonic operation codes to their machine language equivalents.
 - 2. Assigning machine addresses to symbolic tables used by the programmers.

2. Linker

Combines two or more separate object programs and supplies the information needed to allow references between them



3. Loader

Loader is a system program that loads the object program into memory for execution.

4. Macro processor

- A **macro** represents a commonly used group of statements in the source programming language.
- A macro instruction is simply a notational convenience for the programmer to write a shorthand version of a program.
- The macro instruction is replaced by the macro processor with the corresponding group of source language statements. This operation is called "expanding the macro"
- For example:
 - Suppose it is necessary to save the contents of all registers before calling a subroutine.

- This requires a sequence of instructions.
- We can define and use a macro, SAVEREGS, to represent this sequence of instructions.
- A **macro processor** functions essentially involve the substitution of one group of characters or lines for another. Normally, it performs no analysis of the text it handles.
- Macro processors are used in
 - o assembly language
 - o high-level programming languages, e.g., C or C++

5. Text editor

- An Interactive text editor has become an important part of almost any computing environment
- Text editor acts as a primary interface to the computer for all type of "knowledge workers" as they compose, organize, study, and manipulate computer-based information
- A text editor allows you to edit a text file (create, modify etc...)
- Text editors on Windows OS
 - -Notepad, WordPad, Microsoft Word
- Text editors on UNIX OS
 - vi, emacs, jed, pico,

6. Debugger

- Tests & debugs errors
- Debugging is a methodical process of finding and reducing the number of bugs, or defects, in a computer program
- An interactive debugging system provides programmers with facilities that aid in testing and debugging of programs
- Conditional Expressions Programmers can define some conditional expressions ,evaluated during the debugging session, program execution is suspended, when conditions are met, analysis is made, later execution is resumed
- Breakpoint- The programmer may define break points which cause execution to be suspended, when a specified point in the program is reached. After execution is suspended, the debugging command is used to analyze the progress of the program and to diagnose errors detected.


• A Debugging system should also provide functions such as tracing and trace back. Trace back can show the path by which the current statement in the program was reached. It can also show which statements have modified a given variable or parameter.

7. Device driver

- They are distinct "black boxes" that make a particular piece of hardware respond to a welldefined internal programming interface
- They hide completely the details of how the device works.
- User activities are performed by means of a set of standardized calls that are independent of the specific driver; mapping those calls to device-specific operations that act on real hardware is then the role of the device driver.
- This programming interface is such that drivers can be built separately from the rest of the kernel, and "plugged in" at runtime when needed.
- This modularity makes Linux drivers easy to write, to the point that there are now hundreds of them available.

8. Compiler

- A compiler is a program that translates programs written in any high level language into its equivalent machine language program.
- It bridges the semantic gap between a programming language domain and the execution domain.
- The program instructions are taken as a whole.



9. Interpreter

- It is a translator program that translates a statement of high-level language to machine language and executes it immediately. The program instructions are taken line by line.
- The interpreter reads the source program and stores it in memory
- During interpretation, it takes a source statement, determines its meaning and performs actions which implements it. This includes computational and I/O actions.
- Program counter (PC) indicates which statement of the source program is to be interpreted next. This statement would be subjected to the interpretation cycle.
- The interpretation cycle consists of the following steps:

- o Fetch the statement.
- o Analyze the statement and determine its meaning.
- o Execute the meaning of the statement.
- The following are the characteristics of interpretation:
 - o The source program is retained in the source form itself, no target program exists.
 - o A statement is analyzed during the interpretation.

10. Operating system

- It is the most important system program that act as an interface between the users and the system.
- It makes the computer easier to use.
- It provides an interface that is more user-friendly than the underlying hardware.
- The functions of OS are:
 - o Process management
 - o Memory management
 - o Resource management
 - o I/O operations
 - o Data management
 - o Providing security to user's job.

Difference between system software and application software

System software	Application software
System software is used for operating	Application software is used by user
computer hardware.	to perform specific task.
System softwares are installed on the	Application softwares are installed
computer when operating system is	according to user's requirements.
installed.	
In general, the user does not interact	In general, the user interacts with
with system software because it	application sofwares.
works in the background.	
System software can run	Application software can't run
independently. It provides platform	independently. They can't run
for running application softwares.	without the presence of system
	software.
Some examples of system softwares	Some examples of application
are compiler, assembler, debugger,	softwares are word processor, web
driver, etc.	browser, media player, etc.

1.3 The Simplified Instructional Computer (SIC)

- SIC is a hypothetical computer that has been carefully designed to include the hardware features most often found on real machines, while avoiding unusual or irrelevant complexities.
- It is similar to a typical microcomputer. It comes in two versions:
 - o The standard model
 - o XE version (Extra equipment, Extra expensive)
- The two versions have been designed to be **upward compatible** (An object program for the standard SIC machine will also execute properly on a SIC/XE system)

SIC Machine Architecture:

Memory:

- It consists of bytes(8 bits) ,words (24 bits which are consecutive 3 bytes)addressed by the location of their lowest numbered byte.
- All SIC addresses are byte addresses
- There are totally 32,768 (2¹⁵) bytes in memory.

Registers:

There are 5 registers all of which have special uses. Each register is 24 bits in length


Mnemonic	Number	Special use
A	0	Accumulator; used for arithmetic operations
X	1	Index register; used for addressing
L	2	Linkage register; the Jump to Subroutine (JSUB) instruction stores the return address in this register
PC	8	Program counter; contains the address of the next instruction to be fetched for execution
sw	9	Status word; contains a variety of information, including a Condition Code (CC)

Data formats:

- Integers are stored as 24-bit binary numbers
- 2's complement representation is used for negative values
- Characters are stored using their 8 bit ASCII codes.
- They do not support floating point data items.

Instruction formats

All machine instructions are of 24-bits wide. The flag bit x is used to indicate indexed addressing mode.



Addressing modes:

Two types of addressing are available namely,

- 1. Direct addressing mode
- 2. Indexed addressing mode

Mode	Indication	Target address calculation
Direct	x = 0	TA = address
Indexed	x = 1	TA = address + (X)

- Parantheses are used to indicate the contents of a register or a memory location.
- For example (x) represents the contents of the index register X.

Instruction set

It includes instructions like:

1. Data movement instruction

Ex: LDA, LDX, STA, STX.

2. Arithmetic operating instructions

Ex: ADD, SUB, MUL, DIV.

All arithmetic operations involve register A and a word in memory, with the result being left in the register.

3. Comparison instruction

Ex: COMP – the value in the register A is compared with a word in memory. This instruction sets a condition code (CC) flag to indicate the result (<, >, =)

4. Conditional jump instructions

Ex: JLT, JEQ, JGT.

4. Subroutine linkage instructions

Ex: JSUB, RSUB.

JSUB – Jumps to the subroutine, placing the return address in register L.

RSUB – Returns by jumping to the address contained in register L

Input and Output:

- I/O is performed by transferring one byte at a time to or from the rightmost 8 bitsof register A.
- Each device is assigned a unique 8-bit code.
- There are 3 I/O instructions each of which specifies the device code as an operand.
- 1) The Test Device (TD) instructions tests whether the addressed device is ready to send or receive a byte of data.

Condition code is set to indicate the result of this test.

Setting of '<' indicates the device is set to send or receive.

Setting of '= ' indicates the device is not ready

- 2) RD Read Data
- 3) WD Write Data

A program must wait until the device is ready, and then execute a ReadData (RD) or Write Data (WD. The sequence must be repeated for each byte of data to be read or written.

1.4 SIC/XE Architecture

Memory:

- 1 word = 24 bits (3 8-bit bytes)
- Total (SIC/XE) = 2^20 (1,048,576) bytes (1Mbyte)

Registers:

Base register is used for addressing.

MNEMONIC	Register	Purpose
A	0	Accumulator
X	1	Index register
L	2	Linkage register (JSUB/RSUB)
В	3	Base register
S	4	General register
T	5	General register
F	6	Floating Point Accumulator (48 bits)
PC	8	Program Counter (PC)
SW	9	Status Word (includes Condition Code, CC)

Data Format:


- Integers are stored in 24 bit, 2's complement format
- Characters are stored in 8-bit ASCII format
- Floating point is stored in 48 bit signed-exponent-fraction format:



- The fraction is represented as a 36 bit number and has value between 0 and 1. That is the assumed binary point is immediately before the higher order bit.
- The exponent is represented as a 11 bit unsigned binary number between 0 and 2047.
- The sign of the floating point number is indicated by s : 0=positive, 1=negative.
- If the exponent has value e and the fraction has value f, the absolute value of the number represented is $f*2^(e-1024)$.

Instruction Format:

· There are 4 different instruction formats available:



- Format 1 and 2 do not refer memory at all.
- Bit e is used to distinguish between Formats 3 and 4

Addressing modes

Two new addressing modes are available for use with instructions assembled using Format 3

Mode	Indication	Target address ca	lculation
Base relative	b = 1, p = 0	TA = (B) + disp	$(0 \le \text{disp} \le 4095)$
Program-counter relative	b = 0, p = 1	TA = (PC) + disp	$(-2048 \le \text{disp} \le 2047)$

- For **base relative addressing**, the displacement field disp in a Format 3 instruction is interpreted as a 12-bit unsigned integer.
- For **program counter relative addressing**, disp field is interpreted as a 12 bit signed integer with negative values represented in 2's complement notation

Flags b and P:

- b=0 & p=0
 - **Direct addressing** displacement/address field contains TA (Format 4 always uses direct addressing)
- b=0 & p=1
 - PC relative addressing TA=(PC)+disp (-2048<=disp<=2047)
- b=1 & p=0

Base relative addressing - TA=(B)+disp (0<=disp<=4095)

Flags n and i:

• n=0 & i=1

Immediate addressing - TA is used as an operand value (no memory reference)

• n=1 & i=0

Indirect addressing - word at the location given by TA (in memory) is fetched ,the value contained in this word is then taken as the address of the operand value.

• n=0 & i=0

Simple addressing -TA is the location of the operand

In this case bits b,p,e are considered to be part of the address field of the instruction. Hence Format 3 identical to the standarad SIC format providing the desired compatibility.

 \cdot n=1 & i=1

Simple addressing same as n=0 & i=0

Flag x:

• x=1 Indexed addressing add contents of X register to TA calculation

Flag e:

- e=0 use Format 3
- e=1 use Format 4




Fig: Examples of SIC/XE instructions and addressing modes

Instruction set

- SIC provides 26 instructions,
- SIC/XE provides an additional 33 instructions (59 total)
- SIC/XE has 9 categories of instructions:
 - Load/store registers (LDA, LDX, LDCH, STA, STX, STCH, etc.)
 - ➤ Integer arithmetic operations (ADD, SUB, MUL, DIV) these will use register A and a word in memory, results are placed into register A
 - Compare (COMP) compares contents of register A with a word in memory and sets CC (Condition Code) to <, >, or =
 - Conditional jumps (JLT, JEQ, JGT) jumps according to setting of CC
 - Subroutine linkage (JSUB, RSUB) jumps into/returns from subroutine using register L
 - ➤ Input & output control (RD, WD, TD)
 - Floating point arithmetic operations (ADDF, SUBF, MULF, DIVF)
 - Register manipulation, operands-from-registers, and register-to-register arithmetics (RMO, RSUB, COMPR, SHIFTR, SHIFTL, ADDR, SUBR, MULR, DIVR, etc)
 - ➤ Supervisor call instruction (SVC) Executing this instruction generates an interrupt that can be used for communication with the operating system.

Input and Output (I/O)

- 28 (256) I/O devices may be attached, each has its own unique 8-bit address
- 1 byte of data will be transferred to/from the rightmost 8 bits of register A
- Three I/O instructions are provided:
 - o RD Read Data from I/O device into A
 - o WD- Write data to I/O device from A
 - o TD -Test Device determines if addressed I/O device is ready to send/receive a byteof data. The CC (Condition Code) gets set with results from this test:
 - < device is ready to send/receive
 - = device isn't ready
- SIC/XE have I/O channels that can be used to perform input and output while CPU does other work .This allows overlap of computing and I/O resulting in more efficient system operation.
- 3 additional instructions are provided:
 - o SIO Start I/O
 - o HIO Halt I/O
 - o TIO Test I/O

Programming examples

The assembler directives used here are as follows

- **BYTE:** Generate character or hexadecimal constant, occupying as many bytes as needed to represent the constant.
- **WORD:** Generate one- word integer constant.
- **RESB:** Reserve the indicated number of bytes for a data area.
- **RESW:** Reserve the indicated number of words for a data area.

	1200000	30/2000/04/02/03	
	LDA	FIVE	LOAD CONSTANT 5 INTO REGISTER A
	STA	ALPHA	STORE IN ALPHA
	LDCH	CHARZ	LOAD CHARACTER 'Z' INTO REGISTER A
	STCH	C1 _	STORE IN CHARACTER VARIABLE C1
	•		
ALPHA	RESW	1	ONE-WORD VARIABLE
FIVE	WORD	5	ONE-WORD CONSTANT
CHARZ	BYTE	C'Z'	ONE-BYTE CONSTANT
C1	RESB	1	ONE-BYTE VARIABLE
			(a)
4	LDA	#5	LOAD VALUE 5 INTO REGISTER A
	STA	ALPHA	STORE IN ALPHA
	LDA	#90	LOAD ASCII CODE FOR 'Z' INTO REG A
	STCH	C1	STORE IN CHARACTER VARIABLE C1
	SECTION AND ADDRESS.		
	770		
ALPHA	RESW	1	ONE-WORD VARIABLE
C1	RESB	1	ONE-BYTE VARIABLE
	1000		VALUE OF THE VARIABLES

Sample data movement operations for (a) SIC (b) SIC/XE

ALPHA = 5 and C1='Z'

	LDA ADD SUB STA LDA ADD SUB STA	ALPHA INCR ONE BETA GAMMA INCR ONE DELTA	LOAD ALPHA INTO REGISTER A ADD THE VALUE OF INCR SUBTRACT 1 STORE IN BETA LOAD GAMMA INTO REGISTER A ADD THE VALUE OF INCR SUBTRACT 1 STORE IN DELTA
ONTE		i	ONE-WORD CONSTANT
ONE	WORD	1	ONE-WORD CONSTANT ONE-WORD VARIABLES
ALPHA	DECM	1	ONE-WORD VARIABLES
BETA	RESW	1	
GAMMA	RESW	1	
DELTA		1	
	RESW	1	
			(a)
	LDS	INCR	LOAD VALUE OF INCR INTO REGISTER S
	LDA	ALPHA	LOAD ALPHA INTO REGISTER A
		ALPHA S,A	LOAD ALPHA INTO REGISTER A ADD THE VALUE OF INCR
	LDA ADDR SUB	S,A #1	ADD THE VALUE OF INCR SUBTRACT 1
	LDA ADDR SUB STA	S,A #1 BETA	ADD THE VALUE OF INCR SUBTRACT 1 STORE IN BETA
	LDA ADDR SUB STA LDA	S,A #1 BETA GAMMA	ADD THE VALUE OF INCR SUBTRACT 1 STORE IN BETA LOAD GAMMA INTO REGISTER A
	LDA ADDR SUB STA LDA ADDR	S,A #1 BETA GAMMA S,A	ADD THE VALUE OF INCR SUBTRACT 1 STORE IN BETA LOAD GAMMA INTO REGISTER A ADD THE VALUE OF INCR
	LDA ADDR SUB STA LDA ADDR SUB	S,A #1 BETA GAMMA S,A #1	ADD THE VALUE OF INCR SUBTRACT 1 STORE IN BETA LOAD GAMMA INTO REGISTER A ADD THE VALUE OF INCR SUBTRACT 1
	LDA ADDR SUB STA LDA ADDR SUB STA	S,A #1 BETA GAMMA S,A	ADD THE VALUE OF INCR SUBTRACT 1 STORE IN BETA LOAD GAMMA INTO REGISTER A ADD THE VALUE OF INCR
	LDA ADDR SUB STA LDA ADDR SUB STA	S,A #1 BETA GAMMA S,A #1	ADD THE VALUE OF INCR SUBTRACT 1 STORE IN BETA LOAD GAMMA INTO REGISTER A ADD THE VALUE OF INCR SUBTRACT 1
	LDA ADDR SUB STA LDA ADDR SUB STA	S,A #1 BETA GAMMA S,A #1	ADD THE VALUE OF INCR SUBTRACT 1 STORE IN BETA LOAD GAMMA INTO REGISTER A ADD THE VALUE OF INCR SUBTRACT 1
	LDA ADDR SUB STA LDA ADDR SUB STA .	S,A #1 BETA GAMMA S,A #1	ADD THE VALUE OF INCR SUBTRACT 1 STORE IN BETA LOAD GAMMA INTO REGISTER A ADD THE VALUE OF INCR SUBTRACT 1
ALPHA	LDA ADDR SUB STA LDA ADDR SUB STA .	S,A #1 BETA GAMMA S,A #1	ADD THE VALUE OF INCR SUBTRACT 1 STORE IN BETA LOAD GAMMA INTO REGISTER A ADD THE VALUE OF INCR SUBTRACT 1 STORE IN DELTA
ALPHA BETA	LDA ADDR SUB STA LDA ADDR SUB STA .	S,A #1 BETA GAMMA S,A #1 DELTA	ADD THE VALUE OF INCR SUBTRACT 1 STORE IN BETA LOAD GAMMA INTO REGISTER A ADD THE VALUE OF INCR SUBTRACT 1 STORE IN DELTA
	LDA ADDR SUB STA LDA ADDR SUB STA	S,A #1 BETA GAMMA S,A #1 DELTA	ADD THE VALUE OF INCR SUBTRACT 1 STORE IN BETA LOAD GAMMA INTO REGISTER A ADD THE VALUE OF INCR SUBTRACT 1 STORE IN DELTA
BETA GAMMA DELTA	LDA ADDR SUB STA LDA ADDR SUB STA	S,A #1 BETA GAMMA S,A #1 DELTA	ADD THE VALUE OF INCR SUBTRACT 1 STORE IN BETA LOAD GAMMA INTO REGISTER A ADD THE VALUE OF INCR SUBTRACT 1 STORE IN DELTA
BETA GAMMA	LDA ADDR SUB STA LDA ADDR SUB STA	S,A #1 BETA GAMMA S,A #1 DELTA	ADD THE VALUE OF INCR SUBTRACT 1 STORE IN BETA LOAD GAMMA INTO REGISTER A ADD THE VALUE OF INCR SUBTRACT 1 STORE IN DELTA
BETA GAMMA DELTA	LDA ADDR SUB STA LDA ADDR SUB STA	S,A #1 BETA GAMMA S,A #1 DELTA	ADD THE VALUE OF INCR SUBTRACT 1 STORE IN BETA LOAD GAMMA INTO REGISTER A ADD THE VALUE OF INCR SUBTRACT 1 STORE IN DELTA

Sample arithmetic operations for (a) SIC (b)SIC/XE

BETA = ALPHA + INCR -1

DELTA = GAMMA + INCR -1

	LDX	ZERO	INIT	FIALIZE INDEX REGISTER TO 0
MOVECH	LDCH	STR1,X	LOAL	CHARACTER FROM STR1 INTO REG A
	STCH	STR2,X	STOF	RE CHARACTER INTO STR2
	TIX	ELEVEN	ADD	1 TO INDEX, COMPARE RESULT TO 11
	JLT	MOVECH	LOOE	P IF INDEX IS LESS THAN 11
STR1	BYTE	C'TEST STRI	NG'	11-BYTE STRING CONSTANT
STR2	RESB	11		11-BYTE VARIABLE
				ONE-WORD CONSTANTS
ZERO	WORD	0		
ELEVEN	WORD	11		
			(a)
	LDT	#11	TMTT	PIALIZE REGISTER T TO 11
	LDX	#0	47-47-100-00-0	FIALIZE INDEX REGISTER TO 0
MOVECH	LDCH			CHARACTER FROM STR1 INTO REG A
110 V LC11	STCH	STR2,X		RE CHARACTER INTO STR2
	TIXR	T	44.45.45.45.45.45.45.45.45.45.45.45.45.4	1 TO INDEX, COMPARE RESULT TO 11
	JLT	MOVECH		P IF INDEX IS LESS THAN 11
		110 12011	2002	11 11/21/ 10 11/20 11/11/ 11
STR1	BYTE	C'TEST STRI	NG'	11-BYTE STRING CONSTANT
STR2	RESB	11	411/100	11-BYTE VARIABLE
			(b	

Sample looping and indexing operations for (a)SIC (b) SIC/XE

Copy a string(TEST STRING) from STR1 to STR2 $\,$

		nno.	TAITETAL TOP TARREST AND THE TOP O
	LDA	ZERO	INITIALIZE INDEX VALUE TO 0
DDI D	STA	INDEX	I OAD THIDEY WALLE TAMO DEGLECTED V
ADDLP	LDX	INDEX	LOAD WORD FROM ALDUA INTO REGISTER X
	LDA	ALPHA, X	LOAD WORD FROM ALPHA INTO REGISTER A
	ADD	BETA, X	ADD WORD FROM BETA
	STA	GAMMA, X	STORE THE RESULT IN A WORD IN GAMMA
	LDA	INDEX	ADD 3 TO INDEX VALUE
	ADD	THREE	
	STA	INDEX	COMPARE AND THE CO.
	COMP	K300	COMPARE NEW INDEX VALUE TO 300
	JLT	ADDLP	LOOP IF INDEX IS LESS THAN 300
	1		
INDEX	RESW	1	ONE-WORD VARIABLE FOR INDEX VALUE
			ARRAY VARIABLES100 WORDS EACH
ALPHA	RESW	100	
BETA	RESW	100	
SAMMA	RESW	100	
			ONE-WORD CONSTANTS
ZERO	WORD	0	
(300	WORD	300	
THREE	WORD	3	
			(a)
	IDC	#2	INITIALIZE REGISTER S TO 3
	LDT	#3	
		#300	INITIALIZE REGISTER T TO 300 INITIALIZE INDEX REGISTER TO 0
ת זמתו	LDX		
ADDLP	LDA	ALPHA, X	LOAD WORD FROM ALPHA INTO REGISTER A
	ADD	BETA, X	ADD WORD FROM BETA
	STA	GAMMA, X	STORE THE RESULT IN A WORD IN GAMMA
		S,X	ADD 3 TO INDEX VALUE
		X,T	COMPARE NEW INDEX VALUE TO 300
	JLT	ADDLP	LOOP IF INDEX VALUE IS LESS THAN 300
	11.		
	Many.		
	September 1		ADDAY WADTADI DO 100 WORDS DAGY
T DIII	DECE	100	ARRAY VARIABLES100 WORDS EACH
ALPHA	RESW	100	
BETA	RESW		
GAMMA	RESW	100	
			(b)

Sample indexing and looping for (a)SIC (b) SIC/XE

ALPHA , BETA and GAMMA are arrays capable of storing 100 words. Add the words in ALPHA and BETA and store it in the respective position in GAMMA.

			ANNE STOLEN FIRE TARRES
INLOOP	TD	INDEV	TEST INPUT DEVICE
	JEQ	INLOOP	LOOP UNTIL DEVICE IS READY
	RD	INDEV	READ ONE BYTE INTO REGISTER A
	STCH	DATA	STORE BYTE THAT WAS READ
	•		
OUTLP	TD	OUTDEV	TEST OUTPUT DEVICE
	JEQ	OUTLP	LOOP UNTIL DEVICE IS READY
	LDCH	DATA	LOAD DATA BYTE INTO REGISTER A
	WD	OUTDEV	WRITE ONE BYTE TO OUTPUT DEVICE
	•		
	•		
INDEV	BYTE	X'F1'	INPUT DEVICE NUMBER
OUTDEV	BYTE	X'05'	OUTPUT DEVICE NUMBER
DATA	RESB	1	ONE-BYTE VARIABLE

Sample input and output operations for SIC

	JSUB	READ	CALL READ SUBROUTINE
		-	
	T DW	TIPO.	SUBROUTINE TO READ 100-BYTE RECO
READ	LDX	ZERO	INITIALIZE INDEX REGISTER TO 0
RLOOP	TD JEO	INDEV	TEST INPUT DEVICE
	RD	RLOOP INDEV	LOOP IF DEVICE IS BUSY READ ONE BYTE INTO REGISTER A
	STCH	RECORD, X	STORE DATA BYTE INTO RECORD
	TIX	K100	ADD 1 TO INDEX AND COMPARE TO 10
	JLT	RLOOP	LOOP IF INDEX IS LESS THAN 100
	RSUB	14001	EXIT FROM SUBROUTINE
INDEV	BYTE	X'F1'	INPUT DEVICE NUMBER
RECORD	RESB	100	100-BYTE BUFFER FOR INPUT RECORD
			ONE-WORD CONSTANTS
ZERO	WORD	0	
K100	WORD	100	
			(a)
	JSUB	READ	CALL READ SUBROUTINE
			SUBROUTINE TO READ 100-BYTE RECO
		#0	INITIALIZE INDEX REGISTER TO 0
PEAD	LIDY		
READ	LDX		
	LDT	#100	INITIALIZE REGISTER T TO 100
READ	LDT TD	#100 INDEV	
	LDT TD JEQ	#100 INDEV RLOOP	INITIALIZE REGISTER T TO 100 TEST INPUT DEVICE
	LDT TD	#100 INDEV RLOOP INDEV	INITIALIZE REGISTER T TO 100 TEST INPUT DEVICE LOOP IF DEVICE IS BUSY
	LDT TD JEQ RD	#100 INDEV RLOOP INDEV	INITIALIZE REGISTER T TO 100 TEST INPUT DEVICE LOOP IF DEVICE IS BUSY READ ONE BYTE INTO REGISTER A STORE DATA BYTE INTO RECORD
	LDT TD JEQ RD STCH	#100 INDEV RLOOP INDEV RECORD, X	INITIALIZE REGISTER T TO 100 TEST INPUT DEVICE LOOP IF DEVICE IS BUSY READ ONE BYTE INTO REGISTER A STORE DATA BYTE INTO RECORD
	LDT TD JEQ RD STCH TIXR	#100 INDEV RLOOP INDEV RECORD, X	INITIALIZE REGISTER T TO 100 TEST INPUT DEVICE LOOP IF DEVICE IS BUSY READ ONE BYTE INTO REGISTER A STORE DATA BYTE INTO RECORD ADD 1 TO INDEX AND COMPARE TO 10
	LDT TD JEQ RD STCH TIXR JLT	#100 INDEV RLOOP INDEV RECORD, X	INITIALIZE REGISTER T TO 100 TEST INPUT DEVICE LOOP IF DEVICE IS BUSY READ ONE BYTE INTO REGISTER A STORE DATA BYTE INTO RECORD ADD 1 TO INDEX AND COMPARE TO 10 LOOP IF INDEX IS LESS THAN 100
	LDT TD JEQ RD STCH TIXR JLT	#100 INDEV RLOOP INDEV RECORD, X	INITIALIZE REGISTER T TO 100 TEST INPUT DEVICE LOOP IF DEVICE IS BUSY READ ONE BYTE INTO REGISTER A STORE DATA BYTE INTO RECORD ADD 1 TO INDEX AND COMPARE TO 10 LOOP IF INDEX IS LESS THAN 100
RLOOP	LDT TD JEQ RD STCH TIXR JLT RSUB	#100 INDEV RLOOP INDEV RECORD, X T RLOOP	INITIALIZE REGISTER T TO 100 TEST INPUT DEVICE LOOP IF DEVICE IS BUSY READ ONE BYTE INTO REGISTER A STORE DATA BYTE INTO RECORD ADD 1 TO INDEX AND COMPARE TO 10 LOOP IF INDEX IS LESS THAN 100 EXIT FROM SUBROUTINE
RLOOP	LDT TD JEQ RD STCH TIXR JLT RSUB	#100 INDEV RLOOP INDEV RECORD, X T RLOOP	INITIALIZE REGISTER T TO 100 TEST INPUT DEVICE LOOP IF DEVICE IS BUSY READ ONE BYTE INTO REGISTER A STORE DATA BYTE INTO RECORD ADD 1 TO INDEX AND COMPARE TO 10 LOOP IF INDEX IS LESS THAN 100 EXIT FROM SUBROUTINE INPUT DEVICE NUMBER
RLOOP	LDT TD JEQ RD STCH TIXR JLT RSUB	#100 INDEV RLOOP INDEV RECORD, X T RLOOP	INITIALIZE REGISTER T TO 100 TEST INPUT DEVICE LOOP IF DEVICE IS BUSY READ ONE BYTE INTO REGISTER A STORE DATA BYTE INTO RECORD ADD 1 TO INDEX AND COMPARE TO 10 LOOP IF INDEX IS LESS THAN 100 EXIT FROM SUBROUTINE

Sample subroutine call and record input operations for (a)SIC (b) SIC/XE

Read a 100 byte record from input device F1 and store it in a buffer named RECORD of 100 bytes