




01 What It Is

Intruder is a gated algorithmic reverb built around the AMS RMX16's "Non-Lin 2" program. It's a dense, diffuse tank with a hard hold-then-decay envelope stamped on top, the sound behind decades of gated-drum tones. The entire plug-in was reverse-engineered from a small group of impulse response captures.

02 Signal Path

Signal moves through Intruder in a fixed order. Gain and Pre-Delay shape what reaches the tank; Volume and Blend shape what leaves it.



03 The Panel

TIMING CHARACTER LEVELS

TIMING



Decay 0.3–10.0 s · default 1.5 s

How long the tail takes to die away, in continuous seconds rather than the hardware's own compressed 0.1–9.8 label.



Pre-Delay 0–100 ms · default 0 ms

Delay before the reverb signal starts.

CHARACTER



Low/High -12 to +3 dB · default 0 dB

A bass/treble tilt pivoting around ~2kHz. Negative values darken the tonality (more bass, less treble); positive values brighten it.



Smoothing 0–100% · default 0%

Speeds up how quickly echo density builds at the start of the tail. Higher values pack reflections in faster, for a smoother, less grainy onset.

LEVELS



Gain -24 to +24 dB · default 0 dB

Input trim, applied before the reverb engine and before the gate listens for a new hit.



Volume -24 to +24 dB · default 0 dB

Output trim, applied after the reverb engine, before the dry/wet blend.



Threshold -41 to 0 dB · default -36 dB

The level the gate needs to see to treat something as a new hit and retrigger the envelope. Lower it if the tail is cutting off during quiet passages; raise it if it's retriggering on its own.



Blend 0–100% · default 50%

Dry/wet mix.

A Bypass switch sits at the top right of the panel. It mutes the effect entirely, passing dry signal only, for quick A/B comparison.