# Driven Rock Bass

*Sounds like: Royal Blood / Muse — distorted bass that still has low end*

**ACCURACY B**

Close enough to fool most ears.

NOT YET TESTED - settings are a starting point; trust your ears

## WHAT YOU NEED (in this order)

**`Spider Audio split -> path A: MClass EQ (lows only) -> path B: Scream 4 + MClass EQ (mids/highs only) -> merge -> channel comp`**

**Starting material:** DI electric bass or synth bass, clean

---

## DO THIS, STEP BY STEP

**1.** Split the bass with a Spider Audio into two mix channels: "Bass Sub" and "Bass Dirt".

**2.** Bass Sub channel: MClass Equalizer, lo shelf OFF, use Lo Cut off; enable Param 1 as low-pass stand-in — cut everything above ~250 Hz (Param 1: freq 250, gain -inf style deep cut, wide Q). Keep this path CLEAN. No distortion ever.

**3.** Bass Dirt channel: MClass EQ hi-pass — cut below 250 Hz (Lo Cut ON, then Param 1 cut at 180 Hz, -12 dB, medium Q).

**4.** Bass Dirt: Scream 4 after the EQ. Damage type Distortion, Damage 55–70, P1 to taste. Body section ON, type B, for cab-ish resonance.

**5.** Balance: dirt path about equal level with sub path; the distortion should carry the character, the sub carries the weight.

**6.** Merge both to a bass bus channel; bus compressor ratio 4:1, ~3 dB reduction, to glue the two paths into one instrument.

**Why this works**
Distortion destroys low frequencies (intermodulation mud); splitting first means the sub never touches the dirt.

**Why this order**
EQ BEFORE Scream on the dirt path — what you feed a distortion changes what comes out far more than EQ-ing after.

**Reason trick**
Combinator 2 the whole rig; map macro 1 to Scream Damage, macro 2 to dirt-path level. Save as "Driven Bass.cmb" — this is your first "Your Sound" patch.

**The skill you just learned**
Frequency-split (multiband) processing with Spiders — works for guitars, drum busses, anything.

**Worth buying?**
For A-grade: a dedicated bass amp sim RE (Kuassa Cerberus, ~$49) replaces step 4's cab approximation.