COMPUTER NETWORKS

(GR22A3050)

LAB: COURSE FILE

Gokaraju Rangaraju Institute of Engineering and Technology
Bachupally, Kukatpally, Hyderabad - 500072

INDEX

Task 1: Implement the following Data Link Layer framing methods.

1a). BIT STUFFING.

OBJECTIVE: Implement the data link layer framing method.
RESOURCE: Code blocks

PROGRAM LOGIC:
The new technique allows data frames to contain an arbitrary number if bits and allows character codes with an arbitrary no of bits per character. Each frame begins and ends with special bit pattern, 01111110, called a flag byte. Whenever the sender ' s data link layer encounters five consecutive ones in the data ,it automatically stuffs a 0 bit into the out goi ng bit stream. This bit stuffing is analogous to character stuffing, in which a DLE is stuffed into the outgoing g character stream before DLE in the data.

1a.) Bit Stuffing code:

```
#include <stdio.h>
#include<conio.h>
#include<string.h>
void main()
{
int a[20],b[30],i,j,k,count,n;
printf("Enter frame length:");
scanf("%d",&n);
printf("Enter input frame (0's & 1's only):"); for(i=0;i<n;i++)
scanf("%d",&a[i]);
 i=0;
count=1; j=0;
while(i<n)
{
if(a[i]==1)
{
b[j]=a[i];
for(k=i+1;a[k]==1 && k<n &&count<5;k++)
{
j++;
b[j]=a[k]; count++; if(count==5)
{
j++; b[j]=0;
}
i=k;
}
}
else
```

```
{
b[j]=a[i];
} i++; j++;
}
printf("After stuffing the frame is:");
for(i=0;i<j;i++)
printf("%d",b[i]);
getch();
}
```

Output:



NAME OF THE EXPERIMENT: 1 b) CHARACTER STUFFING

OBJECTIVE: Implement the data link layer framing method.

RESOURCE: Codeblocks

PROGRAM LOGIC:
The framing method gets around the problem of resynchronization after an error by having each frame start with the ASCII character sequence DLE STX and the sequence DLE ETX. If the destination ever losses the track of the frame boundaries all it has to do is look for DLE STX or DLE ETX characters to figure out. The data link layer on the receiving g end removes the DLE bbefore the data are given to the network layer. This technique is called character stuffing.

PROGRAM FOR CHARACTER STUFFING

```
#include <stdio.h>
#include <stdlib.h>
#include<string.h>
#include<process.h>
void main()
{
int i=0,j=0,n,pos;char a[20],b[50],ch;
```

```
printf("enter string\n");
scanf("%s",&a);
 n=strlen(a);
printf("enter position\n");
scanf("%d",&pos);
 if(pos>n)
{
printf("invalid position, Enter again :");
 scanf("%d",&pos);
}
printf("enter the character\n");
 ch=getche();
b[0]='d';
b[1]='l';
b[2]='e';
b[3]='s';
b[4]='t';
b[5]='x'; j=6;
while(i<n)
{
if(i==pos-1)
{
b[j]='d';
b[j+1]='l';
b[j+2]='e';
b[j+3]=ch; b[j+4]='d';
b[j+5]='l';
b[j+6]='e';
j=j+7;
}
if(a[i]=='d' && a[i+1]=='l' && a[i+2]=='e')
{
b[j]='d';
b[j+1]='l';
b[j+2]='e';
j=j+3;
}
b[j]=a[i]; i++;
j++;
}
b[j]='d';
b[j+1]='l';
b[j+2]='e';
b[j+3]='e';
b[j+4]='t';
b[j+5]='x';
b[j+6]='\0';
printf("\nframe after stuffing:\n");
printf("%s",b);
getch(); }
```

Output:

NAME OF THE EXPERIMENT: 1.c) Character Count

OBJECTIVE: Implement the data link layer framing method.

RESOURCE: Code blocks

PROGRAM LOGIC:
The framing method To count the number of characters present in the string, we will iterate through the string and count the characters. In above example, total number of characters present in the string are 19.

Program for character count

```
#include <stdlib.h>
#include <string.h>
int main()
{
   char string[] = "The best of both worlds";
   int count = 0;
   //Counts each character except space
   for(int i = 0; i < strlen(string); i++) {
      if(string[i] != ' ')
         count++;
   }
   //Displays the total number of characters present in the given string
   printf("Total number of characters in a string: %d", count);

   return 0;
}
```

Output:

Total number of characters in a string: 19



NAME OF THE EXPERIMENT: 2.a) Simplex protocol (stop and wait protocol)

OBJECTIVE: Implement the data link layer framing method.

RESOURCE: Code blocks

PROGRAM LOGIC: Stop and wait protocol is a simple and reliable protocol for flow control. Stop and wait protocol is a data link layer protocol. In this protocol, the sender will not send the next packet to the receiver until the acknowledgment of the previous packet is received.

Program:

```
#include <stdio.h>
#include <stdlib.h>
void main()
{
   int i,j,n,x,x1=10,x2;
   n=10;
   i=1;j=1;
   printf("no .of frames is %d",n);
   getch();
   while(n>0)
   {
    printf("\n sending frames is %d",i);
    x=rand()%10;
    if(x%10==0)
    {
       for(x2=1;x2<2;x2++)
       {
          printf("\n waiting for %d seonds in \n ",x2);
          sleep(x2);
       }
       printf("\n sending frames is %d ",i);
       x=rand()%10;
    }
    printf("\n ack for frame is %d \n ",j);
    n=n-1;
    i++;
    j++;
   }
   printf("\n end of stop and wait protocol \n");
   getch();
}
```

Output:

NAME OF THE EXPERIMENT: 2.b) Sliding Window protocol(Go Back N)

OBJECTIVE: Implement the data link layer framing method.
RESOURCE: Code blocks

PROGRAM LOGIC: Go-Back-N is a data link layer protocol that uses a sliding window method. In this, if any frame is corrupted or lost, all subsequent frames have to be sent again.

The size of the sender window is N in this protocol. For example, Go-Back-8, the size of the sender window, will be 8. The receiver window size is always 1.

If the receiver receives a corrupted frame, it cancels it. The receiver does not accept a corrupted frame. When the timer expires, the sender sends the correct frame again.

Program:

```
#include<stdio.h>
int main()
{
        int windowsize,sent=0,ack,i;
        printf("enter window size\n");
        scanf("%d",&windowsize);
        while(1)
        {
                for( i = 0; i < windowsize; i++)
                        {
                                printf("Frame %d has been transmitted.\n",sent);
                                sent++;
                                if(sent == windowsize)
                                        break;
                        }
                        printf("\nPlease enter the last Acknowledgement received.\n");
```

```
                        scanf("%d",&ack);
                        if(ack == windowsize)
                                break;
                        else
                                sent = ack;
        }
return 0;
}
```

Output:



NAME OF THE EXPERIMENT: 2.c) Sliding window protocol (selective repeat)

OBJECTIVE: Implement the data link layer framing method.

RESOURCE: Code blocks

PROGRAM LOGIC: Selective Repeat ARQ is also known as the Selective Repeat Automatic Repeat Request. It is a data link layer protocol that uses a sliding window method. The Go-back-N ARQ protocol works well if it has fewer errors. But if there is a lot of error in the frame, lots of bandwidth loss in sending the frames again. So, we use the Selective Repeat ARQ protocol. In this protocol, the size of the sender window is always equal to the size of the receiver window.

PROGRAM:

```
#include <stdio.h>
#include <stdlib.h>
#include <math.h>
int main()
{
   int f,n;
```

```
    printf("Enter the no of bits for the sequence no \n");
    scanf("%d",&n);
    f=pow(2,n-1);
    for(int j=0;j<f;j++)
    {
       printf("\n sender :frame %d is sent",j);
    }
    for(int i=0;i<f;i++)
    {
       printf("\n");
       int flag=rand()%2;
       if(!flag)
       {
          printf("\n receiver :frame %d received correctly \n(ack %d received) \n",i,i);
       }
       else
          {
             printf("\n receiver :frame %d received correctly \n(ack %d lost) \n",i,i);
          printf("(sender time out ....> resend the frame) \n");
       }
    }
printf("\n want to continue");
    return 0;
}
```

Output:



NAME OF THE EXPERIMENT: 3a) Shortest Path routing protocol

OBJECTIVE: Implement the data link layer framing method.

RESOURCE: Code blocks

PROGRAM LOGIC: Dijkstra shortest path (SP): This algorithm finds the shortest route from a given source to a destination in a graph. The route is a path whose cost is the least possible one. K-shortest path (K-SP): K-shortest-path algorithms find more than one route for each source and destination pair.

PROGRAM:

```
#include <stdio.h>
#include <stdlib.h>
#define V 9
int minDistance(int dist[], int sptSet[])
{
   int min = INT_MAX, min_index;
   int v;
   for (v = 0; v < V; v++)
      if (sptSet[v] == 0 && dist[v] <= min)
         min = dist[v], min_index = v;
   return min_index;
}
void printSolution(int dist[], int n) {
   printf("Vertex   Distance from Source\n");
   int i;
   for (i = 0; i < V; i++)
      printf("%d \t\t %d\n", i, dist[i]);
}
void dijkstra(int graph[V][V], int src) {
   int dist[V];
   int sptSet[V];
   int i, count, v;
   for (i = 0; i < V; i++)
      dist[i] = INT_MAX, sptSet[i] = 0;
   dist[src] = 0;
   for (count = 0; count < V - 1; count++) {
      int u = minDistance(dist, sptSet);
      sptSet[u] = 1;
      for (v = 0; v < V; v++)
         if (!sptSet[v] && graph[u][v] && dist[u] != INT_MAX && dist[u]
               + graph[u][v] < dist[v])
            dist[v] = dist[u] + graph[u][v];
   }
   printSolution(dist, V);
}
int main() {
   /* Let us create the example graph discussed above */
```

```
   int graph[V][V] =  {{0, 4, 0, 0, 0, 0, 0, 8, 0},
                       {4, 0, 8, 0, 0, 0, 0, 11, 0},
                       {0, 8, 0, 7, 0, 4, 0, 0, 2},
                       {0, 0, 7, 0, 9, 14, 0, 0, 0},
                       {0, 0, 0, 9, 0, 10, 0, 0, 0},
                       {0, 0, 4, 0, 10, 0, 2, 0, 0},
                       {0, 0, 0, 14, 0, 2, 0, 1, 6},
                       {8, 11, 0, 0, 0, 0, 1, 0, 7},
                       {0, 0, 2, 0, 0, 0, 6, 7, 0}
                      };
   dijkstra(graph, 0);
   return 0;
}
```

Output:



NAME OF THE EXPERIMENT: 3b)Distance Vector routing protocol

OBJECTIVE: Implement the data link layer framing method.

RESOURCE: Code blocks

PROGRAM LOGIC: The distance vector routing algorithm is one of the most commonly used routing algorithms. It is a distributed algorithm, meaning that it is run on each router in the network. The algorithm works by each router sending updates to its neighbours about the best path to each destination.

Program:

```
#include <stdio.h>
#include <stdlib.h>
struct node  {
        unsigned dist[20];
```

```
        unsigned from[20];
}rt[10];
int main()  {
        int dmat[20][20],n,i,j,k,count=0;
        printf("\nEnter the number of nodes : ");
        scanf("%d",&n);
        printf("\nEnter the cost matrix :\n");
        for(i=0;i<n;i++)
                for(j=0;j<n;j++ )  {
                        scanf("%d",&dmat[i][j]);
                        dmat[i][i]=0;
                        rt[i].dist[j]=dmat[i][j];
                        rt[i].from[j]=j;  }
                         do  {  count=0;
                        for(i=0;i<n;i++)
                        for(j=0;j<n;j++)
                        for(k=0;k<n;k++)
                                if(rt[i].dist[j]>dmat[i][k]+rt[k].dist[j])  {
                                        rt[i].dist[j]=rt[i].dist[k]+rt[k].dist[j];
                                        rt[i].from[j]=k;
                                        count++;  }
                }while(count!=0);
                for(i=0;i<n;i++)  {
                        printf("\n\nState value for router %d is \n",i+1);
                        for(j=0;j<n;j++)   {
                                printf("\t\nnode %d via %d
Distance%d",j+1,rt[i].from[j]+1,rt[i].dist[j]);
        printf("\n\n");
                }
}
}
```

Output:

NAME OF THE EXPERIMENT: 3.C)Token Bucket algorithm

OBJECTIVE: Implement the data link layer framing method.

RESOURCE: Code blocks

PROGRAM LOGIC: Token bucket algorithm is one of the techniques for congestion control algorithms. When too many packets are present in the network it causes packet delay and loss of packet which degrades the performance of the system.

PROGRAM:

```
#include <stdio.h>
#include <stdlib.h>
int main()
{
   int no_of_queries, storage, output_pkt_size;
   int input_pkt_size, bucket_size, size_left;
   storage = 0;
   no_of_queries = 4;
   bucket_size = 10;
   input_pkt_size = 4;
   output_pkt_size = 1;
   for (int i = 0; i < no_of_queries; i++)
   {
      size_left = bucket_size - storage;
      if (input_pkt_size <= size_left) {
         storage += input_pkt_size;
      }
      else {
         printf("Packet loss = %d\n", input_pkt_size);
      }
      printf("Buffer size= %d out of bucket size= %d\n",
            storage, bucket_size);
      storage -= output_pkt_size;
   }
   return 0;
}
```

Output:



NAME OF THE EXPERIMENT: 4.a) DES algorithm

OBJECTIVE: Implement the **Data Encryption Standard is a symmetric-key algorithm.**

RESOURCE: Code blocks

PROGRAM LOGIC: The DES (Data Encryption Standard) algorithm is a symmetric-key block cipher created in the early 1970s by an IBM team and adopted by the National Institute of Standards and Technology (NIST). The algorithm takes the plain text in 64-bit blocks and converts them into ciphertext using 48-bit keys.

Program:

```
#include <stdio.h>
#include <stdlib.h>
int Original_key [64] = { // you can change key if required
0, 0, 0, 1, 0, 0, 1, 1, 0, 0, 1, 1, 0, 1, 0, 0,
0, 1, 0, 1, 0, 1, 1, 1, 0, 1, 1, 1, 1, 0, 0, 1,
1, 0, 0, 1, 1, 0, 1, 1, 1, 0, 1, 1, 1, 1, 0, 0,
1, 1, 0, 1, 1, 1, 1, 1, 1, 1, 1, 1, 0, 0, 0, 1
};
int Permutated_Choice1[56] = {
  57, 49, 41, 33, 25, 17,  9,
   1, 58, 50, 42, 34, 26, 18,
  10,  2, 59, 51, 43, 35, 27,
  19, 11,  3, 60, 52, 44, 36,
  63, 55, 47, 39, 31, 23, 15,
   7, 62, 54, 46, 38, 30, 22,
  14,  6, 61, 53, 45, 37, 29,
  21, 13,  5, 28, 20, 12,  4
};

int Permutated_Choice2[48] = {
  14, 17, 11, 24,  1,  5,
   3, 28, 15,  6, 21, 10,
  23, 19, 12,  4, 26,  8,
  16,  7, 27, 20, 13,  2,
  41, 52, 31, 37, 47, 55,
  30, 40, 51, 45, 33, 48,
  44, 49, 39, 56, 34, 53,
  46, 42, 50, 36, 29, 32
};

int Iintial_Permutation [64] = {
  58, 50, 42, 34, 26, 18, 10, 2,
  60, 52, 44, 36, 28, 20, 12, 4,
  62, 54, 46, 38, 30, 22, 14, 6,
  64, 56, 48, 40, 32, 24, 16, 8,
  57, 49, 41, 33, 25, 17,  9, 1,
  59, 51, 43, 35, 27, 19, 11, 3,
  61, 53, 45, 37, 29, 21, 13, 5,
```

```
  63, 55, 47, 39, 31, 23, 15, 7
};

int Final_Permutation[] =
{
  40, 8, 48, 16, 56, 24, 64, 32,
  39, 7, 47, 15, 55, 23, 63, 31,
  38, 6, 46, 14, 54, 22, 62, 30,
  37, 5, 45, 13, 53, 21, 61, 29,
  36, 4, 44, 12, 52, 20, 60, 28,
  35, 3, 43, 11, 51, 19, 59, 27,
  34, 2, 42, 10, 50, 18, 58, 26,
  33, 1, 41,  9, 49, 17, 57, 25
};
int P[] =
{
  16,  7, 20, 21,
  29, 12, 28, 17,
   1, 15, 23, 26,
   5, 18, 31, 10,
   2,  8, 24, 14,
  32, 27,  3,  9,
  19, 13, 30,  6,
  22, 11,  4, 25
};

int E[] =
{
  32,  1,  2,  3,  4,  5,
   4,  5,  6,  7,  8,  9,
   8,  9, 10, 11, 12, 13,
  12, 13, 14, 15, 16, 17,
  16, 17, 18, 19, 20, 21,
  20, 21, 22, 23, 24, 25,
  24, 25, 26, 27, 28, 29,
  28, 29, 30, 31, 32,  1
};

int S1[4][16] =
{
14,  4, 13,  1,  2, 15, 11,  8,  3, 10,  6, 12,  5,  9,  0,  7,
0, 15,  7,  4, 14,  2, 13,  1, 10,  6, 12, 11,  9,  5,  3,  8,
4,  1, 14,  8, 13,  6,  2, 11, 15, 12,  9,  7,  3, 10,  5,  0,
15, 12,  8,  2,  4,  9,  1,  7,  5, 11,  3, 14, 10,  0,  6, 13
};

int S2[4][16] =
{
15,  1,  8, 14,  6, 11,  3,  4,  9,  7,  2, 13, 12,  0,  5, 10,
3, 13,  4,  7, 15,  2,  8, 14, 12,  0,  1, 10,  6,  9, 11,  5,
```

```
0, 14,  7, 11, 10,  4, 13,  1,  5,  8, 12,  6,  9,  3,  2, 15,
13,  8, 10,  1,  3, 15,  4,  2, 11,  6,  7, 12,  0,  5, 14,  9
};

int S3[4][16] =
{
10,  0,  9, 14,  6,  3, 15,  5,  1, 13, 12,  7, 11,  4,  2,  8,
13,  7,  0,  9,  3,  4,  6, 10,  2,  8,  5, 14, 12, 11, 15,  1,
13,  6,  4,  9,  8, 15,  3,  0, 11,  1,  2, 12,  5, 10, 14,  7,
1, 10, 13,  0,  6,  9,  8,  7,  4, 15, 14,  3, 11,  5,  2, 12
};

int S4[4][16] =
{
7, 13, 14,  3,  0,  6,  9, 10,  1,  2,  8,  5, 11, 12,  4, 15,
13,  8, 11,  5,  6, 15,  0,  3,  4,  7,  2, 12,  1, 10, 14,  9,
10,  6,  9,  0, 12, 11,  7, 13, 15,  1,  3, 14,  5,  2,  8,  4,
3, 15,  0,  6, 10,  1, 13,  8,  9,  4,  5, 11, 12,  7,  2, 14
};

int S5[4][16] =
{
2, 12,  4,  1,  7, 10, 11,  6,  8,  5,  3, 15, 13,  0, 14,  9,
14, 11,  2, 12,  4,  7, 13,  1,  5,  0, 15, 10,  3,  9,  8,  6,
4,  2,  1, 11, 10, 13,  7,  8, 15,  9, 12,  5,  6,  3,  0, 14,
11,  8, 12,  7,  1, 14,  2, 13,  6, 15,  0,  9, 10,  4,  5,  3
};

int S6[4][16] =
{
12,  1, 10, 15,  9,  2,  6,  8,  0, 13,  3,  4, 14,  7,  5, 11,
10, 15,  4,  2,  7, 12,  9,  5,  6,  1, 13, 14,  0, 11,  3,  8,
9, 14, 15,  5,  2,  8, 12,  3,  7,  0,  4, 10,  1, 13, 11,  6,
4,  3,  2, 12,  9,  5, 15, 10, 11, 14,  1,  7,  6,  0,  8, 13
};

int S7[4][16]=
{
4, 11,  2, 14, 15,  0,  8, 13,  3, 12,  9,  7,  5, 10,  6,  1,
13,  0, 11,  7,  4,  9,  1, 10, 14,  3,  5, 12,  2, 15,  8,  6,
1,  4, 11, 13, 12,  3,  7, 14, 10, 15,  6,  8,  0,  5,  9,  2,
6, 11, 13,  8,  1,  4, 10,  7,  9,  5,  0, 15, 14,  2,  3, 12
};

int S8[4][16]=
{
13,  2,  8,  4,  6, 15, 11,  1, 10,  9,  3, 14,  5,  0, 12,  7,
1, 15, 13,  8, 10,  3,  7,  4, 12,  5,  6, 11,  0, 14,  9,  2,
7, 11,  4,  1,  9, 12, 14,  2,  0,  6, 10, 13, 15,  3,  5,  8,
2,  1, 14,  7,  4, 10,  8, 13, 15, 12,  9,  0,  3,  5,  6, 11
```

```
};

int shifts_for_each_round[16] = { 1, 1, 2, 2, 2, 2, 2, 2, 1, 2, 2, 2, 2, 2, 2, 1 };
int _56bit_key[56];
int _48bit_key[17][48];
int text_to_bits[99999], bits_size=0;
int Left32[17][32], Right32[17][32];
int EXPtext[48];
int XORtext[48];
int X[8][6];
int X2[32];
int R[32];
int chiper_text[64];
int encrypted_text[64];

int XOR(int a, int b) {
return (a ^ b);
}

void Dec_to_Binary(int n)
{
   int binaryNum[1000];
   int i = 0;
   while (n > 0) {
      binaryNum[i] = n % 2;
      n = n / 2;
      i++;
   }
   for (int j = i - 1; j >= 0; j--) {
text_to_bits[bits_size++] = binaryNum[j];
}
}
int F1(int i)
{
int r, c, b[6];
for (int j = 0; j < 6; j++)
b[j] = X[i][j];

r = b[0] * 2 + b[5];
c = 8 * b[1] + 4 * b[2] + 2 * b[3] + b[4];
if (i == 0)
return S1[r][c];
else if (i == 1)
return S2[r][c];
else if (i == 2)
return S3[r][c];
else if (i == 3)
return S4[r][c];
else if (i == 4)
return S5[r][c];
```

```
else if (i == 5)
return S6[r][c];
else if (i == 6)
return S7[r][c];
else if (i == 7)
return S8[r][c];
}
int PBox(int pos, int bit)
{
int i;
for (i = 0; i < 32; i++)
if (P[i] == pos + 1)
break;
R[i] = bit;
}
int ToBits(int value)
{
int k, j, m;
static int i;
if (i % 32 == 0)
i = 0;
for (j = 3; j >= 0; j--)
{
m = 1 << j;
k = value & m;
if (k == 0)
X2[3 - j + i] = '0' - 48;
else
X2[3 - j + i] = '1' - 48;
}
i = i + 4;
}
int SBox(int XORtext[])
{
int k = 0;
for (int i = 0; i < 8; i++)
for (int j = 0; j < 6; j++)
X[i][j] = XORtext[k++];

int value;
for (int i = 0; i < 8; i++)
{
value = F1(i);
ToBits(value);
}
}
void expansion_function(int pos, int bit)
{
for (int i = 0; i < 48; i++)
if (E[i] == pos + 1)
```

```
EXPtext[i] = bit;
}
void cipher(int Round, int mode)
{
for (int i = 0; i < 32; i++)
expansion_function(i, Right32[Round - 1][i]);
for (int i = 0; i < 48; i++)
{
if (mode == 0)
XORtext[i] = XOR(EXPtext[i], _48bit_key[Round][i]);
else
XORtext[i] = XOR(EXPtext[i], _48bit_key[17 - Round][i]);
}

SBox(XORtext);
for (int i = 0; i < 32; i++)
PBox(i, X2[i]);
for (int i = 0; i < 32; i++)
Right32[Round][i] = XOR(Left32[Round - 1][i], R[i]);
}
void finalPermutation(int pos, int bit)
{
int i;
for (i = 0; i < 64; i++)
if (Final_Permutation[i] == pos + 1)
break;
encrypted_text[i] = bit;
}
void Encrypt_each_64_bit (int plain_bits [])
{
int IP_result [64] , index=0;
for (int i = 0; i < 64; i++) {
IP_result [i] = plain_bits[ Iintial_Permutation[i] ];
}
for (int i = 0; i < 32; i++)
Left32[0][i] = IP_result[i];
for (int i = 32; i < 64; i++)
Right32[0][i - 32] = IP_result[i];
for (int k = 1; k < 17; k++)
{ // processing through all 16 rounds
cipher(k, 0);
for (int i = 0; i < 32; i++)
Left32[k][i] = Right32[k - 1][i]; // right part comes as it is to next round left part
}
for (int i = 0; i < 64; i++)
{ // 32bit swap as well as Final Inverse Permutation
if (i < 32)
chiper_text[i] = Right32[16][i];
else
chiper_text[i] = Left32[16][i - 32];
```

```
finalPermutation(i, chiper_text[i]);
}
for (int i = 0; i < 64; i++)
printf("%d", encrypted_text[i]);
}
void convert_Text_to_bits(char *plain_text){
for(int i=0;plain_text[i];i++){
int asci = plain_text[i];
Dec_to_Binary(asci);
}
}
void key56to48(int round, int pos, int bit)
{
int i;
for (i = 0; i < 56; i++)
if (Permutated_Choice2[i] == pos + 1)
break;
_48bit_key[round][i] = bit;
}
int key64to56(int pos, int bit)
{
int i;
for (i = 0; i < 56; i++)
if (Permutated_Choice1[i] == pos + 1)
break;
_56bit_key[i] = bit;
}
void key64to48(int key[])
{
int k, backup[17][2];
int CD[17][56];
int C[17][28], D[17][28];

for (int i = 0; i < 64; i++)
key64to56(i, key[i]);

for (int i = 0; i < 56; i++)
if (i < 28)
C[0][i] = _56bit_key[i];
else
D[0][i - 28] = _56bit_key[i];
for (int x = 1; x < 17; x++)
{
int shift = shifts_for_each_round[x - 1];
for (int i = 0; i < shift; i++)
backup[x - 1][i] = C[x - 1][i];
for (int i = 0; i < (28 - shift); i++)
C[x][i] = C[x - 1][i + shift];
k = 0;
for (int i = 28 - shift; i < 28; i++)
```

```
C[x][i] = backup[x - 1][k++];
for (int i = 0; i < shift; i++)
backup[x - 1][i] = D[x - 1][i];
for (int i = 0; i < (28 - shift); i++)
D[x][i] = D[x - 1][i + shift];
k = 0;
for (int i = 28 - shift; i < 28; i++)
D[x][i] = backup[x - 1][k++];
}
for (int j = 0; j < 17; j++)
{
for (int i = 0; i < 28; i++)
CD[j][i] = C[j][i];
for (int i = 28; i < 56; i++)
CD[j][i] = D[j][i - 28];
}
for (int j = 1; j < 17; j++)
for (int i = 0; i < 56; i++)
key56to48(j, i, CD[j][i]);
}
int main(){
char plain_text[] = "tomarrow we wiil be declaring war";
convert_Text_to_bits(plain_text);
key64to48(Original_key); // it creates all keys for all rounds
int _64bit_sets = bits_size/64;
printf("Decrypted output is\n");
for(int i=0;i<= _64bit_sets ;i++) {
Encrypt_each_64_bit (text_to_bits + 64*i);
}
return 0;
}
```

Output:



NAME OF THE EXPERIMENT: 4.b) RSA algorithm

OBJECTIVE: Implement the RSA asymmetric cryptographic algorithm

RESOURCE: Code blocks

PROGRAM LOGIC: RSA is a widely used cryptographic algorithm that was first introduced in 1977. It uses public and private key pairs to encrypt and decrypt data. Though RSA can be used in several applications, its computational complexity makes it unsuitable for encrypting large messages or files.

Program:

```
#include <stdio.h>
#include <stdlib.h>
#include<math.h>
//to find gcd
int gcd(int a, int h)
{
   int temp;
   while(1)
   {
      temp = a%h;
      if(temp==0)
      return h;
      a = h;
      h = temp;
   }
}
int main()
{
   //2 random prime numbers
   double p = 3;
   double q = 7;
   double n=p*q;
   double count;
   double totient = (p-1)*(q-1);

   //public key
   //e stands for encrypt
   double e=2;
   //for checking co-prime which satisfies e>1
   while(e<totient){
   count = gcd(e,totient);
   if(count==1)
      break;
   else
      e++;
   }
   //private key
   //d stands for decrypt
```

```
    double d;
    //k can be any arbitrary value
    double k = 2;
    //choosing d such that it satisfies d*e = 1 + k * totient
    d = (1 + (k*totient))/e;
    double msg = 12;
    double c = pow(msg,e);
    double m = pow(c,d);
    c=fmod(c,n);
    m=fmod(m,n);
    printf("Message data = %lf",msg);
    printf("\np = %lf",p);
    printf("\nq = %lf",q);
    printf("\nn = pq = %lf",n);
    printf("\ntotient = %lf",totient);
    printf("\ne = %lf",e);
    printf("\nd = %lf",d);
    printf("\nEncrypted data = %lf",c);
    printf("\nOriginal Message Sent = %lf",m);
    return 0;
}
```

Output:



Task 5 :

a). Configure network devices, such as hubs and switches within a network topology using Packet Tracer software.



Configure the network systems with the above-mentioned IP address and then ping from other systems to test the flow of packets.



b).Construct a single LAN and understand the concepts and operation of ARP.

What is ARP?

The **Address Resolution Protocol** (**ARP**) is a communication protocol used for discovering the physical address, such as a MAC address, associated with a given internet layer address, typically an IPv4 address.

How ARP Works?

Imagine a device that wants to communicate with others over the internet. What does ARP do? It broadcast a packet to all the devices of the source network. The devices of the network peel the header of the data link layer from the **Protocol Data Unit (PDU)** called frame and transfer the packet to the network layer (layer 3 of OSI) where the network ID of the packet is validated with the destination IP's network ID of the packet and if it's equal then it responds to the source with the MAC address of the destination, else the packet reaches the gateway of the network and broadcasts packet to the devices it is connected with and validates their network ID. The above process continues till the second last network device in the path reaches the destination where it gets validated and ARP, in turn, responds with the destination MAC address.

Below topology illustrates 4 PCs with IP address ranging from 10.0.0.1- 10.0.0.4



Initially if we look into ARP table of PC 1 there are no entries



Now ping to PC2 from PC1 as illustrated below. And check the arp rable.



Now from PC1 ping PC3 and PC4 and watch the arp tables



Now you can ping from other systems and see how the ARP tables are constructed.

TASK 6A: a). Configure and implementation of a Switch within a Network using Packet Tracer..

What is a network switch, and how does it work?

The Switch is a network device that is used to segment the networks into different subnetworks called subnets or LAN segments. It is responsible for filtering and forwarding the packets between LAN segments based on MAC address.

Switches have many ports, and when data arrives at any port, the destination address is examined first and some checks are also done and then it is processed to the devices. Different types of communication are supported here like unicast, multicast, and broadcast communication.

Modes of operation:

Mode	Purpose	Prompt	Command to enter	Command to exit
User EXEC	Allow you to connect with remote devices, perform basic tests, temporary change terminal setting and list system information	Router >	Default mode after booting. Login with password, if configured.	Use **exit** command
Privileged EXEC	Allow you to set operating parameters. It also includes high level testing and list commands like show, copy and debug.	Router #	Use **enable** command from user exec mode	Use **exit** command
Global Configuration	Contain commands those affect the entire system	Router(config)#	Use **configure terminal** command from privileged exec mode	Use **exit** command
Interface Configuration	Contain commands those modify the operation of an interface	Router(config-if)#	Use **interface *type number*** command from global configuration mode	Use **exit** command to return in global configuration mode
Sub-Interface Configuration	Configure or modify the virtual interface created from physical interface	Router(config-subif)	Use **interface *type sub interface*** number command from global configuration mode or interface configure mode	Use **exit** to return in previous mode. Use **end** command to return in privileged exec mode.

Step 1. Open the packet tracer desktop and take a switch (PT-Switch) from the devices.

Step 2: Configure the Host name of the swicth0.

- Click on switch0 and go to Command Line Interface.
- Then change the hostname to “sh”

Command:

```
switch>
switch>en
switch#conf t
switch(config)#hostname sh
```

Step 3: Set a message of the day (MOTD) banner for the users.

Command:

```
sh(config)#banner motd $
```

Step 4: Set up line control password and enable secret password.

To configure the Line Control password and Enable secret follow the below commands:

```
sh#conf t
sh(config)#
sh(config)#line con 0
sh(config-line)#password griet123
sh(config-line)#login
sh(config-line)#exit
sh(config)#enable secret griet12345
sh(config)#service password-encryption  // encrypts the password
sh(config)#exit
```

Step 5: Verify the password

- When you try to log in first, it will ask for the **line control password.**
- Then, to configure the terminal it will ask to **enable a secret password.**

To save the run configuration to startup file use the below command:

Command:

```
sh#copy run startup-config   (OR)    write
```

sh# no ip domain-lookup // used to prevent the router from trying to resolve incorrectly pasted commands in the cli by sending out a DNS query.

Select the switch – goto cli mode and type the below configuration commands.

```
Switch>
Switch>enable
Switch#config terminal
Switch(config)#hostname sh
sh(config)#banner motd #Warning Unauthorised access is prohibited#

sh(config)#line con 0
sh(config-line)#password griet1234
sh(config-line)#login
sh(config-line)#exit

sh(config)#enable secret griet5678
sh(config)#service password-encryption

sh(config)#no ip domain-lookup

sh#copy running-config startup-config
Destination filename [startup-config]?
Building configuration...
[OK]


sh#show start
sh#show startup-config
Using 1238 bytes
!
version 15.0
no service timestamps log datetime msec
no service timestamps debug datetime msec
service password-encryption
!
hostname sh
!
enable secret 5 $1$mERr$vyUGBRk3bfoMV8qV.wJrB0
!
!
!
no ip domain-lookup
!
!
!
spanning-tree mode pvst
spanning-tree extend system-id
!
interface FastEthernet0/1
!
```

```
interface FastEthernet0/2
!
interface FastEthernet0/3
!
interface FastEthernet0/4
!
interface FastEthernet0/5

!< deleted some part>
!
interface FastEthernet0/20
!
interface FastEthernet0/21
!
interface FastEthernet0/22
!
interface FastEthernet0/23
!
interface FastEthernet0/24
!
interface GigabitEthernet0/1
!
interface GigabitEthernet0/2
!
interface Vlan1
no ip address
shutdown
!
banner motd ^CWarning Unauthorised access is prohibited^C
!
!
!
line con 0
password 7 08265E470C0D5445415F
login
!
line vty 0 4
login
line vty 5 15
login
!
!
!
!
End
```

TASK 6B : Learn and Implement basic commands.

1. Ping

Ping is most commonly used network tool used to test the connection between the source and destination host.

Ping command uses Internet Control Message Protocol (ICMP) to send an echo packet from the source host to a destination host and listen to the response. If the source host receives a response from the destination host, this host is reachable. If not there is a connection error.

Using Ping command the user can identify in which area the connection problem is there, is it local or outside their LAN.

Ex: You can ping either by using the IP address or by the website name or URL. In the below example I pinged to my wireless router with its IP Address and google.com by its domain name.



2. Tracert/traceroute.

Ping is a basic tool to check the basic connectivity. But if you want to identify the complete path from the source node to the destination node than tracert/traceroute utility is very useful.

The tracert utility for windows and traceroute utility for Linux gives you the entire path, including the number of hops packet travelled.



3. Ipconfig

Ipconfig is one of the most important tool for system admins for troubleshooting networking issue. It is a command-line tool that shows the current TCP/IP configuration of the installed networking stack of a computer connected to a network.

This tool includes a number of switches to perform different actions. In the below example I am using /all which Produces a detailed configuration report for all interfaces. You can observe the 48 bit MAC address, IPaddress, DHCP details etc**.**



4. Nslookup

Some of the most common networking issues revolve around issues with Dynamic Name System (DNS) address resolution issues. nslookup or "name server lookup" is a network administration command-line tool used for querying the Domain Name System to obtain domain name or IP address mapping, or other DNS records. This utility can be used to lookup the specific IP address(es) associated with a domain name. If this utility is unable to resolve this information, there is a DNS issue**.**



A typical DNS lookup is used to determine which IP address is associated with a hostname. A reverse DNS lookup is used for the opposite, to determine which hostname is associated with an IP address. Sometimes reverse DNS lookups are required for diagnostic purposes.

5. Netstat.

Netstat (*network statistics)* is a program that's controlled via commands issued in the command line. It delivers basic statistics on all network activities and informs users on which **ports and addresses** the corresponding connections (TCP, UDP) are running and which ports are open for tasks. The below example illustrates various switches of netstat.



Task 7 : a). Configure and implementation of a Router within a Network using Packet Tracer.

Configure Global Parameters:

Command	**Purpose**
configure terminal Router> enable Router# configure terminal Router(config)#	Enters global configuration mode, when using the console port. If you are connecting to the router using a remote terminal, use the following: telnet router name or address Login: login id Password: ********* Router> enable
Router(config)# hostname Router Router(config)#	hostname name : Specifies the name for the router.
Router(config)# enable secret Griet@14#02&24 Router(config)#	enable secret password: Specifies an encrypted password to prevent unauthorized access to the router
Router(config)# no ip domain-lookup Router(config)#	no ip domain-lookup : Disables the router from translating unfamiliar words (typos) into IP addresses

Configure the Fast Ethernet WAN Interface

Command	**Purpose**

interface type number
Example:
Router(config)# interface fastethernet 4
Router(config-int)
	Enters the configuration mode for a Fast Ethernet WAN interface on the router

Example: Router(config-int)# ip address 192.168.12.2 255.255.255.0 Router(config-int)#	ip address ip-address mask : Sets the IP address and subnet mask for the specified Fast Ethernet interface
no shutdown Example: Router(config-int)# no shutdown Router(config-int)#	Enables the Ethernet interface, changing its state from administratively down to administratively up
exit Example: Router(config-int)# exit Router(config)#	Exits configuration mode for the Fast Ethernet interface and returns to global configuration mode.

Configuring Command-Line Access to the Router:

Command	**Purpose**
line [aux | console | tty | vty] line-number Router(config)# line console 0 Router(config)#	Enters line configuration mode, and specifies the type of line. This example specifies a console terminal for access
password password Router(config)# password Gsbr$$# Router(config)#	Specifies a unique password for the console terminal line
login Router(config)# login Router(config)#	Enables password checking at terminal session login.
exec-timeout minutes [seconds] Router(config)# exec-timeout 5 30 Router(config)#	Sets the interval that the EXEC command interpreter waits until user input is detected. The default is 10 minutes. Optionally, add seconds to the interval value. This example shows a timeout of 5 minutes and 30 seconds. Entering a timeout of 0 0 specifies never to time out
line [aux | console | tty | vty] line-number Router(config)# line vty 0 4 Router(config)#	Specifies a virtual terminal for remote console access.
password password Router(config)# password Gsbr@98# Router(config)#	Specifies a unique password for the virtual terminal line
login Router(config)# login Router(config)#	Enables password checking at the virtual terminal session login.
end Router(config)# end Router#	Exits line configuration mode, and returns to privileged EXEC mode

Summarizing different memories that are used in Cisco Router –

- **RAM** stores the currently working tasks.
- **NVRAM** where startup configuration takes place.
- **ROM** where the information of POST and bootstrap program is available.
- And **Flash Memory** where the operating system of Router IOS is present

b). Configure and examine Network Address Translation (NAT).

NAT Inside and Outside Addresses:

The term inside in a NAT context refers to networks owned by an organization that must be translated. Similarly, the term outside refers to those networks to which the stub network connects, and which are generally not under the control of the organization.

NAT uses the following definitions:

* Inside local address--The IP address that is assigned to a host on the inside network. The address is probably not a legitimate IP address assigned by the NIC or service provider.
* Inside global address--A legitimate IP address (assigned by the NIC or service provider) that represents one or more inside local IP addresses to the outside world
* Outside local address--The IP address of an outside host as it appears to the inside network. Not necessarily a legitimate address, it is allocated from the address space routable on the inside.
* Outside global address--The IP address assigned to a host on the outside network by the owner of the host. The address is allocated from a globally routable address or network space.

NAT types include:

* Static address translation (static NAT)--allows one-to-one mapping between local and global addresses.
* Dynamic address translation (dynamic NAT)--maps unregistered IP addresses to registered IP addresses from a pool of registered IP addresses.
* Overloading--a form of dynamic NAT that maps multiple unregistered IP addresses to a single registered IP address (many to one) using different ports. This method is also known as
* Port Address Translation (PAT). By using PAT (NAT overload), thousands of users can be connected to the Internet using only one real global IP address

i).Static routing



Router configuration:

```
Router>
Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int fa0/0
Router(config-if)#ip add 10.0.0.1 255.0.0.0
Router(config-if)#no shut

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to
up

Router(config-if)#ip nat inside
Router(config-if)#int fa1/0
Router(config-if)#ip add 20.0.0.1 255.0.0.0
Router(config-if)#no shut

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet1/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet1/0, changed state to
up

Router(config-if)#
Router(config-if)#ip nat outside
Router(config-if)#exit

Router(config)#ip nat inside source static 10.0.0.2 200.100.50.25
Router(config)#end
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#
Router#sh ip nat translations
Pro Inside global Inside local Outside local Outside global
--- 200.100.50.25 10.0.0.2 --- ---

Router#
```

To test the connection ping from the terminal



ii).Dynamic routing

Router>
Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int fa0/0
Router(config-if)#ip add 10.0.0.1 255.0.0.0
Router(config-if)#no shut

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Router(config-if)#
Router(config-if)#
Router(config-if)#int fa1/0
Router(config-if)#ip add 20.0.0.1 255.0.0.0
Router(config-if)#no shut

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet1/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet1/0, changed state to up

```
Router(config-if)#
Router(config-if)#exit
Router(config)#
Router(config)#
Router(config)#int fa0/0
Router(config-if)#ip nat inside
Router(config-if)#int fa1/0
Router(config-if)#ip nat outside
Router(config-if)#
Router(config-if)#exit
Router(config)#
Router(config)#access-list 1 permit 10.0.0.0 0.0.0.5
Router(config)#ip nat pool mypool 50.25.10.5 50.25.10.10 netmask 255.0.0.0
Router(config)#ip nat inside source list 1 pool mypool
Router(config)#
```

Task-8 : a).Configure network topology to implement VLANs with using Packet Tracer software.

INTRA VLAN



Switch> Switch>en Switch# Switch#conf t Enter configuration commands, one per line. End with CNTL/Z. Switch(config)#vlan 10 Switch(config-vlan)#name project1 Switch(config-vlan)#int f0/1 Switch(config-if)#switchport mode access Switch(config-if)#switchport access vlan 10 Switch(config-if)#int f0/2 Switch(config-if)#switchport mode access Switch(config-if)#switchport access vlan 10 Switch(config-if)#int f0/7 Switch(config-if)#switchport mode access Switch(config-if)#switchport access vlan 10	Switch(config-if)#vlan 20 Switch(config-vlan)#int f0/3 Switch(config-if)#switchport mode access Switch(config-if)#switchport access vlan 20 Switch(config-if)#int f0/4 Switch(config-if)#switchport mode access Switch(config-if)#switchport access vlan 20 Switch(config-if)#vlan 30 Switch(config-vlan)#name project3 Switch(config-vlan)#int f0/5 Switch(config-if)#switchport mode access Switch(config-if)#switchport access vlan 30 Switch(config-if)#int f0/6 Switch(config-if)#switchport mode access Switch(config-if)#switchport access vlan 30 Switch(config-if)#end Switch#wr

Observe that the PCs of same vlan will ping and other vlans are isolated.

INTER VLAN



Switch> Switch>EN Switch# Switch#conf t Switch(config)# Switch(config)#vlan 10 Switch(config-vlan)#vlan 20 Switch(config-vlan)#vlan 30 Switch(config-vlan)#int f0/1 Switch(config-if)#no shut Switch(config-if)#switchport mode access Switch(config-if)#switchport access vlan 10 Switch(config-if)#int f0/2 Switch(config-if)#switchport mode access Switch(config-if)#switchport access vlan 20 Switch(config-if)#int f0/3 Switch(config-if)#switchport mode access Switch(config-if)#switchport access vlan 30 Switch(config-if)#int g0/1 Switch(config-if)#switchport mode trunk Switch(config-if)#end Switch#wr Building configuration... [OK] **Switch#**	Switch> Switch>en Switch#conf t Switch(config)#hostname SW2 SW2(config)# SW2(config)#vlan 10 SW2(config-vlan)#vlan 20 SW2(config-vlan)#vlan 30 SW2(config-vlan)#int f0/4 SW2(config-if)#switchport mode access SW2(config-if)#switchport access vlan 30 SW2(config-if)#int f0/5 SW2(config-if)#switchport mode access SW2(config-if)#switchport access vlan 20 SW2(config-if)#int f0/6 SW2(config-if)#switchport mode access SW2(config-if)#switchport access vlan 10 SW2(config-if)#int g0/2 SW2(config-if)#sw SW2(config-if)#switchport mode trunk SW2(config-if)#end SW2#wr Building configuration... [OK] **SW2#**

Multilayer Switch Configuration.

Switch> Switch>en Switch# Switch#conf t Switch(config)#hostname MLSW MLSW(config)#vlan 10 MLSW(config-vlan)#vlan 20 MLSW(config-vlan)#vlan 30 MLSW(config-vlan)#exit MLSW(config)# MLSW(config)#int range g0/1-2 MLSW(config-if-range)#switchport trunk encapsulation dot1q MLSW(config-if-range)#switchport mode trunk MLSW(config-if-range)#end After this you will be able to ping in between the same VLANs. But not other vlans. Ex: 192.168.10.1 to 10.2 But you cannot access 192.168.10.1 to 20.1	Below conf. is to access from one pc to all PCs. MLSW#conf t Enter configuration commands, one per line. End with CNTL/Z. MLSW(config)# MLSW(config)#ip routing MLSW(config)#int vlan 10 MLSW(config-if)# MLSW(config-if)#ip add 192.168.10.10 255.255.255.0 MLSW(config-if)#no shut MLSW(config-if)#int vlan 20 MLSW(config-if)# MLSW(config-if)#ip add 192.168.20.20 255.255.255.0 MLSW(config-if)#no shut MLSW(config-if)# MLSW(config-if)#int vlan 30 MLSW(config-if)# MLSW(config-if)#ip add 192.168.30.30 255.255.255.0 MLSW(config-if)#no shut MLSW(config-if)# MLSW(config-if)#end MLSW# MLSW#wr Building configuration... [OK] **MLSW#**

b).Configure network topology and implement static routing using Packet Tracer Software. .**STATIC ROUTING**:



Router 0 Router>en Router# Router#conf t Router(config)# Router(config)#int g0/0/0 Router(config-if)#ip address 10.0.0.3 255.0.0.0 Router(config-if)#no shut Router(config-if)#int s0/2/0 Router(config-if)#ip address 20.0.0.1 255.0.0.0 Router(config-if)#no shut Router(config-if)#exit Router(config)# **Router(config)#ip route 30.0.0.0 255.0.0.0 s0/2/0**	Router 1 Router# Router#conf t Router(config)# Router(config)#int g0/0/0 Router(config-if)#ip address 30.0.0.2 255.0.0.0 Router(config-if)#no shut Router(config-if)# Router(config-if)#int s0/1/0 Router(config-if)#ip add 20.0.0.2 255.0.0.0 Router(config-if)#no shut Router(config-if)#exit Router(config)# **Router(config)#ip route 10.0.0.0 255.0.0.0 s0/1/0** %Default route without gateway, if not a point-to-point interface, may impact performance Router(config)#

Task-9

a). Configure network topology and implement dynamic routing protocol such as RIP, OSPF using Packet Tracer.

RIP



R4 (Router 4)	R5 (Router 5)	R6 (Router 6)
router rip network 10.0.0.0 network 11.0.0.0 network 12.0.0.0 interface GigabitEthernet0/0/0 ip address 10.0.0.1 255.0.0.0 interface Serial0/1/0 ip address 11.0.0.1 255.0.0.0 interface Serial0/1/1 ip address 12.0.0.1 255.0.0.0 no shutdown	router rip network 11.0.0.0 network 192.168.1.0 interface GigabitEthernet0/0/0 ip address 192.168.1.1 255.255.255.0 no shutdown interface Serial0/1/0 ip address 11.0.0.2 255.0.0.0 clock rate 2000000 no shutdown	router rip network 12.0.0.0 network 192.168.2.0 interface GigabitEthernet0/0/0 ip address 192.168.2.1 255.255.255.0 no shutdown interface Serial0/1/0 ip address 12.0.0.2 255.0.0.0 clock rate 2000000 no shutdown

OSPF



R1 (Router 1)	R3 (Router 3)
Router(config)#router ospf 1 Router(config-router)#network 192.168.2.0 255.0.0.0 area 1 Router(config-router)#network 192.168.2.0 0.0.0.255 area 1 Router(config-router)#network 10.0.0.0 0.255.255.255 area 1 Router(config-router)#network 10.0.0.0 0.255.255.255 area 1 Router(config-router)#network 11.0.0.0 0.255.255.255 area 1 Router(config-router)#^Z Router#copy run startup-config	router ospf 1 network 192.168.1.0 0.0.0.255 area 1 network 10.0.0.0 0.255.255.255 area 1 network 12.0.0.0 0.255.255.255 area 1
Router>enable Router# Router#configure terminal Router(config)#interface GigabitEthernet0/0 Router(config-if)#ip address 192.168.2.1 255.255.255.0 Router(config-if)#no shutdown Router(config-if)#exit Router(config)#interface Serial0/0/0 Router(config-if)#clock rate 125000 ********** Router(config-if)#ip address 10.0.0.2 255.0.0.0 Router(config-if)#no shutdown Router(config-if)#exit	interface GigabitEthernet0/0 ip address 192.168.1.1 255.255.255.0 interface Serial0/0/0 ip address 10.0.0.1 255.0.0.0 no shut down interface Serial0/0/0 ip address 10.0.0.1 255.0.0.0 interface Serial0/0/1 ip address 12.0.0.1 255.0.0.0 clock rate 125000 ********** no shut down

Router(config)#interface Serial0/0/1 Router(config-if)# clock rate 125000 Router(config-if)#ip address 11.0.0.1 255.0.0.0 Router(config-if)#ip address 11.0.0.1 255.0.0.0 Router(config-if)#no shutdown	

Router(config)#router ospf 1 Router(config-router)#network 192.168.3.0 0.0.0.255 area 1 Router(config-router)#network 11.0.0.0 0.255.255.255 area 1 Router(config-router)#network 12.0.0.0 0.255.255.255 area 1 Router(config-router)# Router(config)#interface GigabitEthernet0/0 Router(config-if)#ip address 192.168.3.1 255.255.255.0 Router(config-if)#ip address 192.168.3.1 255.255.255.0 Router(config-if)#no shutdown	Router(config)#interface Serial0/0/0 Router(config-if)#ip address 11.0.0.2 255.0.0.0 Router(config-if)#ip address 11.0.0.2 255.0.0.0 Router(config-if)#no clock rate This command applies only to DCE interfaces Router(config-if)#no shutdown Router(config)#interface Serial0/0/1 Router(config-if)# no clock rate This command applies only to DCE interfaces Router(config-if)#ip address 12.0.0.2 255.0.0.0 Router(config-if)#ip address 12.0.0.2 255.0.0.0 Router(config-if)#no shutdown

Task 10:

a) Configure DHCP Server in the Network using packet tracer software.
b) Configure a remote login using SSH and Telnet.

DHCP server:



Router>
Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#int f0/0
Router(config-if)#ip address 10.0.0.1 255.0.0.0
Router(config-if)#no shut

Router(config-if)#ip dhcp pool lan1
Router(dhcp-config)#network 10.0.0.1 255.0.0.0

Router(dhcp-config)#
Router(dhcp-config)#int f1/0
Router(config-if)#ip address 20.0.0.1 255.0.0.0
Router(config-if)#no shut

Router(config-if)#
Router(config-if)#ip dhcp pool lan2

Router(dhcp-config)#network 20.0.0.1 255.0.0.0
Router(dhcp-config)#

After configuring the router, goto every PC and select DHCP to get the ip address from the DHCP pool. After completing this process run the below command to see the IP address allocated**.**

Router#sh ip dhcp binding
IP address Client-ID/ Lease expiration Type
Hardware address
10.0.0.2 00D0.D3CD.5175 -- Automatic
10.0.0.3 000A.41CD.3BB2 -- Automatic
20.0.0.2 0060.5C8D.DBBE -- Automatic
20.0.0.3 0005.5EE5.2223 -- Automatic
20.0.0.4 00E0.B070.0842 -- Automatic

Router# sh run

!
ip dhcp pool lan1
network 10.0.0.0 255.0.0.0
ip dhcp pool lan2
network 20.0.0.0 255.0.0.0

DHCP

Configuring DHCP Server

Beginning in privileged EXEC mode, follow these steps to configure DHCP server.
The following example configures the DHCP server:

Router# **configure terminal**
Router(config)# **ip dhcp included-address 192.168.1.101 192.168.1.150**
Router(config)# **ip dhcp pool**
Router(dhcp-config)# **network 192.168.1.0 255.255.255.0**
Router(dhcp-config)# **domain-name cisco.com**
Router(dhcp-config)# **dns-server 8.8.8.8**
Router(dhcp-config)# **default-router 192.168.1.1**
Router(dhcp-config)# **exit**
Router(config)# **service dhcp vlan1**

Command Purpose

1. configure terminal Enter global configuration mode.
2. ip dhcp pool Create a DHCP server address pool and enters DHCP
pool configuration mode.
Note: If you have changed the parameters of the DHCP server, you must perform a refresh using the **no service dhcp** *interface-type number* command and **service dhcp** *interface-type number* commands.

3. network *network-number mask* Specify the subnet network number and mask of the DHCP address pool.
4. domain-name *domain* Specify the domain name for the client.
5. dns-server *address* Specify the IP address of a DNS server that is available to a DHCP client.
6. default-router *address* Specify the IP address of the default router for a DHCP client.
7. exit Return to privileged EXEC mode.
8. service dhcp *interface-type number* Enable DHCP server on the interface.

10 b) Configure a remote login using SSH and Telnet.

First connect the console cable from PC0 RS232 port to Switch console port.

From PC0 Terminal	
Switch> Switch>en Switch#conf terminal Switch(config)# Switch(config)#interface vlan 1 Switch(config-if)#ip address 10.0.0.2 255.0.0.0 Switch(config-if)#no shut Switch(config-if)#end Switch# Switch#sh run	Switch# Switch#conf t Switch(config)# Switch(config)#username myname password mypass Switch(config)#line vty 0 15 Switch(config-line)#login local Switch(config-line)#transport input telnet Switch(config-line)#
Before Telnet configuration	After Telnet configuration
C:\>telnet 10.0.0.2 *Trying 10.0.0.2 ...* *% Connection timed out; remote host not responding* *C:\>telnet 10.0.0.2* *Trying 10.0.0.2 ...Open* *[Connection to 10.0.0.2 closed by foreign host]*	C:\>telnet 10.0.0.2 Trying 10.0.0.2 ...Open User Access Verification Username: myname Password: Switch>

SSH

Switch#conf t
Switch(config)#
Switch(config)#hostname myswitch
myswitch(config)#ip domain-name mydomain
myswitch(config)#username myname1 password mypass1
myswitch(config)#line vty 0 15
myswitch(config-line)#login local
myswitch(config-line)#transport input ssh
myswitch(config-line)#exit
myswitch(config)#crypto key generate rsa

The name for the keys will be: myswitch.mydomain
Choose the size of the key modulus in the range of 360 to 2048 for your
General Purpose Keys. Choosing a key modulus greater than 512 may take
a few minutes.

How many bits in the modulus [512]:
% Generating 512 bit RSA keys, keys will be non-exportable...[OK]

myswitch(config)#exit

Now test SSH connection

C:\>ssh -l myname1 10.0.0.2
Password:

myswitch>

Task 11 a). Establish a webserver connection using the PCs browser.



Configure the webserver connection and DNS server





11b) Install wireshark and view ii). Network Traffic and iii).Examine ethernet frames View Wired and Wireless NIC information.

Objectives:

a. Capture and analyse local ICMP data in wireshark
b. Capture and analyse Remote ICMP data in wireshark

Install wireshark latest version.

Step 1: Retrieve your PC interface addresses.

For this lab, you will need to retrieve your PC IP address and its network interface card (NIC) physical address, also called the MAC address.
a. Open a command window, type **ipconfig /all**, and then press Enter.
b. Note the IP address of your PC interface, its description, and its MAC (physical) address

Steps

1: Open wireshark and start capturing the packets. The data lines will appear in different colors based on protocol.

2. open command prompt and
   ping any url. Ex: ping google.com
   ping sdc.in
   ping yahoo.com
   ping cisco.com

3. Stop capturing the packets.

Step 3: Examine the captured data.

Wireshark data is displayed in three sections: 1) The top section displays the list of PDU frames captured with a summary of the IP packet information listed; 2) the middle section lists PDU information for the frame selected in the top part of the screen and separates a captured PDU frame by its protocol layers; and 3) the bottom section displays the raw data of each layer. The raw data is displayed in both hexadecimal and decimal form.

Click the first ICMP request PDU frames in the top section of Wireshark. Notice that the Source column has your PC IP address, and the Destination column contains the IP address you pinged.



4. Go to the filter bar and type and check the following protocols

ICMP enter.
DNS
TCP
UDP
ARP

And observe the packets.



Examine the Ethernet frame fields in the middle section:



View Wired and Wireless NIC information:

Step 1: Use the Network and Sharing Center.

a. Open the Network and Sharing Center by clicking the Windows Start button > Control Panel > View network status and tasks under Network and Internet heading in the Category View.
b. In the left pane, click the Change adapter settings link.
c. The Network Connections window displays, which provides the list of NICs available on this PC. Look for your Local Area Connection and Wireless Network Connection adapters in this window.

Or

1. Right click on start (windows button)
Settings – status – properties

Compare with:

Open a command window prompt and type **ipconfig /all**
And observe the above addresses, both must be same.

Task-12

a). Adding IoT devices to Smart Homes using Packet Tracer
b). Connect and Monitor IoT Devices using Packet Tracer






RadiusServer
Physical
Config
Services
Desktop
Programming
Attributes
SERVICES
HTTP
DHCP
DHCPv6
TFTP
DNS
SYSLOG
AAA
NTP
EMAIL
FTP
IoT
VM Management
Radius EAP
AAA
Service
On
Off
Radius Port
1645
Network Configuration
Client Name
Client IP
Secret
ServerType
Radius
Client Name
Client IP
Server Type
Key
1
home
192.168.0.1
Radius
pass1234
Add
Save
Remove
User Setup
Username
Password
Username
Password
1
fan
fan
2
led
led
3
ac
ac
Add
Save
Remove
Top


Home Router
Physical
Config
GUI
Attributes
Wireless Tri-Band Home Router
Firmware Version: v0.9.7
Wireless
Setup
Wireless
Security
Access Restrictions
Applications & Gaming
Administration
Status
Basic Wireless Settings
Wireless Security
Guest Network
Wireless MAC Filter
Advanced Wireless Settings
Basic Wireless Settings
Help...
2.4 GHz
Network Mode:
Auto
Network Name (SSID):
home
SSID Broadcast:
Enabled
Disabled
Standard Channel:
1 - 2.412GHz
Channel Bandwidth:
Auto
5 GHz - 2
Network Mode:
Auto
Network Name (SSID):
Default
SSID Broadcast:
Enabled
Disabled
Standard Channel:
Auto
Top


Home Router
Physical
Config
GUI
Attributes
Wireless Tri-Band Home Router
Firmware Version: v0.9.7
Wireless
Setup
Wireless
Security
Access Restrictions
Applications & Gaming
Administration
Status
Basic Wireless Settings
Wireless Security
Guest Network
Wireless MAC Filter
Advanced Wireless Settings
Wireless Security
Help...
2.4 GHz
Security Mode:
WPA2 Enterprise
Encryption:
AES
RADIUS Server:
192
168
1
10
RADIUS Port:
1645
Shared Secret:
pass1234
Key Renewal:
3600
seconds
5 GHz - 1
Security Mode:
Disabled
5 GHz - 2
Security Mode:
Disabled
Top


fan
Specifications
I/O Config
Physical
Config
Thing Editor
Programming
Attributes
GLOBAL
Settings
Algorithm Settings
Files
INTERFACE
Wireless0
Bluetooth
Wireless0
Port Status
Bandwidth
11 Mbps
MAC Address
0060.472C.D249
SSID
home
Authentication
Disabled
WEP
WEP Key
WPA-PSK
WPA2-PSK
PSK Pass Phrase
WPA
WPA2
User ID
fan
Password
fan
802.1X
Method:
MD5
User Name
Password
Encryption Type
AES
IP Configuration
DHCP
Static
IPv4 Address
169.254.210.73
Subnet Mask
255.255.0.0
IPv6 Configuration
Top
Advanced



Add more IoT devices and monitor their functioning like On and Off.