COMPLETE GUIDE · ENGLISH

Rovunet for Android

Several routes to your own server, in one app

Installing and updating, importing configurations and subscriptions, connecting, testing, Soar scanning, security and troubleshooting.

5	4	2	4
protocol families	languages	taps to connect	Soar scan modes

Version
0.3.0-alpha15.4 · code 31

Android
7.0 or later

License
AGPL-3.0

Community
t.me/RovunetVPN

Contents

Read sections 2 to 4 to get connected for the first time; the rest explains testing, scanning, security and what to do when something does not work.

01 **Overview**
What the app does

02 **Install and update**
Requirements, first install, upgrades

03 **Importing configurations**
Links, QR, files and subscriptions

04 **Collections and connecting**
Select, connect, approve, stop

05 **Tests, DNS and Soar scanning**
Measuring paths and finding resolvers

06 **Security, privacy and settings**
Credentials, sharing, appearance

07 **Troubleshooting**
Common problems and safe reports

08 **Resources and support**
Links, license and support

01 Overview

Rovunet is a multi-protocol Android VPN client for reaching your own server by several routes. DNS tunnels, SSH transports, HTTPS proxies and Xray-backed profiles live in one interface, and related paths stay together in named collections.

Collections

Paths of one server and account are grouped; your explicit choice and completed measurements are remembered.

Direct connection

First tap selects a path, the second connects. No mandatory ping or resolver scan before connecting.

Subscriptions

Import an HTTPS subscription once and update it later; local edits and stable profile IDs are kept.

Real HTTPS tests

Measures HTTPS (HTTP 204) through the actual tunnel with certificate checks, success ratio and latency spread.

Soar scanner

Quick, Advanced, E2E and Prism modes with authenticated Soar handshakes; UDP and TCP tested separately.

Security

Encrypted stored credentials, SSH and self-signed identity approval, password-encrypted backups.

Interface

Persian, English, Simplified Chinese and Russian; light, dark and AMOLED themes; quick controls.

Safe reports

Local stage/code reports without addresses or credentials, shared only when you choose.

VLESS WS · VLESS + REALITY · VLESS + XHTTP · Hysteria 2 · WireGuard · NaïveProxy · SSH over TLS · SSH · SOCKS5 · DNSTT · NoizDNS · VayDNS · Slipstream · Soar · Tor + bridges


You need a server

Rovunet does not provide free accounts. Use configurations from your own server, for example one managed by Rovunet Panel, or from an operator you trust.

02 Install and update

Item	Detail
Android	7.0 (API 24) or later
Architectures	ARM64, ARM32 and x86_64 (Naive and Tor are not available on x86_64)
Package	`app.veyra.client`, signed with the production certificate introduced in alpha14

Item	Detail
Certificate SHA-256	`1e40bd201489a8209043e346255772823d9d52ee21b468bdef2c152d239bc416`
Where	GitHub Releases only; no Google Play, App Store or desktop version



Upgrading

- Public alpha14 and alpha15 update **in place**: same package and signer. Do not uninstall and do not clear data.
- Their older updater does not recognize dotted revisions such as 15.4, so this time download the Full APK directly from Releases and install it over the existing app. From 15.4 on, the in-app updater recognizes later dotted revisions.
- Settings → Check for updates downloads a compatible GitHub release, verifies checksum, package, version and signer, then asks Android to install it. Installation is never silent; an unrelated signer is rejected.
- Historical alpha11 and private test builds have different identities and cannot be upgraded in place; see the migration guide in the repository.

> **!** **Keep a readable copy**
>
> Before any reinstall, export a password-encrypted backup and check that it imports. Locked profiles are not included in bulk export; device-bound profiles may need the original link from your operator.


03 Importing configurations

Use **+** → **Import** for text, a supported file or a QR code. Review the preview and confirm.

Format	Notes
`rovunet://`	Native format (v33) with collection metadata and lossless credentials
`veyra://` , `slipnet://`	Compatible aliases of the native format
`vless://` , `hysteria2://`	Supported standard links
WireGuard INI	Single-peer configuration files
HTTPS subscription	JSON feed such as `https://example.com/sub/<token>.json` from Rovunet Panel


Unknown future versions are rejected rather than partly imported: update the app instead of editing version or security fields. Arbitrary core JSON, AmneziaWG and every WireGuard URI dialect are not supported.

Subscriptions




- On an error the dialog and the form stay, so nothing has to be typed again.
- A duplicate source URL is not added twice; the app points you to Update.
- Importing a new subscription does not interrupt the current connection.
- Share small collections as QR or PNG; large ones are shared as files.

04 Collections and connecting



- A remembered path is already selected when you return; edit, delete and menu controls never connect.
- The collection power button starts the remembered path or an eligible first path, without an automatic ping. An explicit choice is never replaced by another protocol silently.
- Use the main or collection power control, or the path menu, to cancel Connecting or to disconnect.
- **Connected** means the tunnel is ready; it is not proof that every site is reachable. Zero counters while idle are not a reason to disconnect.
- Background work never approves a new identity, and a changed identity is never accepted silently.

Which path to try first



05 Tests, DNS and Soar scanning

Tests are separate from connecting: a failed measurement never blocks a manual connection.

Collection tests

- Run a collection test while disconnected. Each path is checked with real HTTPS (HTTP 204) through the actual tunnel, with certificate validation and a limited alternative target.
- Results show the last test time, success ratio and latency spread; they are short samples, not download speed. Results from another network are marked separately.
- Direct paths are tested before UDP and DNS fallback. Entering the DNS fallback phase asks for your consent; DNS testing can take minutes and can be cancelled.

Soar scanner modes

Mode	What it checks
Quick	One authenticated Soar handshake with the same domain and Ed25519 key; no generic DNS score filter
Advanced	DNS diagnostics only; its score is not proof that Soar connects

Mode	What it checks
E2E	A working tunnel and then an HTTP 204 test address; for Soar + SSH, the SSH account with an already approved server identity
Prism	Several authenticated Soar handshakes with a repeat count and success threshold (default timeout 15 s); no DNSTT challenge is sent

1. **Disconnect the VPN**

   Scan on the network you want to use, with the VPN off.

2. **Start with Quick**

   Try known resolvers with **UDP and TCP**, then UDP and TCP separately, and compare.

3. **Confirm with Prism and E2E**

   Run them on the same list; on a slow network raise the Prism timeout.

4. **Keep what works**

   Save the mode that works on your network. If every result is zero, send only the safe report and the mode/transport name.

✓ **Soar connection modes**

New Soar and Soar + SSH profiles default to **UDP + TCP**. Automatic starts with UDP and may add TCP later; TCP only and UDP only are also available. Existing and imported choices are never changed. SSH over Soar also needs the server to allow the SSH destination and port.

06 Security, privacy and settings

Encrypted credentials

Stored secrets use Android Keystore-backed encryption. An unreadable record is marked for explicit recovery, never silently erased.

Identity approval

SSH and self-signed TLS identities need your approval; validated TLS is required elsewhere.

Locks and sharing limits

Locked profiles and collection sharing restrictions stay in effect in supported export paths (a client policy, not a guarantee against modified clients).

Portable backups

Password-encrypted backups; use a strong password and check that a backup imports before relying on it.

Languages and themes

Persian, English, Simplified Chinese and Russian; light, dark and AMOLED. Protocol names and addresses stay untranslated.

Quick controls

Notification, widget and quick-settings tile, depending on Android permissions and launcher.

Encryption scope

Plain SOCKS5 does not encrypt the transport, and DoH alone encrypts only DNS, not all traffic.

07 Troubleshooting

Symptom	What to do
Connected but pages do not open	Run the collection test; try another path in the collection. Connected means tunnel readiness only.
Subscription update refused	Disconnect the VPN, then Update. Use Import only for a new source.
Soar finds no resolvers	Scan with the VPN off, use UDP and TCP, then Prism with a longer timeout; send the safe report.
SSH over a tunnel fails	The server must allow the SSH destination and port in addition to a working base tunnel.
Identity changed warning	Do not approve blindly; confirm the new fingerprint with your operator.
Crash after updating	Reopen the app and share the safe report with the time; old exit records can remain after an update.
Limited account lost paths	Your operator may give limited accounts only metered paths; update the subscription.

Reporting a problem

- Include the app and Android versions, phone model, network type, protocol, steps to reproduce and whether ordinary pages open.
- Attach the **safe report**: typed stages and codes, Soar mode and traffic snapshots, without addresses, accounts or credentials. It stays on the phone until you share it.
- Detailed debug logs may contain sensitive data; review them before sharing.
- Never post configuration links, subscription links, passwords, private keys or device IDs in public groups or issues.

Known limits

No automatic failover between paths, no download-speed benchmark and no store or desktop versions. No protocol guarantees access through every network.

08 Resources and support

Telegram

t.me/RovunetVPN · news, questions and help

Download

github.com/msVPNco/rovunet-android/releases/latest

Server panel

github.com/msVPNco/rovunet-panel

User guide

docs/USER_GUIDE.md in four languages in the repository

Donations are voluntary and never required to use the app: **USDT on Tron (TRC20) only** to `TG3Mhou3pdq9KaFgJSHjDiDx2ahhJuHvbJ`.

License: AGPL-3.0; Xray-core is MPL-2.0. Rovunet is based on SlipNet 2.5.6 Full by Anonvector and is an independent project, not affiliated with SlipNet.

Early release

Rovunet is an alpha under active development. Test the paths you need on your own network.