# Architecture of DMTCP

#### Gene Cooperman

#### February, 2014

This is intended as a gentle introduction to the architecture of DMTCP. Shorter descriptions are possible. For a low-level description with references to code in the implementation, see doc/restart\_algorithm.txt. For the general use of plugins, see doc/plugin\_tutorial.pdf . DMTCP uses plugins internally from DMTCP\_ROOT/src/plugin. DMTCP also offers optional plugins (not enabled by default) to end users. Thes come in two flavors: DMTCP\_ROOT/plugin (fully supported) and DMTCP\_ROOT/contrib (newer plugins, possibly contributed by third parties).

#### 1. Usage of DTMCP:

- 1: dmtcp\_launch a.out
- $2: \ {\tt dmtcp\_command} \ {\tt --checkpoint}$ 
  - $\hookrightarrow$  ckpt\_a.out.\*.dmtcp
- 3: dmtcp\_restart ckpt\_a.out.\*.dmtcp

DMTCP offers a --help command line option along with additional options both for configure and for the individual DMTCP commands. To use DMTCP, just prefix your command line with dmtcp\_launch.

## 2. dmtcp\_launch a.out


The command dmtcp\_launch a.out is roughly equivalent to:

- 1: dmtcp\_coordinator --background (if not already running)
- 2: LD\_PRELOAD=libdmtcp.so a.out

The dmtcp\_launch command will cause a coordinator process to be launched on the local host with the default DMTCP port (if one is not already available).

DMTCP implements a coordinator process because DMTCP can also checkpoint distributed computations across many computers. The user can issue a command to the coordinator, which will then relay the command to each of the user processes of the distributed computation.

Note that a *DMTCP computation* is defined to be a coordinator process and the set of user processes connected to that coordinator. Therefore, one can have more than one DMTCP computation on a single computer, each computation having its own unique coordinator.



The coordinator is *stateless*. If the computation is ever killed, one needs only to start an entirely new coordinator, and then restart using the latest checkpoint images for each user process.

LD\_PRELOAD is a special environment variable known to the loader. When the loader tries to load a binary (a.out, in this case), the loader will first check if LD\_PRELOAD is set (see 'man ld.so'). If it is set, the loader will load the binary (a.out) and then the preload library (libdmtcp.so) before running the 'main()' routine in a.out. (In fact, dmtcp\_launch may also preload some plugin libraries, such as pidvirt.so (starting with DMTCP-2.0) and set some environment variables such as DMTCP\_DLSYM\_OFFSET.)

When the library libdmtcp.so is loaded, any top-level variables are initialized, before calling the user main(). If the top-level variable is a C++ object, then the C++ constructor is called before the user main. In DMTCP, the first code to execute is the code below, inside libdmtcp.so:

```
dmtcp::DmtcpWorker dmtcp::DmtcpWorker::theInstance ( true );
```

This initializes the global variable, the Instance via a call to new dmtcp::DmtcpWorker::DmtcpWorker(true). (Here, dmtcp is a C++ namespace, and the first DmtcpWorker is the class name, while the second DmtcpWorker is the constructor function. If DMTCP were not using C++, then it would use a direct way to use GNU gcc attributes to directly run a constructor function.)

Note that DMTCP is organized in at least two layers. The lowest layer is MTCP (mtcp subdirectory), which handles single-process checkpointing. The higher layer is again called DMTCP (dmtcp subdirectory), and delegates to MTCP when it needs to checkpoint one process. MTCP does not require a separate DMTCP coordinator.

So, at startup, we see:

```
1: a.out process:
```

- 2: primary user thread:
- 3: new DmtcpWorker(true):
- 4: Create a socket to the coordinator
- 5: Register the signal handler that will be used for checkpoints.

The signal handler is mtcp/mtcp.c:stopthisthread()


The default signal is STOPSIGNAL (default: SIGUSR2)

The signal handler is registered by mtcp\_sigaction(STOPSIGNAL, &act, &old\_act) in mtcp/mtcp.c

- 6: Create the checkpoint thread Call pthread\_create (&checkpointhreadid, NULL, checkpointhread, NULL) in mtcp/mtcp.c
- 7: Wait until the checkpoint thread has initialized.
- 8: checkpoint thread:
- 9: checkpointhread(dummy): [from mtcp/mtcp.c]
- 10: Register a.out process with coordinator
- 11: Tell user thread we're done
- 12: Call select() on socket to coordinator
- 13: primary user thread:
- 14: new DmtcpWorker(true): [continued from above invocation]
- 15: Checkpoint thread is now initialized. Return.
- 16: main() [User code now executes.]

PRINCIPLE: At any given moment either the user threads are active and the checkpoint thread is blocked on select(), or the checkpoint thread is active and the user threads are blocked inside the signal handler, stopthisthread().

### 3. Execute a Checkpoint:



- 1: checkpoint thread:
- 2: return from select()
- 3: receive CKPT message
- 4: send STOPSIGNAL (SIGUSR2) to each user thread
- 5: See: retval = mtcp\_sys\_kernel\_tgkill(motherpid, thread-¿tid, STOPSIGNAL); in mtcp/mtcp.c See mtcp\_state\_set (&(thread -> state), ST\_SUSPINPROG, ST\_SIGENABLED) and mtcp\_state\_set (&(thread -> state), ST\_SUSPINPROG) in mtcp/mtcp.c
- 6: mtcp\_state\_set(MtcpState \* state, int value, int oldval) is defined in mtcp/mtcp\_state.c, and does its work through a Linux per-thread futex (similar to a mutex).
- 7: [Recall that dmtcpWorker created a signal handler, STOPSIGNAL (default: SIGUSR2)
- 8: Each user thread in the signal handler for STOPSIGNAL will block on the per-thread futex.
- 9: The checkpoint thread does the checkpoint.
- 10: Release each thread from its per-thread futex. See mtcp\_state\_set (&(thread -> state), ST\_RUNENABLED, ST\_SUSPENDED) in mtcp/mtcp.c
- 11: Call select() on the socket to the coordinator and again wait for messages from the coordinator.

### 4. Checkpoint strategy (overview)

- 1: Quiesce all user threads (using STOPSIGNAL (SIGUSR2), as above)
- 2: Drain sockets
  - (a) Sender sends a "cookie"
  - (b) Receiver receives until it sees the "cookie"

Note: Usually all sockets are "internal" — within the current computation. Heuristics are provided for the case of "external" sockets.

- 3: Interrogate kernel state (open file descriptors, file descriptor offset, etc.)
- 4: Save register values using setcontext (similar to setjmp) in mtcp/mtcp.c
- 5: Copy all user-space memory to checkpoint image To find all user-space memory, one can execute: cat /proc/self/maps
- 6: Unblock all use threads

### 5. Principle: DMTCP is contagious

New Linux "tasks" are created in one of three ways:

- 1. new thread: created by pthread\_create() or clone()
- 2. new process: created by fork()
- 3. new remote process: typically created by the 'system' system call:
  system("ssh REMOTE\_HOST a.out");

DMTCP makes sure to load itself using wrapper functions.

### 6. Principle: One DMTCP Coordinator for each DMTCP Computation

One may wish to run multiple DMTCP-based computations on a single host. This is easily done by using the --host and --port flags of dmtcp\_launch or of dmtcp\_coordinator. If not specified, the default values are localhost and port 7779. By using dmtcp\_command, one can communicate a checkpoint or other request to one's preferred coordinator (again by specifying host and port, if one is not using the default coordinator).

In the simplest case, the user invokes only dmtcp\_launch, with no flags. The dmtcp\_launch command then looks for an existing coordinator at localhost:7779. If none is found, dmtcp\_launch invokes dmtcp\_coordinator with those default values, localhost:7779.

Thus, an occasional issue occurs when two users on the same host each invoke dmtcp\_launch with default parameters. They cannot both use the same coordinator. Similarly, a single user may want to launch two independent copmutations, and independently checkpoint them. If the user invokes dmtcp\_launch (default parameters) for both computation, then there will only be one coordinator. So, in the view of DMTCP, there will only be a single computation, and a checkpoint command will checkpoint the processes of both computations.

### 7. Plugins, and other End-User Customizations

DMTCP offers a rich set of features for customizing the behavior of DMTCP. In this short overview, we will point to examples that can easily be modified by an end-user.

**DMTCP Plugins.** *DMTCP plugins* are the most general way to customize DMTCP. Examples are in DMTCP-ROOT/test/plugin/. A dynamic library (\*.so) file is created to modify the behavior of DMTCP. The library can write additional wrapper functions (and even define wrappers around previous wrapper functions). The library can also register to be notified of *DMTCP events*. In this case, DMTCP will call any plugin functions registered for each event. Examples of important events are e.g. prior to checkpoint, after resume, and after restart from a checkpoint image. As of this writing, there is no central list of all DMTCP events, and names of events are still subject to change.

Plugin libraries are preloaded after libdmtcp.so. As with all preloaded libraries, they can initialize themselves before the user's "main" function, and at run-time, plugin wrapper functions will be found in standard Linux library search order prior to ordinary library functions in libc.so and elsewhere.

For example, the sleep2 plugin example uses two plugins. After building the plugins, it might be called as follows:

In a more involved example, whenever ./configure --enable-ptrace-support is specified, then DMTCP will use the plugin DMTCP\_ROOT/plugin/ptrace/ptracehijack.so. A new plugin to provide PID/TID virtualization is currently planned. As with support for ptrace, a more modular structure for PID/TID virtualization will be easier to maintain.

**Dmtcpaware.** The dmtcpaware interface is an obsolete customization mechanism that is no longer supported in DMTCP-2.2 and beyond.

MTCP. In DMTCP-2.1 and earlier, the MTCP component of DMTCP could be compiled to run standalone, with opportunities for hook functions using weak symbols. MTCP has now been almost entirely re-written, and is now tightly integrated with DMTCP. For thos who wished to use the prior MTCP arhitecture (just the checkpoint thread, but no separate coordinator), a plugin with those features is planned for the future.

### 8. Implementation of Plugins

The implementation techniques of wrapper functions and pid/tid virtualization we part of the DMTCP implementation not too long after the initial offering of DMTCP. More recently, this functionality was wrapped into a high level abstraction, plugins. This section emphasizes the implementation of these features. For information on using plugins, and writing your own, see doc/plugin-tuorial.pdf .

#### a. Wrapper functions

Wrapper functions are functions around functions. DMTCP creates functions around libc.so functions. Wrapper functions are typically created using dlopen/dlsym. For example, to define a wrapper around libc:fork(), one defines a function fork() in libdmtcp.so (see extern "C" pid\_t fork() in execurappers.cpp).

Continuing this example, if the user code calls fork(), then we see the following progression.

a.out:call to fork()  $\longrightarrow$  libdmtcp.so:fork()  $\longrightarrow$  libc.so:fork()

The symbol libdmtcp.so:fork appears before libc.so:fork in the library search order because libdmtcp.so was loaded before libc.so (due to LD\_PRELOAD).

Next, the wrapper around pthread\_create remembers the thread id of the new thread created. The wrapper around fork ensures that the environment variable LD\_PRELOAD is still set to libdmtcp.so. If LD\_PRELOAD does not currently include libdmtcp.so, then it is reset to include libdmtcp.so before the call to fork(), and then LD\_PRELOAD is reset to the original user value after fork().

The wrapper around system (in the case of creating remote processes) is perhaps the most interesting one. See 'man system' for a description of the call system. It looks at an argument, for example "ssh REMOTE\_HOST a.out", and then edits the argument to "ssh REMOTE\_HOST dmtcp\_launch a.out" before calling system. Of course, this works only if dmtcp\_launch is in the user's path on REMOTE\_HOST. This is the responsibility of the user or the system administrator.

#### b. PID/TID Virtualization

Any system calls that refer to a process id (pid) or thread id (tid) requires a wrapper. DMTCP then translates between a virtual pid/tid and the real pid/tid. The user code always sees the virtual pid/tid, while the kernel always sees the real pid/tid.

#### c. Publish/Subscribe

Plugins also offer a publish/subscribe service for situations where a DMTCP computation contains more than one process, and the user processes must coordinate with each other. Details are in  $doc/plugin\_tutorial.pdf$ .