Sample 8-2

離散コサイン変換

可分離変換

画像処理特論

村松 正吾

動作確認: MATLAB R2023a

Discrete cosine transform

Separable transforms

Advanced Topics in Image Processing

Shogo MURAMATSU

Verified: MATLAB R2023a

準備

(Preparation)

close all

2変量の配列定義

(Definition of bivariate array)

$$X = [02;46]$$

$$X = 2 \times 2$$

$$0$$

$$4$$

単変量変換行列の定義

(Definition of univariate transform)

• 回転行列(rotation matrix)

$$\mathbf{A}_{\theta} = \begin{pmatrix} \cos \theta & -\sin \theta \\ \sin \theta & \cos \theta \end{pmatrix}$$

行列 A_θによる変換

$$\mathbf{y} = \mathbf{A}_{\theta} \mathbf{x}$$

Atheta = @(theta) [cos(theta) -sin(theta); sin(theta) cos(theta)];

```
theta = -pi/4;
A = Atheta(theta)
```

```
A = 2×2
0.7071 0.7071
-0.7071 0.7071
```

順変換の分離処理

(Separate process of the forward transform)

```
\mathbf{Y} = \mathbf{A}\mathbf{X}\mathbf{A}^T
```

```
fwdT = @(x) A*x*A.';
Y = fwdT(X)
```

```
Y = 2×2
6.0000 2.0000
4.0000 0.0000
```

逆変換の分離処理

(Separate process of the inverse transform)

2.0000

6.0000

$$\mathbf{X} = \mathbf{A}^{-1} \mathbf{Y} \mathbf{A}^{-T}$$

```
invA = inv(A)

invA = 2×2
    0.7071    -0.7071
    0.7071    0.7071

invT = @(y) invA*y*invA.';
R = invT(Y)
R = 2×2
```

基底展開

(Basis expansion)

-0.0000

4.0000

```
B00 = invT([1 0; 0 0])

B00 = 2×2
0.5000 0.5000
0.5000 0.5000

B01 = invT([0 1; 0 0])
```

```
-0.5000 0.5000
-0.5000 0.5000
```

```
-0.5000 -0.5000


0.5000 0.5000

B11 = invT([0 0; 0 1])

B11 = 2×2

0.5000 -0.5000
```

```
hfig1 = figure(1);
hfig1.Color = 0.9*[1 1 1];
subplot(2,2,1)
imshow(B00+.5)
subplot(2,2,2)
imshow(B01+.5)
subplot(2,2,3)
imshow(B10+.5)
subplot(2,2,4)
imshow(B11+.5)
```



```
Y(1,1)*B00 + Y(1,2)*B01 + Y(2,1)*B10 + Y(2,2)*B11
```

ans = 2×2 -0.0000 2.0000

 $B10 = 2 \times 2$

-0.5000

0.5000

4.0000 6.0000

© Copyright, Shogo MURAMATSU, All rights reserved.