

# Displacement Current

by Tony Shing

## Overview:

- Definition of current, conservation of charge
- Fixing Ampere's law - displacement current

In electromagnetism, theoretically every problem can be solved through a set of PDEs called the **Maxwell Equations**.

$$\begin{aligned}\vec{\nabla} \cdot \vec{E} &= \frac{\rho}{\epsilon_0} & \vec{\nabla} \cdot \vec{B} &= 0 \\ \vec{\nabla} \times \vec{E} &= -\frac{\partial \vec{B}}{\partial t} & \rightarrow \vec{\nabla} \times \vec{B} &= \mu_0 \vec{J} + \mu_0 \epsilon_0 \frac{\partial \vec{E}}{\partial t}\end{aligned}$$

However, a *system of PDEs* is too complicated to be solved. So we need to learn different "tricks" to avoid them, which are enough for some simple scenarios.

In this note, we will discuss why it is necessary to add the second term in Ampere's law.

## 1 Charge Conservation

In magnetostatics, we describe everything by using current as the source. But when we come to the dynamics part of E&M, we should treat charge as the only real source, while current is a distribution of velocity of the charges.

### 1.1 Definition of Current

To inter-convert the two perspectives, we now define current by its relation to charge as:

Current = Rate of charge's flow into/out of a volume

Across textbooks, this definition can appear as different formulae.

1. "Wire" description - Consider the volume to flow through to be a line. Current can then be defined by counting the total amount of charge  $Q$  through the wire within a duration  $t$ .

$$I \stackrel{\text{def}}{=} \frac{dQ}{dt} \quad \text{or simply} \quad I \stackrel{\text{def}}{=} \frac{Q}{t} \quad \left( \begin{array}{l} \text{For people} \\ \text{who can't do} \\ \text{calculus} \end{array} \right)$$




2. **"Cylinder" description** - Magnify the wire to become a straight cylinder. Current can be defined by counting the total amount of charge flowing into/out of the cylinder.

$$I = \frac{dQ}{dt} \Rightarrow I = \frac{d}{dt} [(\text{Charge per particle}) (\# \text{ of particle}) (\text{Volume of cylinder})] = \frac{d}{dt} [qn(AL)]$$

If we assume that all the charges are moving at the same velocity - their average velocity  $\bar{v} \sim \frac{dL}{dt}$ , while the number density / cross-section of the wire being constant of time. Then it is simplified to the familiar formula in textbooks:

$$I \stackrel{\text{def}}{=} nAq\bar{v}$$

3. **"Microscopic" description** - If we want the exact current distribution at each position instead of taking average, we may first abstractly treated the wire as a surface, just like the water pipe we have learnt in Gauss's law.




Then the current can be described with integration over in-flux / out-flux on the surface.

$$\begin{aligned} I = nq\bar{v}A &\Rightarrow I_{\text{total}} = \iint nq\vec{v} \cdot d\vec{s} \\ &= \iint \rho\vec{v} \cdot d\vec{s} \\ &= \iint \rho(\vec{r}) \vec{v}(\vec{r}) \cdot d\vec{s} \end{aligned}$$

↓  
 $nq = (\# \text{ of particle}) (\text{charge per particle}) \sim \text{Charge density}$   
 $\rho \text{ and } \vec{v} \text{ can be different at different position}$   
 $\therefore \text{should be treated as functions of position}$

Also, recall the conversion between line current element and volume current element,

$$\begin{aligned} I \cdot (\text{Unit length}) &\sim I d\vec{l} = \vec{J} d\tau \sim \vec{J} \cdot (\text{Unit volume}) \\ &\Rightarrow I = \vec{J} \cdot d\vec{s} \sim \vec{J} \cdot (\text{Unit area}) \\ &\Rightarrow I_{\text{total}} = \iint \vec{J} \cdot d\vec{s} \end{aligned}$$



Comparing the results, we now have a new relation between current density and the flow distribution of charges.


$$\vec{J}(\vec{r}) \stackrel{\text{def}}{=} \rho(\vec{r})\vec{v}(\vec{r})$$

## 1.2 Continuity Equation

We can write the simplest description of charge conservation as

$$(\text{Current flow into region}) - (\text{Current flow out of region}) = \frac{d}{dt} (\text{Charge enclosed in region})$$

i.e.  $I_{\text{in}}(t) - I_{\text{out}}(t) = \frac{d}{dt} Q_{\text{enc}}(t)$



This relation should hold for any time  $t$ . Furthermore, we can write this relation using the fancier density distributions:

- Charge → Volume charge density


$$Q_{\text{enc}}(t) \rightarrow \iiint_{\text{region}} \rho(\vec{r}, t) d\tau$$

- Current → Volume current density

$$I_{\text{in/out}}(t) \rightarrow \iint_{\substack{\text{surfaces} \\ \text{with} \\ \text{in/out-flux}}} \vec{J}(\vec{r}, t) \cdot d\vec{s}$$

To visualize in the microscopic view, we can think of some current flowing through a region in the wire. The surface that wraps the region can be separated into 2 pieces:

- One that contains all the in-flux of  $\vec{J}$ .
- The other contains all the out-flux of  $\vec{J}$ .



By writing as integrals, we can combine the flux on the two surfaces as one integral through a closed surface:

$$(\text{In-flux of current}) - (\text{Out-flux of current}) = -(\text{Net Out-flux of current})$$

↑  
By convention,  
out-flux = +ve

i.e.  $\iint_{\substack{\text{surface} \\ \text{with} \\ \text{in-flux}}} \vec{J} \cdot d\vec{s} - \iint_{\substack{\text{surface} \\ \text{with} \\ \text{out-flux}}} \vec{J} \cdot d\vec{s} = - \iint_{\substack{\text{surface} \\ \text{around} \\ \text{the region}}} \vec{J} \cdot d\vec{s}$

So that the conservation relation becomes:

$$-\left(\text{Net Out-flux of current}\right) \sim -\iint_{\substack{\text{surface} \\ \text{around} \\ \text{the region}}} \vec{J} \cdot d\vec{s} = \frac{d}{dt} \iiint_{\text{region}} \rho d\tau \sim \frac{d}{dt} (\text{Enclosed charge})$$

This is the integral form of the equation of charge conservation. We can also convert it into its differential form by divergent theorem.

$$\begin{aligned} -\iint_{\substack{\text{surface} \\ \text{around} \\ \text{the region}}} \vec{J} \cdot d\vec{s} &= \frac{d}{dt} \iiint_{\text{region}} \rho d\tau \\ \text{Divergent Theorem} \downarrow & \quad \rho \text{ depends on position} \\ -\iiint (\vec{\nabla} \cdot \vec{J}) \cdot d\tau &= \iiint \frac{\partial}{\partial t} \rho d\tau \\ \vec{\nabla} \cdot \vec{J} &= -\frac{\partial \rho}{\partial t} \end{aligned}$$

This is a PDE known as the **continuity equation of charge**. For example, we can use it to predict the distribution of current given that we know the initial charge distribution. But in practice, it is more often used in theoretical derivations.

---

## 2 Displacement Current


### 2.1 Enclosed by A Loop?

To understand the following section, we first need to rigorously define what it means by "enclosed by a loop". Recall the Stoke's theorem,,

$$(\text{Line integral}) \sim \oint_{\text{along a loop}} \vec{F} \cdot d\vec{l} = \iint_{\text{over the surface}} (\vec{\nabla} \times \vec{F}) \cdot d\vec{s} \sim \left( \begin{array}{c} \text{Flux integral of curl} \\ \text{over the surface} \\ \text{surrounded by the loop} \end{array} \right)$$

Therefore, we can borrow the idea of surface integral:

- Cover the Ampere loop with a surface.
- A line is "enclosed by the loop" if it goes through the surface (for an odd number of times).



In this definition, there is no specification about the surface - which means as an universal definition, it should work for ALL choices of surface.



#### Enclosed by the loop:

If you can find a surface that is poked through by any odd number of times (blue), you will always find a surface that is poked through only once (red).

**NOT enclosed by the loop:**

If you can find a surface that is poked through by any even number of times (blue), you will always find a surface that is not being poked through (red).




## 2.2 Problem with Ampere's Law


Now we re-visit the statement of Ampere's law in magnetostatics:

$$\left( \text{Dot product integral of } \vec{B} \text{ along loop} \right) \sim \oint \vec{B} \cdot d\vec{l} = \mu_0 I_{\text{enc}} \sim \mu_0 \left( \text{"Enclosed" current} \right)$$


In statics cases (no time-varying current), the statement holds for any choice of surfaces to capture the enclosed current. This is because in order to have steady current flow - current must be running in 1. a closed loop, or 2. an infinitely long wire.




In these two cases, you cannot separate the gray ring without breaking the current wire.



But when current is allowed to change with time, we can have current discontinues at the end of a broken wire and accumulate as charges. Depends on which surface is chosen, it becomes undefined whether the current wire is enclosed by the loop.



As an analogy to the problem, we can think of how scoring works in basketball - the choice of surface does matter.



You get a score if the winning condition is the ball poking through the blue surface



You don't get a score if the winning condition is the ball poking through the red surface

## 2.3 The Fix: Another Current

According to charge conservation:

**Termination of current always results in accumulation of charge,  
and charge always creates E-field.**

We can fix the ambiguity of Ampere's law by adding a new current term  $I_d$ , called **displacement current**, which is defined as

$$I_d \stackrel{\text{def}}{=} \epsilon_0 \frac{\partial}{\partial t} \iint_{\text{the chosen surface}} \vec{E} \cdot d\vec{s}$$

or in terms of volume current density,

$$\vec{J}_d \stackrel{\text{def}}{=} \epsilon_0 \frac{\partial \vec{E}}{\partial t}$$

So that Ampere's law is modified into:


– Integral form:

$$(\vec{B}'s \text{ loop integral}) \sim \oint \vec{B} \cdot d\vec{l} = \mu_0(I_{\text{enc}} + I_d) \sim (\text{Enclosed current}) + (\text{Displacement current})$$

– Differential form:

$$\left( \vec{B}'s \text{ loop integral} \right) \sim \nabla \times \vec{B} = \mu_0(\vec{J}_{\text{enc}} + \vec{J}_d) \sim \left( \begin{array}{c} \text{Enclosed} \\ \text{current} \end{array} \right) + \left( \begin{array}{c} \text{Displacement} \\ \text{current} \end{array} \right)$$

With  $I_d$  depending on the flux of E-field produced by the charge accumulation, Ampere's law is always satisfied, independent of the choice of the surface. For example,



The blue surface is poked through by the real current wire.

$$I_{\text{enc}} \neq 0$$

The red surface is not poked through by the current wire, but it captures the flux of E-field.

$$I_{\text{enc}} = 0 \quad \text{but} \quad I_d \neq 0$$

Derivation:

The expression of displacement current is a direct result of charge conservation. We can start with the continuity equation and substitute Gauss's law:

$$\begin{aligned} 0 &= \vec{\nabla} \cdot \vec{J} + \frac{\partial \rho}{\partial t} \quad \boxed{\vec{\nabla} \cdot \vec{E} = \frac{\rho}{\epsilon_0}} \\ &= \vec{\nabla} \cdot \vec{J} + \frac{\partial}{\partial t} (\epsilon_0 \vec{\nabla} \cdot \vec{E}) \\ &= \vec{\nabla} \cdot \left( \vec{J} + \epsilon_0 \frac{\partial \vec{E}}{\partial t} \right) \end{aligned}$$

Recall that if a vector field is divergent-less, it can be expressed as the curl of another vector field. (Just like B-field,  $\vec{\nabla} \cdot \vec{B} = 0 \Rightarrow \vec{B} = \vec{\nabla} \times \vec{A}$ ). It is the same here:

$$\vec{\nabla} \cdot \left( \vec{J} + \epsilon_0 \frac{\partial \vec{E}}{\partial t} \right) = 0 \quad \Rightarrow \quad \vec{J} + \epsilon_0 \frac{\partial \vec{E}}{\partial t} = \vec{\nabla} \times (\text{another field})$$

Comparing with the original Ampere's law, the "another field" has the same unit as the B-field (divided by  $\mu_0$ ). So the correct modification must be

$$\boxed{\vec{\nabla} \times \vec{B} = \mu_0 \left( \vec{J} + \epsilon_0 \frac{\partial \vec{E}}{\partial t} \right)}$$

And its integral form can be shown by Stoke's theorem.

$$\boxed{\oint \vec{B} \cdot d\vec{l} = \mu_0 \left( I + \epsilon_0 \frac{\partial}{\partial t} \iint \vec{E} \cdot d\vec{s} \right)}$$


## 2.4 Complication of Electro-Magnetic Induction

Combining the results of Faraday's law and Ampere's law, we can see that time-varying E-field and B-field can induce each other.

- Faraday -  $\vec{\nabla} \times \vec{E} = - \frac{\partial \vec{B}}{\partial t}$  - Time varying B-field induces (time-varying) E-field.
- Ampere -  $\vec{\nabla} \times \vec{B} = \mu_0 \vec{J} + \mu_0 \epsilon_0 \frac{\partial \vec{E}}{\partial t}$  - Time varying E-field induces (time-varying) B-field.

Ideally  $\vec{E}$  and  $\vec{B}$  must be solved together - as a system of PDE!

Theoretically, if we only look at Faraday's law or Ampere's law one at a time, we will end up like this mess:



However solving system of PDEs is too complicated for anyone. So to make practical problems for studying, there is usually a hidden compromise:

**We just assume induced E-field do not create induced B-field.**

This is OK for small scale system when the magnitude of displacement current is small enough to be ignored:

$$\mu_0\epsilon_0 = \frac{1}{c^2} = \frac{1}{(3 \times 10^8)^2} \quad \Rightarrow \quad \vec{\nabla} \times \vec{B}_1 = \mu_0\epsilon_0 \frac{\partial \vec{E}_1}{\partial t} \sim (10^{-16}) \frac{\Delta \vec{E}_1}{\Delta t}$$

But there do exist systems where you cannot take this approximation. In those cases, solving PDEs is unavoidable. For example,

- Plamsa Physics (Plamsa = A mixture of high energy charges).
- Astronomy, e.g. structure of neutron star, surroundings around black holes.

Fortunately, you will almost never see them unless you are doing related researches in the future.

— The End —