

# Magnetic Material & Magnetization

by Tony Shing

---

## Overview:

- Model of magnetic dipole
- How to describe dipole arrangement: Magnetization field, bound currents
- Material under external  $\vec{B}$  field:
  - A special case of material model: Linear magnetic material
  - Describe external field: Free currents, auxiliary field  $\vec{H}$

**If linear magnetic material is all you need, you can skip most of the maths.**

---

# 1 Magnetic Dipole

## 1.1 Magnetic Response in Materials

In modern theory, magnetic response in atoms is purely a quantum mechanical effect. But before quantum mechanics being turned into a complete mathematics theory, scientists had been explaining magnetic response with a few semi-classical theories.

### 1.1.1 Electron as Magnetic Source

In an atom, the majority of magnetic response comes from the electrons. An electron behaves as a magnetic dipole in 2 ways:

- **Orbital motion** - Electron orbiting around the nucleus, equivalent to a tiny current loop.
- **Spin** - Electron carries a fundamental quantum property called **spin**, which determines how it interacts with B-field. It cannot be described fully by any classical picture.

(add figure here: orbital motion + spin)

Magnetic response of an atom is the combined effect from both orbital motion and spin. Depends on which effect dominates, magnetic responses can be classified into 2 types:

- **Diamagnetism** - When orbital motion dominates. Exists on most non-metals.
- **Paramagnetism** - When spin dominates. Exists on many metals, and some non-metals that contain chemical bonds with unpaired electrons.

In general, effects from spin is much stronger than that from orbital motion. However since chemical bonds are usually made of pairs of electrons with opposite spins (Pauli exclusion principle), such that the effect from spin cancels out, making orbital motion the dominant effect.

(add figure here: normal bond -> dia mat; unusual bond with unpair electron -> para mat)

### 1.1.2 Diamagnetism

In a diamagnetic material, its chemical bonds do not contain any unpaired electrons such that all effects from spin cancel.

(Pauli exclusion principle)

and the magnetic response is only due to orbital motion of electrons.

although the effect from spin being much stronger. However when atoms form chemical bonds, effects of spin can be cancelled due to paring of electrons .

When an external B-field is applied, **electron orbital motion reacts by weakening the external B-field**. This is equivalent to creating magnetic dipoles in the material that point opposite to the external B-field.

(add figure here: original - $\downarrow$  weaken = create opposite dipole)

In the semi-classical theory of diamagnetism, the orbital motion of electron is characterized by:

- Electron (charge  $-q$ ) orbits around a nucleus with charge  $+Zq$  ( $Z$  = atomic number).
- Orbit of electron is a circle of fixed radius  $r$ . (Bohr model of atom)

Diamagnetism is due to the decrease in orbital speed under external B-field.

1. By Coulomb's law, first calculate the electron's original orbital speed  $v$ :

$$\frac{mv^2}{r} = \frac{1}{4\pi\epsilon_0} \frac{Zq^2}{r^2} \quad \Rightarrow \quad v = \sqrt{\frac{Zq^2}{4\pi\epsilon_0 mr}}$$

2. When an external B-field  $\vec{B}$  is applied perpendicular to the orbital plane, the moving electron experiences a magnetic force  $\vec{F} = (-q)\vec{v} \times \vec{B}$ .

(add figure here: magnetic force on orbiting electron)

So the electron's orbital speed is changed to a new value  $v'$ . Newton's law writes:

$$\begin{aligned} \frac{mv'^2}{r} &= \frac{1}{4\pi\epsilon_0} \frac{Zq^2}{r^2} - qv'B \\ \Rightarrow v' &= \frac{-qB \pm \sqrt{(qB)^2 + 4\left(\frac{m}{r}\right)\left(\frac{Zq^2}{4\pi\epsilon_0 r^2}\right)}}{2\left(\frac{m}{r}\right)} \\ &= \sqrt{\frac{Zq^2}{4\pi\epsilon_0 r^2} + \left(\frac{qBr}{2m}\right)^2} - \frac{qBr}{2m} \\ &< \sqrt{\frac{Zq^2}{4\pi\epsilon_0 mr}} \end{aligned}$$

### 1.1.3 Paramagnetism

*Side Note:*

Textbooks usually describe **ferromagnetism** as the 3<sup>rd</sup> kind of magnetic response. However its origin is very different from dia-/paramagnetism:

- Dia-/paramagnetism comes from individual atoms' response to B-field. They can exist even if there is only one atom.
- Ferromagnetism is due to the collective behavior of many atoms. It is actually a big topic in statistical mechanics.

On a ferromagnetic material,

## 1.2 Potential from Magnetic Dipole

This is the classical model of magnetic dipole. Same calculations can be found in many textbooks.

- A circular loop of radius  $R$ , carrying current  $I$ .
- We are only interested in the potential/field far away from the dipole, i.e.  $|\vec{r}| \gg R$ . The position vector  $\vec{r}$  is referenced from the center of the dipole.

(add figure here: magnetic dipole model)

The derivation of magnetic potential from a dipole is straightforward by Biot-Savart law, while applying Taylor approximation in the middle step.

1. The total potential contributions towards position  $\vec{r}$  by two current elements at opposite position on the loop is

$$\begin{aligned}
 d\vec{A}(\vec{r}) &= \frac{\mu_0}{4\pi} \left( \frac{I d\vec{l}_+}{|\vec{r}_+|} + \frac{I d\vec{l}_-}{|\vec{r}_-|} \right) \\
 &= \frac{\mu_0 I}{4\pi} \left( \underbrace{\frac{R d\theta}{|\vec{r}_+|} (\hat{\theta})}_{\text{By geometry, } |\vec{d}\vec{l}| = R d\theta} + \underbrace{\frac{R d\theta}{|\vec{r}_-|} (-\hat{\theta})}_{\text{And they point in opposite direction}} \right) \\
 &= \frac{\mu_0 I R d\theta}{4\pi} \left( \underbrace{\frac{1}{\sqrt{|\vec{r}|^2 + R^2 - 2|\vec{r}|R \cos \phi}}}_{\text{These are just cosine law}} - \underbrace{\frac{1}{\sqrt{|\vec{r}|^2 + R^2 + 2|\vec{r}|R \cos \phi}}}_{\text{These are just cosine law}} \right) \hat{\theta} \\
 &= \frac{\mu_0 I R d\theta}{4\pi |\vec{r}|} \left( \frac{1}{\sqrt{1 + \frac{R^2}{|\vec{r}|^2} - \frac{2R}{|\vec{r}|} \cos \phi}} - \frac{1}{\sqrt{1 + \frac{R^2}{|\vec{r}|^2} + \frac{2R}{|\vec{r}|} \cos \phi}} \right) \hat{\theta}
 \end{aligned}$$

(add figure here: show geometry, opposite current elements and position vectors)

2. Taylor expansion “ $(1+x)^n \approx 1+nx$  for  $x \ll 1$ ” is always applied at this step. Because we are only interested in the potential far from the dipole,  $\frac{R}{|\vec{r}|} \ll 1$ ,

- $\frac{R^2}{|\vec{r}|^2} \approx 0$
- $\frac{1}{\sqrt{1-\frac{R}{|\vec{r}|}\cos\phi}} = \left(1 - 2\frac{R}{|\vec{r}|}\cos\phi\right)^{-\frac{1}{2}} \approx 1 + \frac{R}{|\vec{r}|}\cos\phi$

So the potential becomes

$$\begin{aligned} d\vec{A}(\vec{r}) &= \frac{\mu_0 IR d\theta}{4\pi |\vec{r}|} \left[ \left(1 + \frac{R}{|\vec{r}|}\cos\phi\right) - \left(1 - \frac{R}{|\vec{r}|}\cos\phi\right) \right] \hat{\theta} \\ &= \frac{\mu_0 IR d\theta}{4\pi |\vec{r}|} \cdot 2 \frac{R}{|\vec{r}|} \cos\phi \cdot \hat{\theta} \end{aligned}$$

3. Before doing any integration, we first need to express every non-constant in terms of  $\theta$ :

- Recall what we learnt about polar coordinate, the angular unit vector  $\hat{\theta}_{\{r,\theta\}}$  is a function of angle  $\theta$ .

$$\hat{\theta} = -(\sin\theta)\hat{x} + (\cos\theta)\hat{y}$$

- $\phi$  is the angle between the target’s position  $\vec{r}$  and position vector of  $I d\vec{l}_+$ . Expressing them in x-y-z coordinate:

- Target’s position:  $\vec{r} = x\hat{x} + y\hat{y} + z\hat{z}$
- Position vector of  $I d\vec{l}_+$ :  $\vec{R} = (R\cos\theta)\hat{x} + (R\sin\theta)\hat{y}$

So that  $\cos\phi$  can be calculated as their dot product:

$$\cos\phi = \frac{\vec{r} \cdot \vec{R}}{|\vec{r}||\vec{R}|} = \frac{x\cos\theta + y\sin\theta}{|\vec{r}|}$$

4. Finally integrate over  $\theta$  from 0 to  $\pi$  to find the total contribution of the loop.

$$\begin{aligned} \int d\vec{A}(\vec{r}) &= \int_0^\pi \frac{\mu_0 IR d\theta}{4\pi |\vec{r}|} \cdot 2 \frac{R}{|\vec{r}|} \cos\phi \cdot \hat{\theta} \\ &= \frac{\mu_0 IR^2}{2\pi |\vec{r}|^2} \int_0^\pi \left( \frac{x\cos\theta + y\sin\theta}{|\vec{r}|} \right) (-(\sin\theta)\hat{x} + (\cos\theta)\hat{y}) d\theta \\ &= \frac{\mu_0 IR^2}{2\pi |\vec{r}|^3} \int_0^\pi (-x\hat{x} + y\hat{y}) \underbrace{\frac{\sin\theta\cos\theta}{\int_0^\pi \sin\theta\cos\theta d\theta}}_{=0} + (x\hat{y}) \underbrace{\frac{\cos^2\theta}{\int_0^\pi \cos^2\theta d\theta}}_{=\frac{\pi}{2}} - (y\hat{x}) \underbrace{\frac{\sin^2\theta}{\int_0^\pi \sin^2\theta d\theta}}_{=\frac{\pi}{2}} d\theta \\ &= \frac{\mu_0 IR^2}{2\pi |\vec{r}|^3} \cdot \frac{\pi}{2} \cdot (x\hat{y} - y\hat{x}) \end{aligned}$$

It happens that the term in the bracket is the cross product of  $\hat{z}$  and  $\vec{r}$ , since

$$\hat{z} \times \vec{r} = \begin{vmatrix} \hat{x} & \hat{y} & \hat{z} \\ 0 & 0 & 1 \\ x & y & z \end{vmatrix} = -y\hat{x} + x\hat{y}$$

So that the potential becomes

$$\begin{aligned}\vec{A}(\vec{r}) &= \frac{\mu_0 I R^2}{4|\vec{r}|^2} \left( \frac{x\hat{y} - y\hat{x}}{|\vec{r}|} \right) \\ &= \frac{\mu_0 I R^2}{4|\vec{r}|^2} \frac{\hat{z} \times \vec{r}}{|\vec{r}|} \\ &= \frac{\mu_0}{4\pi} \frac{I\pi R^2}{|\vec{r}|^2} (\hat{z} \times \vec{r})\end{aligned}$$

5. To emphasize that we now treat a magnetic dipole as “one unit of source”, We define the **magnetic dipole moment**  $\vec{m}$ ,

$$\boxed{\vec{m} \stackrel{\text{def}}{=} I \cdot \left( \begin{smallmatrix} \text{Loop's} \\ \text{Area} \end{smallmatrix} \right) \cdot \left( \begin{smallmatrix} \text{Unit vector} \\ \text{normal to loop} \end{smallmatrix} \right)}$$

In our case of a loop in x-y plane,  $\vec{m} = I(\pi R^2)\hat{z}$ . Finally we reach the standard formula of magnetic potential from a magnetic dipole:

$$\boxed{\vec{A}(\vec{r}) = \frac{\mu_0}{4\pi} \frac{\vec{m} \times \hat{r}}{|\vec{r}|^2}}$$

As a comparison with Biot-Savart law formula from current element,

$$d\vec{A}(\vec{r}) = \frac{\mu_0}{4\pi} \frac{I d\vec{l}}{|\vec{r}|}$$

(add figure here: V from point charge source)

- $\vec{A}$  is always along the same direction as the current element.
- Dependence on distance is  $\frac{1}{r}$ .

$$\vec{A}(\vec{r}) = \frac{\mu_0}{4\pi} \frac{\vec{m} \times \hat{r}}{|\vec{r}|^2}$$

(add figure here: V from dipole source)

- Magnitude of potential depends on the current’s magnitude AND the angle (cross product) between  $\vec{m}$  and  $\hat{r}$ .
- Dependence on distance is  $\frac{1}{r^2}$ .

### 1.3 B-field from Magnetic Dipole

The standard derivation of B-field from dipole is through the relation  $\vec{B} = \vec{\nabla} \times \vec{A}$ . It is nothing more than some boring vector calculus. Here I quote the final result:

$$\boxed{\vec{B}(\vec{r}) = \frac{\mu_0}{4\pi} \frac{3(\vec{m} \cdot \hat{r})\hat{r} - \vec{m}}{|\vec{r}|^3}}$$

And this formula is rarely used because vector calculation is annoying.

The boring derivation:

- Derivation is possible with high school calculus if we turn all vectors into x-y-z form:  $\vec{r} = x\hat{x} + y\hat{y} + z\hat{z}$ ,  $|\vec{r}| = \sqrt{x^2 + y^2 + z^2}$  and  $\vec{m} = m_x\hat{x} + m_y\hat{y} + m_z\hat{z}$ :

$$\begin{aligned}\frac{\vec{m} \times \hat{r}}{|\vec{r}|^2} &= \frac{\vec{m}}{|\vec{r}|^2} \times \frac{\vec{r}}{|\vec{r}|} = \frac{1}{|\vec{r}|^3} (\vec{m} \times \vec{r}) = \frac{1}{|\vec{r}|^3} \begin{vmatrix} \hat{x} & \hat{y} & \hat{z} \\ m_x & m_y & m_z \\ x & y & z \end{vmatrix} \\ &= \frac{1}{(x^2 + y^2 + z^2)^{\frac{3}{2}}} [(m_y z - m_z y)\hat{x} + (m_z x - m_x z)\hat{y} + (m_x y - m_y x)\hat{z}]\end{aligned}$$

- First the  $x$  term in curl,  $\left(\frac{\partial \bullet_z}{\partial y} - \frac{\partial \bullet_y}{\partial z}\right) \hat{x}$ , can be calculated by:

$$\begin{aligned}\frac{\partial \bullet_z}{\partial y} &= \frac{\partial}{\partial y} \left[ \frac{(m_x y - m_y x)}{(x^2 + y^2 + z^2)^{\frac{3}{2}}} \right] \\ &= \frac{m_x(x^2 + y^2 + z^2)^{\frac{3}{2}} - (m_x y - m_y x) \cdot 3y(x^2 + y^2 + z^2)^{\frac{1}{2}}}{(x^2 + y^2 + z^2)^3} \\ &= \frac{m_x |\vec{r}|^2 - 3(m_x y - m_y x)y}{|\vec{r}|^5} \\ \frac{\partial \bullet_y}{\partial z} &= \frac{\partial}{\partial z} \left[ \frac{(m_z x - m_x z)}{(x^2 + y^2 + z^2)^{\frac{3}{2}}} \right] \\ &= \frac{-m_x(x^2 + y^2 + z^2)^{\frac{3}{2}} - (m_z x - m_x z) \cdot 3z(x^2 + y^2 + z^2)^{\frac{1}{2}}}{(x^2 + y^2 + z^2)^3} \\ &= \frac{-m_x |\vec{r}|^2 - 3(m_z x - m_x z)z}{|\vec{r}|^5} \\ \Rightarrow \left(\frac{\partial \bullet_z}{\partial y} - \frac{\partial \bullet_y}{\partial z}\right) \hat{x} &= \frac{2m_x |\vec{r}|^2 - 3(m_x y - m_y x)y + 3(m_z x - m_x z)z}{|\vec{r}|^5} \hat{x} \\ &= \frac{2m_x |\vec{r}|^2 - 3m_x y^2 + 3m_y xy + 3m_z xz - 3m_x z^2 + 3m_x x^2 - 3m_x x^2}{|\vec{r}|^5} \hat{x} \\ &= \frac{2m_x |\vec{r}|^2 - 3m_x(x^2 + y^2 + z^2) + 3m_x x^2 + 3m_y xy + 3m_z xz}{|\vec{r}|^5} \hat{x} \\ &= \frac{-m_x |\vec{r}|^2 + 3(m_x x + m_y y + m_z z)x}{|\vec{r}|^5} \hat{x} \\ &= \frac{-m_x |\vec{r}|^2 + 3(\vec{m} \cdot \vec{r})x}{|\vec{r}|^5} \hat{x}\end{aligned}$$

3. Similar for  $y$  and  $z$  terms:

$$\left( \frac{\partial \bullet_x}{\partial z} - \frac{\partial A_z}{\partial x} \right) \hat{y} = \frac{-m_y |\vec{r}|^2 + 3(\vec{m} \cdot \vec{r})y}{|\vec{r}|^5} \hat{y}$$

$$\left( \frac{\partial \bullet_y}{\partial x} - \frac{\partial A_x}{\partial y} \right) \hat{z} = \frac{-m_z |\vec{r}|^2 + 3(\vec{m} \cdot \vec{r})z}{|\vec{r}|^5} \hat{z}$$

4. Summing all 3 components gives:

$$\begin{aligned} \vec{\nabla} \times \vec{A}(\vec{r}) &= \left( \frac{\partial A_z}{\partial y} - \frac{\partial A_y}{\partial z} \right) \hat{x} + \left( \frac{\partial A_x}{\partial z} - \frac{\partial A_z}{\partial x} \right) \hat{y} + \left( \frac{\partial A_y}{\partial x} - \frac{\partial A_x}{\partial y} \right) \hat{z} \\ &= \frac{\mu_0}{4\pi} \frac{3(\vec{m} \cdot \vec{r})(x\hat{x} + y\hat{y} + z\hat{z}) - (m_x \hat{x} + m_y \hat{y} + m_z \hat{z})|\vec{r}|^2}{|\vec{r}|^5} \\ &= \frac{\mu_0}{4\pi} \frac{3(\vec{m} \cdot \vec{r})\vec{r} - \vec{m}|\vec{r}|^2}{|\vec{r}|^5} \\ &\quad \text{Take out magnitude to become unit vector} \\ &= \frac{\mu_0}{4\pi} \frac{3(\vec{m} \cdot \hat{r})\hat{r}|\vec{r}|^2 - \vec{m}|\vec{r}|^2}{|\vec{r}|^5} \\ \boxed{\vec{B}(\vec{r}) = \frac{\mu_0}{4\pi} \frac{3(\vec{m} \cdot \hat{r})\hat{r} - \vec{m}}{|\vec{r}|^3}} \end{aligned}$$

## 2 Describing Dipole Arrangement

In general, all materials are made of many tiny magnetic dipoles. To analyze the material's magnetic properties, we can begin with the property of a single dipole, then sum the contributions of all dipoles according to the dipole arrangement in the material.

$$\underbrace{\vec{A}(\vec{r}) = \frac{\mu_0}{4\pi} \frac{\vec{m}_i}{|\vec{r}|^2} \times \left( \frac{\vec{r}}{|\vec{r}|} \right)}_{\text{By a single dipole from origin}} \Rightarrow \underbrace{\vec{A}(\vec{r}) = \frac{\mu_0}{4\pi} \sum_{\text{All dipoles } i} \frac{\vec{m}_i}{|\vec{r} - \vec{r}_i|^2} \times \left( \frac{\vec{r} - \vec{r}_i}{|\vec{r} - \vec{r}_i|} \right)}_{\text{By many dipoles at different positions } \vec{r}_i}$$

(add figure here: single dipole point to  $\vec{r}$  vs many dipoles at different  $\vec{r}_i$  to  $\vec{r}$ )

Here we introduce two quantities that describe magnetic dipole arrangements in materials.

- Magnetization field -  $\vec{M}(\vec{r})$
- Bound current distributions -  $\vec{J}_b(\vec{r})$  and  $\vec{K}_b(\vec{r})$

## 2.1 Magnetization Field

When the dipoles in the material are so dense such that we can treat them as a continuous distribution, we can replace

- Summation of all dipoles  $\xrightarrow{\text{become}}$  Volume integral over the whole object.
- Discrete dipoles source  $\xrightarrow{\text{become}}$  A vector distribution called **magnetization field**  $\vec{M}(\vec{r})$ .

$$\boxed{\vec{A}(\vec{r}) = \frac{\mu_0}{4\pi} \iiint_{\substack{\text{Whole} \\ \text{material}}} \frac{\vec{M}(\vec{r}')}{|\vec{r} - \vec{r}'|^2} \times \left( \frac{\vec{r} - \vec{r}'}{|\vec{r} - \vec{r}'|} \right) d^3\vec{r}'}$$

(add figure here: dipole arrangement is similar to some vector field in the object)

The magnetization field  $\vec{M}(\vec{r})$  can also be interpreted as **magnetic dipole density** because its usage is similar to charge density  $\vec{J}(\vec{r})$ . Comparing with the Biot-Savart law for magnetic potential:

- When the source is made of current elements:

$$\vec{A}(\vec{r}) = \frac{\mu_0}{4\pi} \iiint \frac{\vec{J}(\vec{r}')}{|\vec{r} - \vec{r}'|} d^3\vec{r}' \sim \frac{\mu_0}{4\pi} \sum \frac{(\text{current density})}{(\text{distance})}$$

- When the source is made of dipoles:

$$\vec{A}(\vec{r}) = \frac{\mu_0}{4\pi} \iiint \frac{\vec{M}(\vec{r}')}{|\vec{r} - \vec{r}'|^2} \times \left( \frac{\vec{r} - \vec{r}'}{|\vec{r} - \vec{r}'|} \right) d^3\vec{r}' \sim \frac{\mu_0}{4\pi} \sum \frac{(\text{dipole density})}{(\text{distance})^2} \times (\text{vector})$$

(add figure here: charge density vs dipole density in the same material)

## 2.2 Bound Current Distribution

Ultimately, magnetic dipoles are just loops of currents. If the dipoles are aligned non-uniformly in a material, some regions may appear to have a higher flow of current in one direction than the other way.

(add figure here: dipole loops non uniform)

These regions with extra current flow are described as **bound current** distribution in the material - they are always “bounded” to regions where the current flow is not cancelled. So bound current distribution can be used to describe magnetic dipole arrangement in the material.

### 2.2.1 Mathematical Origin

With vector calculus, the potential formula can be rewritten into a “current densities form”.

$$\begin{aligned}\vec{A}(\vec{r}) &= \frac{\mu_0}{4\pi} \iiint_{\substack{\text{Whole} \\ \text{material}}} \frac{\vec{M}(\vec{r}')}{|\vec{r} - \vec{r}'|^2} \times \left( \frac{\vec{r} - \vec{r}'}{|\vec{r} - \vec{r}'|} \right) d^3\vec{r}' \\ &= (\dots \text{ After more boring vector calculus } \dots) \\ &= \frac{\mu_0}{4\pi} \iiint_{\substack{\text{Whole} \\ \text{material}}} \frac{\vec{\nabla} \times \vec{M}(\vec{r}')}{|\vec{r} - \vec{r}'|} d^3\vec{r}' + \frac{\mu_0}{4\pi} \iint_{\substack{\text{Surface} \\ \text{of material}}} \frac{\vec{M}(\vec{r}')}{|\vec{r} - \vec{r}'|} \times d^2\vec{r}'\end{aligned}$$

By comparing with the Biot-Savart law for electric potential  $\vec{A} \sim \frac{\mu_0}{4\pi} \sum \frac{(\text{current density})}{(\text{distance})}$ , we identify the 2 source terms as the **bound current densities**:

– The 1<sup>st</sup> term:

$$\frac{\mu_0}{4\pi} \iiint_{\substack{\text{Whole} \\ \text{material}}} \frac{\vec{\nabla} \times \vec{M}(\vec{r}')}{|\vec{r} - \vec{r}'|} d^3\vec{r}' \sim \frac{\mu_0}{4\pi} \sum_{\text{Inside material}} \frac{(\vec{\nabla} \times \vec{M})}{(\text{distance})}$$

$\vec{\nabla} \times \vec{M}$  appears as some current density distributed inside the material. Therefore it is defined as the **volume bound current density**  $\vec{J}_b$ .

$$\boxed{\vec{J}_b(\vec{r}) \stackrel{\text{def}}{=} \vec{\nabla} \times \vec{M}(\vec{r})}$$

– The 2<sup>nd</sup> term:

$$\frac{\mu_0}{4\pi} \iint_{\substack{\text{Surface} \\ \text{of material}}} \frac{\vec{M}(\vec{r}')}{|\vec{r} - \vec{r}'|} \times d^2\vec{r}' \sim \frac{\mu_0}{4\pi} \sum_{\text{On material surface}} \frac{(\text{Surface cross product of } \vec{M})}{(\text{distance})}$$

The surface cross product of  $\vec{M}$  means that we are taking cross product between  $\vec{M}$  and normal vector of the surface. It appears as some current density distributed on the surface of the material. So it is defined as the **surface bound current density**  $\vec{K}_b$ .

$$\boxed{\vec{K}_b(\vec{r}) \stackrel{\text{def}}{=} \vec{M}(\vec{r}) \times \hat{n}}$$

where  $\hat{n}$  is the (outward) unit normal vector on the material surface.

Finally, the expression of the “current densities” form is nothing more than saying that the magnetic potential from a material is the result of the two kinds of current distributions.

$$\begin{aligned}\vec{A}(\vec{r}) &= \frac{\mu_0}{4\pi} \iiint_{\substack{\text{Whole} \\ \text{material}}} \frac{\vec{J}_b(\vec{r}')}{|\vec{r} - \vec{r}'|} d^3\vec{r}' + \frac{\mu_0}{4\pi} \iint_{\substack{\text{Surface} \\ \text{of material}}} \frac{\vec{K}_b(\vec{r}')}{|\vec{r} - \vec{r}'|} d^2\vec{r}' \\ &= \left( \begin{array}{c} \text{Contribution} \\ \text{by currents inside} \\ \text{the material} \end{array} \right) + \left( \begin{array}{c} \text{Contribution} \\ \text{by currents on} \\ \text{material's surface} \end{array} \right)\end{aligned}$$

The boring derivation:

- Deriving the “current densities form” begins with a vector calculus identity:

$$\begin{aligned}
 \vec{\nabla} \left( \frac{1}{|\vec{r} - \vec{r}'|} \right) &= \left( \hat{x} \frac{\partial}{\partial x'} + \hat{y} \frac{\partial}{\partial y'} + \hat{z} \frac{\partial}{\partial z'} \right) \left( \frac{1}{\sqrt{(x - x')^2 + (y - y')^2 + (z - z')^2}} \right) \\
 \text{Note: Differentiation} \quad &= \frac{\hat{x}(x - x') + \hat{y}(y - y') + \hat{z}(z - z')}{[(x - x')^2 + (y - y')^2 + (z - z')^2]^{\frac{3}{2}}} \\
 \text{is w.r.t. } x', y', z' &= \frac{\vec{r} - \vec{r}'}{|\vec{r} - \vec{r}'|^3} \quad \text{This part is just a unit vector} \\
 &= \frac{1}{|\vec{r} - \vec{r}'|^2} \left( \frac{\vec{r} - \vec{r}'}{|\vec{r} - \vec{r}'|} \right) \quad \left( \text{This is basically } \frac{d}{dr'} \left( \frac{1}{r'} \right) = \frac{1}{(r')^2} \right)
 \end{aligned}$$

- So the potential formula can be rewritten as:

$$\begin{aligned}
 \vec{A}(\vec{r}) &= \frac{\mu_0}{4\pi} \iiint \frac{\vec{M}(\vec{r}')}{|\vec{r} - \vec{r}'|^2} \times \left( \frac{\vec{r} - \vec{r}'}{|\vec{r} - \vec{r}'|} \right) d^3 r' \\
 &= \frac{\mu_0}{4\pi} \iiint \frac{\vec{M}(\vec{r}') \times \vec{\nabla} \left( \frac{1}{|\vec{r} - \vec{r}'|} \right)}{|\vec{r} - \vec{r}'|} d^3 r' \\
 &\quad \text{Note the order of } f \text{ and } \vec{G} \\
 &= \frac{\mu_0}{4\pi} \iiint \frac{-\vec{\nabla} \times \left( \frac{\vec{M}(\vec{r}')}{|\vec{r} - \vec{r}'|} \right) + \frac{\vec{\nabla} \times \vec{M}(\vec{r}')}{|\vec{r} - \vec{r}'|}}{|\vec{r} - \vec{r}'|} d^3 r' \\
 &\quad \text{Note the order of } f \text{ and } \vec{G}
 \end{aligned}$$

Here we used the product rule of curl  $\vec{\nabla} \times (f\vec{G}) = f\vec{\nabla} \times \vec{G} + (\vec{\nabla} f) \times \vec{G}$ , where  $f$  is a scalar function (like  $\frac{1}{|\vec{r} - \vec{r}'|}$ ) and  $\vec{G}$  is a vector function (like  $\vec{M}$ ).

- Finally use the “divergence theorem for curl” to convert the 1<sup>st</sup> term’s volume integral into a surface integral over the volume’s surface:

$$\begin{aligned}
 \vec{A}(\vec{r}) &= \frac{\mu_0}{4\pi} \iiint \vec{\nabla} \times \left( \frac{\vec{M}(\vec{r}')}{|\vec{r} - \vec{r}'|} \right) d^3 r' + \frac{\mu_0}{4\pi} \iiint \frac{\vec{\nabla} \times \vec{M}(\vec{r}')}{|\vec{r} - \vec{r}'|} d^3 r' \\
 &\quad \text{Divergence theorem for curl} \\
 &= \frac{\mu_0}{4\pi} \iint \frac{\vec{M}(\vec{r}')}{|\vec{r} - \vec{r}'|} \times d^2 \vec{r}' + \frac{\mu_0}{4\pi} \iiint \frac{\vec{\nabla} \times \vec{M}(\vec{r}')}{|\vec{r} - \vec{r}'|} d^3 r' \\
 &= \left( \begin{array}{c} \text{Contribution} \\ \text{from material's} \\ \text{surface} \end{array} \right) + \left( \begin{array}{c} \text{Contribution} \\ \text{from inside} \\ \text{the material} \end{array} \right)
 \end{aligned}$$

Remind that we are integrating regions where dipoles exist. So this volume integral corresponds to the whole material and surface integral corresponds to only the surface of the material.

## 2.2.2 Visualization

The bound current densities are related to  $\vec{M}$  pretty much like normal current density are related to  $\vec{B}$  in Ampere's law.

- **Volume bound current:** By drawing an Ampere's loop and check how many dipoles are pointing in the same direction as we travel along the loop,

More dipole align with the circle	$\Leftrightarrow$	Stronger current at the center
-----------------------------------	-------------------	--------------------------------

(add figure here: dipole 's current in toroid shape)

Recall that we can use sign of dot product line integral to identify positions with vector field in rotation pattern, and curl operator  $\vec{\nabla} \times$  is equivalent to finding dot product line integral per area.

$$\left(\begin{array}{l} \text{Bound current} \\ \text{volume density} \end{array}\right) \sim \vec{J}_b = \vec{\nabla} \times \vec{M} \sim \left(\begin{array}{l} \# \text{ of dipoles per area} \\ \text{around a rotation center} \end{array}\right)$$

- **Surface bound current:** On the material surface, we can see that

More dipole align in the same direction	$\Leftrightarrow$	More current flow on the material surface
---	-------------------	---

(add figure here: surface out of paper dipole form current to left)

As we have defined the normal vector  $\hat{n}$  of the material surface to be pointing outward, the direction of current is exactly along  $\vec{M} \times \hat{n}$ .

$$\left(\begin{array}{l} \text{Bound current} \\ \text{surface density} \end{array}\right) \sim \vec{K}_b = \vec{M} \times \hat{n} \sim \left(\begin{array}{l} \text{Same direction dipole} \\ \text{per surface area} \end{array}\right)$$

*Side note:*

For paramagnetic and diamagnetic materials, we almost never observe their  $\vec{M}$  field or bound current because

- Magnitude of a dipole is too small. Typical magnetic dipole moment are of order  $10^{-24} \text{ A} \cdot \text{m}^2$ .
- The dipoles are usually randomly arranged, or in patterns such that their effects cancel out. Especially when the material is large.

Their magnetization effect is negligible unless it is placed under an external B-field, which forces its dipoles to align and change their dipole moment's magnitude.

(add figure here: para, dia vs ferro)

But we see magnetization in ferromagnetic material because their dipoles are uniformly aligned at room temperature, making the material behaves like a giant dipole.

### 3 Material under External B-field

Now we study what will happen when a material is magnetized by an external B-field:

1. External B-field acts on material, aligns the dipoles and changes their dipole moments.
2. New dipoles alignment create a new B-field, which also affects surrounding dipoles.
3. Alignment continues, until it reaches an equilibrium between external field and interactions between dipoles.

Theoretically, how the dipoles response to the external B-field is a complicated process when all the bondings and interactions are involved - it highly depends on the material's structure. So the final dipole alignment might not always align with the external B-field!

(add figure here: random spherical dipole + regular external B-field = irregular align ellipse dipole)

In a general theory about material's B-field response, one may treat the magnetization field  $\vec{M}$  (i.e. new dipole alignment) as some function to the total B-field  $\vec{B}_{\text{total}}$ ,

$$\vec{M} = f(\vec{B}_{\text{total}}) \sim \underbrace{\vec{a}_i^{(1)} B_i + \vec{a}_{ij}^{(2)} B_i B_j + \vec{a}_{ijk}^{(3)} B_i B_j B_k + \dots}_{\text{Like a Taylor expansion}}$$

This  $f$  function denotes a theoretical model that we have chosen to investigate the material. And the model parameters  $\vec{a}^{(1)}, \vec{a}^{(2)}, \vec{a}^{(3)} \dots$  shall be determined from experiment.

#### 3.1 Special Case: Linear Magnetic Material

Linear magnetic material is the simplest model of B-field response - where the dipoles are completely free to rotate, such that new dipole alignment is directly proportional to the external B-field's magnitude and direction. This assumption is applicable to most daily life materials.

(add figure here: dipoles uniform under external B-field)

The linear model only has 1 parameter to be determined from experiments - the proportionality constant between  $\vec{M}$  and  $\vec{B}_{\text{total}}$ .

$$\vec{M} = (\underset{\text{constant}}{\text{Some}}) \cdot \vec{B}_{\text{total}}$$

Unlike using  $\vec{P}$  v.s.  $\vec{E}$  in linear dielectric model, linear magnetization model is almost always written by  $\vec{M}$  v.s. a new kind of field  $\vec{H}$ . We shall explain what  $\vec{H}$  right after.

$$\boxed{\vec{M} = \chi_m \vec{H}}$$

Here the  $\chi_m$  is called **magnetic susceptibility**, a pure number (no unit) whose value depends on the type of material.

- $\chi_m = 0$  for vacuum (by definition), because there are no dipoles in a vacuum.
- $\chi_m < 0$  for diamagnetism, since their dipoles are opposite to the B-field's direction.
- $\chi_m > 0$  for paramagnetism, since their dipoles follow the B-field's direction.

## 3.2 Describing External Field

The total B-field is a result of the external B-field plus the field induced by dipole alignment. After we have chosen the model about dipole alignment, now we look at the external B-field.

### 3.2.1 Free Current Distribution

In order to create an external B-field around the material, we need a “setup” to build an external source of currents. For example, apply current through a long solenoid:

(add figure here: free charge vs bound charge in dielectric setup)

The currents that flow in the setup are given the name **free charges**, to distinguish from the bound currents (dipole alignment) in the material. They are “free” because we can always control them by varying the setup, making them known quantities in calculation.

(add figure here: adjust solenoid current - $\zeta$  adjust free current amount)

$$\mu_0 n I_{\text{free}} = |\vec{B}|$$

For calculation, free current densities are denoted like bound currents:

- Volume free current density  $\vec{J}_f(\vec{r})$  - Current distribution inside the setup.
- Surface free charge density  $\vec{K}_f(\vec{r})$  - Current on any surfaces of the setup.

In real practices, solenoid or a large U-shape electromagnet are the most common setup to create external B-field. The B-field can be directly controlled by controlling current. So line or surface free current are mostly all you need. No reason to make things complicated.

### 3.2.2 Auxiliary Field $\vec{H}$

Previously, we have related bound currents to a vector field quantity - the magnetization field  $\vec{M}$ . Similarly, free current can be related with another vector field. From Ampere’s law,

$$\begin{aligned} \frac{1}{\mu_0} \vec{\nabla} \times \vec{B}_{\text{total}} &= \vec{J}_{\text{total}} = \left( \begin{array}{l} \text{All} \\ \text{currents} \end{array} \right) \\ &= \vec{J}_f + \vec{J}_b = \left( \begin{array}{l} \text{Free currents} \\ \text{on setup} \end{array} \right) + \left( \begin{array}{l} \text{Bound currents} \\ \text{on material} \end{array} \right) \\ &= \vec{J}_f + \vec{\nabla} \times \vec{M} \\ \vec{\nabla} \times \left( \frac{1}{\mu_0} \vec{B} - \vec{M} \right) &= \vec{J}_f \end{aligned}$$

Here we define the **Auxiliary field**  $\vec{H}$ :

$$\vec{H} \stackrel{\text{def}}{=} \frac{1}{\mu_0} \vec{B} - \vec{M}$$

← This relation connects all 3 field quantities

Such that it is related to the free charge density by:

$$\begin{cases} \vec{J}_f(\vec{r}) \stackrel{\text{def}}{=} \vec{\nabla} \times \vec{H}(\vec{r}) \\ \vec{K}_f(\vec{r}) \stackrel{\text{def}}{=} \vec{H}(\vec{r}) \times \hat{n} \end{cases}$$

where  $\hat{n}$  is the (outward) unit normal vector on the equipment surface. Cross product with it shows the direction of the surface current relative to the  $\vec{H}$  field.

Notice the relations of  $\vec{H}$  with free currents are almost identical to  $\vec{B}$  with total currents in Ampere's law. In the special case of linear magnetic material, we can solve for  $\vec{H}$  from the given free currents like the Ampere's law integral form or with Biot-Savart law.

$$\begin{aligned} I_f &= \oint \vec{H}(\vec{r}) \cdot d\vec{l} \\ &= \oint |\vec{H}| |d\vec{l}| \cos \theta \quad \leftarrow \text{Just dot product} \\ &= |\vec{H}| \cos \theta \oint |d\vec{l}| \\ &\quad \uparrow \quad \uparrow \\ &\quad \text{Same magnitude everywhere} \quad \text{Form same angle everywhere} \\ &\quad \text{Can move out of integral} \quad \text{Can move out of integral} \\ &= |\vec{H}| \cos \theta \text{ (Perimeter of loop)} \end{aligned}$$

$$|\vec{H}| = \frac{I_f}{(\text{Perimeter of loop}) \cos \theta}$$

But note that this can be wrong for other models of magnetic material.

Side Note:

Although  $\vec{H}$  forms a PDE relationship to free current just like  $\vec{B}_{\text{total}}$  with total current, we cannot solve for  $\vec{H}$  exactly by free current if we don't know the material's model. This is because:

- $\vec{B}_{\text{total}}$  is guaranteed to be “divergent-less”, such that we can define a vector potential function  $\vec{A}$  and solve for  $\vec{B}_{\text{total}}$  uniquely.
- $\vec{M}$  may not be “divergent-less” since the dipole arrangement can be arbitrary, e.g. if they arrange into some vortex-like pattern. Then by  $\vec{H} = \frac{1}{\mu_0} \vec{B}_{\text{total}} - \vec{M}$ , there is no guaranteed that  $\vec{H}$  is “divergent-less” either.

(add figure here: vortex dipole arrangement - $\vec{M}$  field not curl 0)

But in the special case of linear magnetic material,

$\vec{M}$ aligns with $\vec{B}_{\text{total}}$	$\Rightarrow$	$\vec{M}$ is “divergent-less”	$\Rightarrow$	$\vec{H} = \frac{1}{\mu_0} \vec{B}_{\text{total}} - \vec{M}$ is also “divergent-less”
---	---------------	----------------------------------	---------------	--

So it is fine to solve for  $\vec{H}$  like normal Ampere's law problems for linear magnetic material.

### 3.3 Measurement in Practice

In problems that involve magnetic material,

- The material's magnetization (dipole alignment) is the cause of all troubles. But usually we are only told which material model we need to apply. (*E.g. Given a linear magnetic material ...*)
- Actual calculation requires measurements from equipment setup. In magnetostatic experiments, usually the control/measureable parameters are
  - Applied current - Directly connect with a power source. All you need is an ammeter.
  - Total B-field - Can be measured through magnetic force.

(add figure here: control set up with voltage or free charge procedure)

Then once we have chosen a model of the material, we can connect the two measurables by:

$$\vec{H} = \frac{1}{\mu_0} \vec{B}_{\text{total}} - f(\vec{B}_{\text{total}})$$

Then the model parameters in  $f(\dots)$  can be determined by experiments. But in the special case

of linear magnetic material, since there is only 1 constant parameter  $\chi_m$  for each material,

$$\begin{aligned}\vec{H} &= \frac{1}{\mu_0} \vec{B}_{\text{total}} - \chi_m \vec{H} \\ (1 + \chi_m) \vec{H} &= \frac{1}{\mu_0} \vec{B}_{\text{total}} \\ \vec{H} &= \frac{1}{\mu_0(1 + \chi_m)} \vec{B}_{\text{total}} \\ &= \frac{1}{(\text{A constant})} \cdot \vec{B}_{\text{total}}\end{aligned}$$

We usually use this new constant to represent the material's response to B-field, by defining

$$\boxed{\mu \stackrel{\text{def}}{=} \mu_0(1 + \chi_m) \stackrel{\text{def}}{=} \mu_0\mu_r} \quad \text{such that} \quad \vec{H} = \frac{1}{\mu} \vec{B}_{\text{total}}$$

where

- $\mu$  = **Absolute permeability**, or **magnetic permeability**. Has the same unit as  $\mu_0$ .
- $\mu_r$  = **Relative permeability**. A pure number.  $< 1$  for diamagnetism and  $> 1$  for paramagnetism.

Note that  $\vec{H}$  only depends on applied current, i.e. can be easily controlled in experiments.

- For convenience, experimentalists always prefer using  $\vec{H}$  to describe material's magnetic response. This is why the linear model is written as  $\vec{M} \propto \vec{H}$  instead of  $\vec{M} \propto \vec{B}_{\text{total}}$ .
- $\chi_m$  is more oftenly tabulated in material handbooks and used in theories. This is because most material has very small  $\chi_m$  (e.g.  $10^{-5}$  for aluminum). Tabulating  $\mu_r = 1 + \chi_m$  only makes the values harder to read.

(add figure here: do you prefer reading table of chi m or mu r?)

### 3.4 Calculation Example

Here are some examples of questions you may see in the chapter of linear magnetic material. In principle, one of the information about  $\vec{H}$  (free current) or  $\vec{B}_{\text{total}}$  (force) will be given, then you are asked to find the other, and so as  $\vec{M}$  and bound currents.

— The End —