

Volume/Delta Sprint

Indicators & Analysis / Volume & Delta | advanced | 4 min read | DeepCharts Help Center | August 24, 2026

Volume/Delta Sprint displays cumulative volume and delta values over specified time periods as a histogram in a separate panel beneath the chart. Where a plain volume histogram tells you how much traded per bar, Sprint accumulates activity across a rolling window, making sustained bursts of participation — and the side driving them — stand out from ordinary bar-to-bar noise.

It is an advanced tool: it rewards traders who already read delta and volume individually and want a single panel that shows how pressure builds and fades over a chosen lookback.

What it is

The indicator sums volume or delta over a configurable lookback window (**Length**, default **10** bars) and plots the result as histogram bars. Positive readings show the window was dominated by buying pressure, negative readings by selling pressure. The **Delta Color Mode** can shade each bar by the magnitude of that pressure — so a fading gradient tells you at a glance whether aggression is intensifying or draining away.

[SCREENSHOT PLACEHOLDER] Chart window with the Volume/Delta Sprint indicator in a separate footer panel — price candles above, Sprint histogram below showing a cluster of tall positive (buy-colored) bars during a rally followed by shrinking bars as the move stalls. [volume-delta-sprint-chart-overview.png](#)

When to use it

- You want to see whether a breakout is backed by a sustained sprint of volume and positive delta, not a single-bar spike.
- You track momentum decay: histogram bars shrinking while price still grinds higher warns that the aggressive side is stepping away.
- You compare activity regimes across a session — quiet accumulation windows versus high-participation impulse windows.
- You want a smoothed, filterable view of delta instead of the raw bar-by-bar values of Delta Bar.

Quick start

1. Open the **Indicator List** on your chart and add **Volume/Delta Sprint**.
2. Open the indicator's **Settings**.
3. Keep **Input Data** on **Volume** to start — switch to **Order** or **Trade** only when you have a specific reason (see [Different Types of Input Data for Indicators](#)).
4. Leave **Length** at its default of **10** bars; shorten it later if you trade fast intraday moves.
5. Set **Delta Color Mode** to **Fading** so bar color intensity reflects delta magnitude.
6. Leave **Filter Min** and **Filter Max** untouched at first — add filters once you know the typical trade sizes on your symbol.

[SCREENSHOT PLACEHOLDER] Volume/Delta Sprint settings dialog open on the General section, showing Input Data, Filter Min, Filter Max, Length = 10 and Delta Color Mode visible. [volume-delta-sprint-settings-general.png](#)

How to read it

- **Tall bars in one color** — a sprint: one side is committing size over the whole window. Sustained sprints in the direction of a breakout confirm participation.
- **Shrinking bars while price extends** — effort is fading; the move is running on fewer aggressive orders and becomes vulnerable to a pullback.

- **Color flip after a sprint** — the dominant side changed inside the lookback window; watch for price to follow.
- **Fading gradient (Fading mode)** — deeper color means larger delta magnitude, so the shade itself grades conviction; **Fixed** mode reduces this to a binary positive/negative read.

Because values are cumulative over the window, one large print keeps influencing the histogram for **Length** bars — expect readings to decay gradually rather than reset each bar.

Settings reference

General

Setting	What it does
Input Data	Calculation source: Volume (total traded activity), Order (order flow data), or Trade (executed transactions). See Different Types of Input Data for Indicators.
Filter Min	Minimum threshold for filtering the data — excludes low values to reduce noise.
Filter Max	Maximum threshold for filtering the data — removes outliers that distort the analysis.
Length	Lookback period for the cumulative window. Default 10 bars. Shorter lengths are more responsive; longer lengths show broader patterns.
Delta Color Mode	Fading applies gradient coloring based on delta magnitude; Fixed uses binary colors for positive and negative values.

Smoothing

Setting	What it does
Enable	Activates smoothing to reduce noise and clarify volume trends.
Average Type	Moving average method: Simple , Exponential , Triangular , or Weighted .
Length	Period for the moving-average calculation; higher values create smoother lines.

Subgraphs

Setting	What it does
Color	Primary bar color, used for positive delta / buying pressure.
2° Color	Secondary color, used for negative delta / selling pressure.
Subgraph Style	Drawing style. Default Bars (histogram).
Auto Color	Set to +/- for automatic positive/negative coloring.
Line Style	Default Solid for filled bars.
Line Width	Bar/line thickness. Default 3 pixels.
Short Name	Custom label shown in the panel legend.

Tips and common mistakes

- **Match Length to your timeframe.** A 10-bar window on a 1-minute chart covers 10 minutes of flow; the same setting on a 15-minute chart covers half a session. Re-tune when you change timeframes.
- **Do not stack filters blindly.** An aggressive **Filter Min** plus a short **Length** can leave the histogram nearly empty on quiet symbols. Add one constraint at a time.

- **Fading mode needs contrast.** Pick primary and secondary colors that remain distinguishable at low opacity, or magnitude grading becomes unreadable.
- **Smoothing trades speed for clarity.** Enabling a long smoothing average makes turns easier to see but delays them — momentum traders should keep smoothing short or off.

Related articles

- Orderflow 101: Bid, Ask, Aggressor and Delta
- Delta Bar
- Speed of Tape
- Deep Delta
- Different Types of Input Data for Indicators
- How to Change the Layout of Indicators