

Deep Profile Values

Indicators & Analysis / Deep Indicators | advanced | 8 min read | DeepCharts Help Center | July 15, 2026

Deep Profile Values (also called VBP Values) plots the key values of the volume-by-price analysis on your chart — Volume POC, Value Area, VWAP with standard deviations, Peaks and Valleys — without drawing the volume distributions themselves. You get the levels that matter on a clean chart.

Where Deep Profile (Volume / Delta Profile) shows the full histogram, this indicator extracts only its outputs, and adds line-extension logic powerful enough to track naked (virgin) POCs — levels that price has never returned to touch.

What it is

The indicator computes a volume profile over a period you define (composite, multiples, visible or personalized) and then draws only the resulting reference levels as lines: the point of control, the value area boundaries, the VWAP and its deviation bands, and high/low-volume nodes. Each line family has its own display, extension and styling controls, plus an optional per-profile data summary.

When to use it

- You trade off profile levels (POC, VAH/VAL, VWAP) but want candles readable — no histogram overlay.
- You track naked/virgin POCs across days: untouched levels that often act as magnets on revisit.
- You want VWAP with $\pm 1/\pm 2/\pm 3$ standard-deviation bands anchored to a profile period.
- You want several periods' key levels on screen at once (the **Number of Profiles** setting).

Quick start

1. Open a chart and add **Deep Profile Values** from the chart's **Indicators** button.
2. Set **VBP Period** to **Multiples** with **Length Type** = Days and **Length Value** = 1 so each day produces its own set of levels.
3. In the **POC** section, set **Enable** on and **Extend Line** to **Till Interaction**.
4. In **Value Area**, enable the lines with **% Value Area** = 70.
5. Apply — each day's POC and value area boundaries now draw as lines, and POC lines that price has not yet revisited keep extending: those are your naked POCs.

[SCREENSHOT PLACEHOLDER] Chart with Deep Profile Values active showing daily POC lines and value area boundary lines; one older POC line extends untouched across several days, annotated as a naked POC

deep-profile-values-naked-poc.png

How to read it

- **POC** — the highest-volume price of the period. It can be displayed fixed, developing (updating live as volume shifts), or with shifted-zone highlighting.
- **Value Area** — the price range containing the configured percentage of the period's volume (70% is the conventional choice). Its high and low boundaries are the classic VAH/VAL references.
- **VWAP** — the volume-weighted average price. Trading above it means paying more than the volume-weighted average — "expensive" relative to the session's business; below is "cheap." Institutions use it as an execution benchmark.
- **VWAP standard deviations** — ± 1 is the typical range where price usually remains; ± 2 marks meaningfully stretched conditions; ± 3 is rare and signals extreme movement.
- **Peaks and Valleys** — peaks are concentrated high-volume areas (strong market interest); valleys are low-volume voids that price tends to cross quickly.

- **Naked (virgin) levels** — with **Extend Line = Till Interaction**, a line stops the moment price touches it. Any line still extending has never been revisited: a naked POC or untested level. This is the key mechanic of the indicator.

See Understanding Volume Profile: POC, Value Area, HVN/LVN and Understanding VWAP for the concepts behind these levels.

Settings reference

Grouped as in the indicator dialog.

Note: The continuous line-extension option is listed as **Till End Window** in some sections and **Till End Interaction** in others. **[CONFIRM: exact label of the continuous Extend Line option in each section of the Deep Profile Values dialog]**

General settings

Setting	What it does
VBP Period	Reference timeframe: Composite (all loaded data in one profile), Multiples (separate profiles per time interval), Visible (based on the currently visible chart portion), Personalized (manual period from specific dates/times)
Length Type	Measurement unit for the profile: Minutes, Days, Weeks, Months or Volume
Length Value	How many Length Type units each profile covers

Custom Period

Setting	What it does
Start Date/Time	Beginning of the period when VBP Period is set to the personalized/customized mode

Data settings

Setting	What it does
Input Data	Calculation basis: Volume (total volume per level), Order (buy/sell order quantities), Aggregate Trades (combined trades at the same price), Number of Trades (transaction frequency per level). See Different Types of Input Data for Indicators
Filter Min	Minimum volume threshold for inclusion
Max Filter	Maximum ceiling, excluding distorting very large volumes

Auto Grouping

Setting	What it does
Type	Automatic (adapts tick grouping to the market) or Manual (you specify it)
Grouping Factor	Aggregation intensity in Automatic mode — higher means more aggregation
Tick in Manual	Grouped tick quantity in Manual mode

Plot settings

Setting	What it does
Number of Profiles	How many profiles' values display simultaneously for the selected period

POC

Setting	What it does
Enable	Shows the POC — the highest-volume price level
Show Line	Display method: Show (fixed line at the maximum-volume level), Developing (dynamic line updating as the POC moves), Extend Shifted (highlights the zones where the POC shifted during its evolution)
Extend Line	None (no extension beyond the period), Till Interaction (extends until price touches or exceeds the level — surviving lines are naked POCs), Till End Window (continuous across the chart)
Line-Color / Line Width	POC line styling
Dev. POC Start Time	When the dynamic (developing) POC calculation begins
Shifted POC Tick Grouping	How many ticks group together before a POC position counts as shifted
Opacity POC Grouping	Visibility of the grouped POC display — higher is more visible

Value Area

Setting	What it does
Enable	Shows the value area — the range containing the set percentage of volume
% Value Area	The percentage threshold (e.g. 70% draws the range holding 70% of total volume)
Show Line	Draws the lines delimiting the Value Area High and Low
Developing	Dynamic mode — plots the value area's shifts as traded volume changes
Extend Line	None , Till Interaction , or continuous across the chart
Line Color / Line Width	Value area line styling

Peaks and Valleys

Setting	What it does
Sensitivity	Detection precision — higher gives fewer (more significant) detections, lower gives more
Exclude High/Low	Automatically removes peaks/valleys at the profile's extreme top and bottom zones
Peak: Enable / Minimum Volume / Extend Line / Line Width / Line Color	Peak line visualization, its volume threshold, extension mode (None, Till Interaction, Till End Window) and styling
Valley: Enable / Minimum Volume / Extend Line / Line Width / Line Color	The same controls for valley lines

VWAP

Setting	What it does
Enable	Shows the VWAP line
Extend Line	None , Till Interaction , or continuous across the chart
Line Color / Line Width	VWAP line styling
Developing VWAP	Real-time dynamic VWAP that updates with each new volume

Setting	What it does
Enable Bands	Shows the standard-deviation envelope around the VWAP
Envelope Settings	Opens band customization, including how many standard deviations to draw

Summary

Setting	What it does
Enable-Summary	Shows a data summary per profile — total volume, delta, trades, ticks and related statistics
Volume Summary	Displays total traded volume
Trade Summary	Displays the total transaction count for the profile period
Text Color / Ask Color / Bid Color	Colors for the summary text and its ask/bid volume figures

Customized Timetable

Setting	What it does
Filter Mode	None (all data, no filtering), Filter (a custom temporal filter over a specific period), Split (divides the profile by sessions, e.g. morning/afternoon)
Ini Session / End Session	Trading session start and end times

Warning: Customized Timetable session times reference the U.S. time zone exclusively. If you trade from another region, convert your session boundaries before entering them, or the profiles will cover the wrong hours.

[SCREENSHOT PLACEHOLDER] Deep Profile Values settings dialog open at the POC section showing Show Line and Extend Line dropdowns with Till Interaction selected [deep-profile-values-settings-poc.png](#)

Tips and common mistakes

- **Hunting naked POCs:** set the POC **Extend Line** to **Till Interaction** — lines that survive are the untouched levels. With **Till End Window** every line extends forever and the naked/tested distinction disappears.
- **Too many peak/valley lines:** raise **Sensitivity** — higher values yield fewer but more meaningful detections — and use each line family's **Minimum Volume** threshold.
- **Levels shift when zooming:** Automatic grouping recalculates bar heights; set grouping to Manual (Tick in Manual = 1) to freeze level prices.
- **Values disagree with your Deep Profile histogram:** compare VBP Period, Input Data and grouping between the two indicators — they compute independently from their own settings.
- **Screen overload:** this indicator can draw POC, VA, VWAP, bands, peaks and valleys simultaneously. Enable one family at a time and keep only what you actually trade from.

Related articles

- Deep Profile (Volume / Delta Profile)
- Understanding Volume Profile: POC, Value Area, HVN/LVN
- Understanding VWAP
- VWAP Envelopes
- Dynamic POC
- Different Types of Input Data for Indicators