

Trading Panel Reference: Every Button and Field

Trading & Orders | intermediate | 8 min read | DeepCharts Help Center | July 15, 2026

The trading panel is the order-entry column that docks to the right side of every price chart. This article documents every readout, button and field on it, top to bottom, so you can look up exactly what a control does before you rely on it with live orders.

If you have never traded from a chart before, start with the walkthrough in [Trading from the Chart](#) — this page is the reference you come back to.

What it is

The trading panel answers one question: how do I send, protect and close orders on a specific instrument without leaving the chart? It bundles instrument selection, position readouts, an order-type button grid, one-click exit buttons and an OCO bracket block into a single column. It appears when **Trading panel** is toggled in the chart's bottom bar (or right-click → **Show Trading Panel, Ctrl Alt P**) and requires **Trading Enabled** (the green \$ icon) — disabling the \$ icon hides the panel automatically

[SCREENSHOT PLACEHOLDER] Full trading panel on the right edge of a chart, annotated in three zones from top to bottom: header readouts, account and quantity row, order button grid with exit buttons, OCO Strategy block
trading-panel-full-annotated.png

When to use it

- You execute from charts and want order entry, exits and brackets in one place.
- You need to trade a different contract than the one charted (mini chart, micro orders).
- You want one-click risk actions: **Cancel**, **Flat**, **Cancel and Flat**, **Breakeven**.
- You want automatic stop/target brackets (OCO) attached to every entry.

For ladder-style click trading at price levels, use the on-chart DOM instead — see [DOM Trading on the Chart \(Click-Trading Ladder\)](#).

Quick start

1. Open a chart and click the \$ icon so it turns green (Trading from the Chart covers this step by step).
2. Toggle **Trading panel** in the chart's bottom bar.
3. Set **Broker** to **SIM** and pick a simulation account (Trading Accounts and Simulation).
4. Set **Qty** to 1 and place a test order with **MKT**.
5. Close it with **Flat**.

How to read it

The header block tells you your exposure at a glance:

- **Open Qty** — how many contracts (or shares) you currently hold on the panel's instrument. 0 means flat.
- **Open P/L** — unrealized profit or loss of the open position, updating in real time.
- **Daily P/L** — the day's total profit or loss for this instrument.

In the OCO block, watch for the **red (!)** icon next to **Mode**: it means the selected MULTI strategy's total quantity does not match the panel's **Qty** field, and execution is blocked until you match them. Green checkmarks indicate the quantities are aligned

[SCREENSHOT PLACEHOLDER] Trading panel OCO block in MULTI mode showing the red exclamation icon next to the Mode dropdown, with the panel Qty field visible showing a mismatching value
trading-panel-oco-red-exclamation.png

Settings reference

Header — instrument and position

Control	What it does
Symbol dropdown	Opens Select Instrument to pick the contract the panel trades. A new chart pre-selects the chart's symbol; after you change either, chart and panel are independent (view NQ, trade MNQ). Only exchanges subscribed in Options → Symbol Manage are listed — Symbol Manage: Subscribe Exchanges and Map Your Feed.
Open Qty	Current open position size on the panel's instrument.
Open P/L	Unrealized P/L of that position.
Daily P/L	The day's realized plus open P/L for the instrument.

Account row

Control	What it does
Qty	Contract size for the next order. The pre-filled value and the step size when nudging it come from Options → Settings → Trading Quantity (per-symbol Default Quantity and Increment Quantity). It is a convenience default, not a limit — hard caps belong in the Risk Manager.
Broker	Which connection executes the order — a live feed/broker connection or SIM for paper trading.
Account	The account under that broker connection (relevant for multi-account and prop-firm setups).

Ticks diff.

Control	What it does
Ticks diff. checkbox + number	Modifies the BID/ASK buttons. Off (default 0): BID buys limit at the best bid, ASK sells limit at the best ask. With a difference N enabled: BID places the buy limit N ticks below the best bid, ASK places the sell limit N ticks above the best ask. Use it to rest orders a fixed distance behind the market with one click.

Order button grid

Each row has a buy button (left) and a sell button (right).

Button	Order placed	When to use it
MKT	Market order	You want in or out now and accept the current price.
BID / ASK	Limit at best bid (buy) / best ask (sell), offset by Ticks diff. if enabled	Joining the best price passively instead of crossing the spread.
LMT	Limit at your chosen price	Buy below the market or sell above it. Placed on the wrong side it fills immediately as a market order.
STP	Stop that triggers a market order	Buy above the market or sell below it — breakout entries and protective stops.
STP LMT	Stop-limit	Avoids slippage on the trigger, at the risk of not being executed at all.

Exit and cancel buttons

All four act only on the symbol currently selected in the panel.

Button	What it does
Cancel	Cancels all working (pending) orders — LMT/STP. Open positions are not touched.
Flat	Closes the current open position only.
Cancel and Flat	Closes the open position and cancels all remaining working orders.
Breakeven	Moves the stop to breakeven: entry price plus the Breakeven - Ticks buffer set in Options → Settings → General → Trading . 0 = exact entry; raise it to cover commissions/slippage.

OCO Strategy block

The bracket engine — one executed exit cancels the other. Full walkthrough: OCO (One-Cancels-the-Other) Strategies.

Control	What it does
OCO Strategy toggle	Arms automatic brackets for new entries.
Mode	SL/TP = one stop loss and one target, each defined in ticks or money and individually enabled. MULTI = named multi-bracket strategies for scaling out.
SL / TP fields	The stop-loss and take-profit distances (ticks or money) in SL/TP mode.
BE	Breakeven automation in SL/TP mode (ticks or money).
Trail	Trailing-stop automation in SL/TP mode, with trailing amount and offset fields below.
Gear icon (MULTI)	Opens the Oco Strategy editor: name the strategy, add Stop/Target brackets (each with a quantity and a Ticks/Money value, added via Add bracket), optionally move the stop to breakeven after a target fills, then Save . Saved strategies become selectable in the panel when MULTI mode is on.
Server / Client radio	Where the bracket lives. Server : managed on the data-feed provider's server — survives closing the platform or losing your connection. Client : managed inside DeepCharts — the platform must stay open and connected or the OCO is not effective. Client exists because some feed providers do not offer server-side OCO.
Link pending orders	For a take-profit and stop-loss you already placed without OCO: opens a window to select the two pending orders and links them into an OCO pair retroactively.

Warning: Rithmic does not allow server-side OCO together with copy trading. If you run the How to Set Up the Trade Copier on Rithmic, you must use **Client**-side OCO — and keep the platform open and online, or your brackets will not fire. A single Rithmic account without the copier can use Server normally.

Related settings outside the panel

Setting	Location	What it does
Breakeven - Ticks	Options → Settings → General → Trading	Buffer added to entry when the Breakeven button moves your stop.

Setting	Location	What it does
Frequency Limitation	Options → Settings → General → Trading	Max orders per second plus a pause duration after exceeding it — protects against accidental rapid-fire submissions.
Default / Increment Quantity	Options → Settings → Trading Quantity	Per-symbol starting value and step size for the Qty field. Changing the default does not modify working orders or open positions — only future orders. Whether it also applies to DOM/chart-click order entry is not confirmed; verify on a SIM account.

Tips and common mistakes

- **Panel gone?** The \$ Trading Enabled icon was toggled off — it auto-hides the panel. Re-arm with **Ctrl Alt T**.
- **Limit filled instantly at market price.** It was placed on the wrong side (buy limit above / sell limit below). The click ladder in DOM Trading on the Chart (Click-Trading Ladder) picks LMT vs STP automatically from the level you click, removing the decision entirely.
- **"Flat" vs "Cancel and Flat".** Flat only closes the position; a forgotten resting stop or target keeps working. Cancel and Flat clears both. End of session, verify in the Orders Window with the **Submitted** filter that nothing is still live.
- **MULTI strategy will not execute.** Check for the red (!) — the strategy's total quantity must equal the panel **Qty**. Change one to match the other.
- **Brackets vanished after closing the platform.** They were Client-side. Only Server-side OCO survives with the platform closed.
- **Test sizing changes on SIM first.** Raising the default quantity from 1 to 2 doubles the size — and the risk — of every future order on that symbol.

Related articles

- Trading from the Chart
- OCO (One-Cancels-the-Other) Strategies
- DOM Trading on the Chart (Click-Trading Ladder)
- Orders Window
- Risk Manager
- How to Set Up the Trade Copier