



Graduation Project

Implementing a Secure Multi-Branch Office Network

File Configurations

Cisco Cybersecurity Engineer (ONL2 ISS5 S2)

Made by

Ahmed Mohamed Gharib

Abdul Rahman Mohammed Hamed


Hassan Muhammed Abdelnabi

Muhammed Samy Elhamzawy

Muhammed Mustafa Gomaa

Supervised by

Eng. Amr Adel



Agenda

Page No	Device
4	HQ-Edge1
7	HQ-Edge2
9	HQ-NGFW1
11	HQ-NGFW2
13	HQ-DMZ-MLS
16	HQ-CORE-MLS1
19	HQ-CORE-MLS2
21	HQ-DIS-MLS1
27	HQ-DIS-MLS2
32	HQ-ACC-SW1
36	HQ-ACC-SW2
39	HQ-ACC-SW3
42	HQ-ACC-SW4
45	HQ-ACC-SW5
48	HQ-ACC-SW6
52	HQ-ACC-SW7
54	HQ-ACC-SW
57	HQ-SW-CAM-F1
60	HQ-SW-CAM-F2
63	HQ-SW-CAM-F3
66	HQ-SW-CAM-F4
69	B1-EdgeRouter
71	B1-NGFW
73	B1-DMZ-MLS
76	B1-CORE-MLS1
81	B1-CORE-MLS2
85	B1-ACC-SW1
89	B1-ACC-SW2
92	B1-ACC-SW3

No	Description
1	Interfaces IP Addresses
	Configuration
	HQ-Egde1(config)#interface Loopback1 HQ-Egde1(config-if)#ip address 1.1.1.8 255.255.255
	HQ-Egde1(config)#interface GigabitEthernet0/0/0 HQ-Egde1(config-if)#no shutdown
	HQ-Egde1(config-if)#ip address 172.16.0.25 255.255.255.252 HQ-Egde1(config-if)#ip ospf authentication message-digest
	HQ-Egde1(config-if)#ip ospf message-digest-key 1 md5 DEPI HQ-Egde1(config-if)#ip nat inside
	HQ-Egde1(config)#interface GigabitEthernet0/0/1 HQ-Egde1(config-if)#no shutdown
	HQ-Egde1(config-if)#ip address 172.16.0.34 255.255.252
	HQ-Egde1(config-if)#ip ospf authentication message-digest HQ-Egde1(config-if)#ip ospf message-digest-key 1 md5 DEPI
	HQ-Egde1(config-if)#ip nat inside
	HQ-Egde1(config)#interface GigabitEthernet0/0/2 HQ-Egde1(config-if)#ip address 50.50.20.1 255.255.248
	HQ-Egde1(config-if)#ip nat outside
	HQ-Egde1(config-if)#crypto map VPN-B1
2	OSPF Routing
	Configuration
	HQ-Egde1(config)#router ospf 1 HQ-Egde1(config-router)#router-id 1.1.1.8
	HQ-Egde1(config)#redistribute static subnets
	HQ-Egde1(config)#passive-interface GigabitEthernet0/0/2 HQ-Egde1(config-router)#area 0 authentication message-digest
	HQ-Egde1(config)#network 172.16.0.24 0.0.0.3 area 0

	HQ-Egde1(config)#network 172.16.0.32 0.0.0.3 area 0
3	Default Route & Static Route
	Configuration HQ-Egde1(config)#ip route 0.0.0.0 0.0.0 50.50.20.22 HQ-Egde1(config)#ip route 192.168.71.0 255.255.255.0 50.50.20.2 HQ-Egde1(config)#ip route 192.168.61.0 255.255.255.0 50.50.20.2 HQ-Egde1(config)#ip route 192.168.81.0 255.255.255.0 50.50.20.2 HQ-Egde1(config)#ip route 192.168.31.0 255.255.255.0 50.50.20.2 HQ-Egde1(config)#ip route 195.1.1.0 255.255.255.240 172.16.0.26 HQ-Egde1(config)#ip route 195.1.1.0 255.255.255.240 172.16.0.33 HQ-Egde1(config)#ip route 192.168.41.0 255.255.255.0 50.50.20.2 HQ-Egde1(config)#ip route 10.1.0.0 255.255.255.0 50.50.20.2
4	PAT
	Configuration HQ-Egde1(config)#ip access-list standard NAT HQ-Egde1(config-std-nacl)#deny udp host 195.1.1.3 eq domain 192.168.0.0 0.0.255.255 HQ-Egde1(config-std-nacl)#deny ip 192.168.0.0 0.0.255.255 192.168.0.0 0.0.255.255 HQ-Egde1(config-std-nacl)#deny tcp host 195.1.1.6 eq 443 192.168.0.0 0.0.255.255 HQ-Egde1(config-std-nacl)#deny udp host 195.1.1.8 eq 123 any eq 123 HQ-Egde1(config-std-nacl)#deny tcp host 195.1.1.10 eq ftp 192.168.31.0 0.0.0.15 HQ-Egde1(config-std-nacl)#deny tcp host 195.1.1.9 eq ftp 192.168.71.0 0.0.0.15 HQ-Egde1(config-std-nacl)#permit ip any any HQ-Egde1(config)#ip nat pool NatPool 50.50.20.1 50.50.20.1 netmask 255.255.255.248 HQ-Egde1(config)#ip nat inside source list Nat pool NatPool overload HQ-Egde1(config)#in range gig0/0/0,gig0/0/1 HQ-Egde1(config-if-range)#in t gig0/0/2 HQ-Egde1(config-if)#ip nat outside
5	NTP
	Configuration

	HQ-Egde1(config)#ntp authentication-key 123 md5 cisco HQ-Egde1(config)#ntp authenticate HQ-Egde1(config)#ntp trusted-key 123 HQ-Egde1(config)#ntp server 195.1.1.8
6	Sys-logs
	Configuration HQ-Egde1(config)#service timestamps log datetime msec HQ-Egde1(config)#logging 195.1.1.5
7	Disable CDP
	Configuration HQ-Egde1(config)#int g0/0/2 HQ-Egde1(config-if)#no cdp enable
8	AAA
	Configuration
9	VPN (IPsec)
	Configuration

HQ-Egde1(config)# access-list 100 permit ip 192.168.30.0 0.0.0.31 192.168.31.0 0.0.0.15

Crypto Map

HQ-Egde1(config)# crypto map VPN_B1 10 ipsec-isakmp

HQ-Egde1(config-crypto-map)# match address 100

HQ-Egde1(config-crypto-map)# set peer 50.24.32.26

HQ-Egde1(config-crypto-map)# set transform-set B1

Apply Crypto Map to Interface

HQ-Egde1(config)# interface GigabitEthernet0/0/2

HQ-Egde1(config-if)# crypto map VPN-B1

HQ-Edge2

No	Description
1	Interfaces IP Addresses
	Configuration HQ-Egde2(config)#interface GigabitEthernet0/0/0 HQ-Egde2(config-if)#no shutdown HQ-Egde2(config-if)#ip address 172.16.0.29 255.255.255.252 HQ-Egde2(config-if)#ip ospf authentication message-digest HQ-Egde2(config-if)#ip ospf message-digest-key 1 md5 DEPI HQ-Egde2(config)#interface GigabitEthernet0/0/1 HQ-Egde2(config-if)#no shutdown HQ-Egde2(config-if)#ip address 172.16.0.37 255.255.252 HQ-Egde2(config-if)#ip ospf authentication message-digest HQ-Egde2(config-if)#ip ospf message-digest-key 1 md5 DEPI HQ-Egde2(config)#interface Loopback1 HQ-Egde2(config-if)#ip address 1.1.1.9 255.255.255.255.255
2	OSPF Routing
	Configuration HQ-Egde2(config)#router ospf 1 HQ-Egde2(config-router)#router-id 1.1.1.9

	HQ-Egde2(config)#redistribute static subnets HQ-Egde2(config)#passive-interface GigabitEthernet0/0/2 HQ-Egde2(config-router)#area 0 authentication message-digest HQ-Egde2(config)#network 172.16.0.24 0.0.0.3 area 0 HQ-Egde2(config)#network 172.16.0.32 0.0.0.3 area 0	
3	Default Route & Static Route	
	Configuration HQ-Egde2(config)#ip route 0.0.0.0 0.0.0.0 50.50.20.10 HQ-Egde2(config)#ip route 195.1.1.0 255.255.255.240 172.16.0.38 HQ-Egde2(config)#ip route 195.1.1.0 255.255.255.240 172.16.0.30	
4	PAT & Static NAT	
	Configuration HQ-Egde2(config)#ip nat inside source static 195.1.1.6 50.50.20.11 HQ-Egde2(config)#ip access-list standard NAT HQ-Egde2(config-std-nacl)#permit ip any any HQ-Egde2(config)#ip nat pool NatPool 50.50.20.9 50.50.20.9 netmask 255.255.255.248 HQ-Egde2(config)#ip nat inside source list Nat pool NatPool overload HQ-Egde2(config)#int range gig0/0/0,gig0/0/1 HQ-Egde2(config-if-range)#ip nat inside HQ-Egde2(config-if-range)#int gig0/0/2 HQ-Egde2(config-if)#ip nat outside	
5	NTP	
	Configuration HQ-Egde2(config)#ntp authentication-key 123 md5 cisco HQ-Egde2(config)#ntp authenticate HQ-Egde2(config)#ntp trusted-key 123 HQ-Egde2(config)#ntp server 195.1.1.8	

6	Sys-logs
	Configuration HQ-Egde2(config)#service timestamps log datetime msec HQ-Egde2(config)#logging 195.1.1.5
7	Disable CDP
	Configuration HQ-Egde2(config)#int g0/0/2 HQ-Egde2(config-if)#no cdp enable

HQ-NGFW1

No	Description
1	Interfaces IP Addresses
	Configuration HQ-NGFW1(config)#interface GigabitEthernet1/1 HQ-NGFW1(config-if)#no shutdown HQ-NGFW1(config-if)#ip address 172.16.0.2 255.255.255.252 HQ-NGFW1(config-if)#nameif INSIDE1 HQ-NGFW1(config-if)#security-level 100 HQ-NGFW1(config-if)#ospf authentication message-digest HQ-NGFW1(config-if)#ospf message-digest-key 1 md5 DEPI HQ-NGFW1(config)#interface GigabitEthernet1/2 HQ-NGFW1(config-if)#no shutdown HQ-NGFW1(config-if)#ip address 172.16.0.10 255.255.255.255 HQ-NGFW1(config-if)#nameif INSIDE2 HQ-NGFW1(config-if)#security-level 100 HQ-NGFW1(config-if)#ospf authentication message-digest HQ-NGFW1(config-if)#ospf message-digest-key 1 md5 DEPI HQ-NGFW1(config-if)#interface GigabitEthernet1/3

	Configuration HQ-NGFW1(config)#access-list DMZ-INSIDE extended permit udp host 195.1.1.2 any eq bootps HQ-NGFW1(config)#access-list DMZ-INSIDE extended permit udp host 195.1.1.2 any eq bootpc HQ-NGFW1(config)#access-list DMZ-INSIDE extended permit udp host 195.1.1.3 eq domain any HQ-NGFW1(config)#access-list DMZ-INSIDE extended permit udp host 195.1.1.8 eq 123 any
5	NTP
	Configuration HQ-NGFW1(config)#ntp authentication-key 123 md5 cisco

HQ-NGFW2

No	Description
1	Interfaces IP Addresses
	Configuration HQ-NGFW2(config)#interface GigabitEthernet1/1 HQ-NGFW2(config-if)#no shutdown HQ-NGFW2(config-if)#ip address 172.16.0.6 255.255.255.252 HQ-NGFW2(config-if)#nameif INSIDE1 HQ-NGFW2(config-if)#security-level 100 HQ-NGFW2(config-if)#no shutdown HQ-NGFW2(config-if)#no shutdown HQ-NGFW2(config-if)#ip address 172.16.0.14 255.255.252 HQ-NGFW2(config-if)#nameif INSIDE2 HQ-NGFW2(config-if)#security-level 100 HQ-NGFW2(config-if)#interface GigabitEthernet1/3 HQ-NGFW2(config-if)#interface GigabitEthernet1/3 HQ-NGFW2(config-if)#in shutdown HQ-NGFW2(config-if)#ip address 172.16.0.21 255.255.255.252 HQ-NGFW2(config-if)#nameif DMZ

	HQ-NGFW2(config-if)#security-level 50
	HQ-NGFW2(config-if)#interface GigabitEthernet1/4 HQ-NGFW2(config-if)#no shutdown HQ-NGFW2(config-if)#ip address 172.16.0.30 255.255.255.252 HQ-NGFW2(config-if)#nameif OUTSIDE1 HQ-NGFW2(config-if)#security-level 0
	HQ-NGFW2(config-if)#interface GigabitEthernet1/5 HQ-NGFW2(config-if)#no shutdown HQ-NGFW2(config-if)#ip address 172.16.0.33 255.255.255.252 HQ-NGFW2(config-if)#nameif OUTSIDE2 HQ-NGFW2(config-if)#security-level 0
2	OSPF Routing
	Configuration
	HQ-NGFW2(config)#router ospf 1 HQ-NGFW2(config-router)#router-id 1.1.1.7 HQ-NGFW2(config-router)#network 172.16.0.4 255.255.255.252 area 0 HQ-NGFW2(config-router)#network 172.16.0.12 255.255.255.252 area 0 HQ-NGFW2(config-router)#network 172.16.0.20 255.255.255.252 area 0 HQ-NGFW2(config-router)#network 172.16.0.28 255.255.252 area 0 HQ-NGFW2(config-router)#network 172.16.0.32 255.255.252 area 0
3	Default Route
	Configuration HQ-NGFW2(config)#route OUTSIDE1 0.0.0.0 0.0.0.0 172.16.0.29 1 HQ-NGFW2(config)#route OUTSIDE2 0.0.0.0 0.0.0.0 172.16.0.34 10
4	Access Lists (ACLs) Configuration
	Configuration HQ-NGFW1(config)#access-list DMZ-INSIDE extended permit udp host 195.1.1.2 any eq bootps HQ-NGFW1(config)#access-list DMZ-INSIDE extended permit udp host 195.1.1.2 any eq bootpc HQ-NGFW1(config)#access-list DMZ-INSIDE extended permit udp host 195.1.1.3 eq domain any HQ-NGFW1(config)#access-list DMZ-INSIDE extended permit udp host 195.1.1.8 eq 123 any

5	NTP
	Configuration
	HQ-NGFW1(config)#ntp authentication-key 123 md5 cisco HQ-NGFW1(config)#ntp authenticate HQ-NGFW1(config)#ntp trusted-key 123 HQ-NGFW1(config)#ntp server 195.1.1.8

HQ-DMZ-MLS

No	Description
1	Create Vlans
	Configuration HQ-DMZ-MLS(config)#vlan 40 HQ-DMZ-MLS(config-vlan)#name Servers HQ-DMZ-MLS(config)#vlan 999 HQ-DMZ-MLS(config-vlan)#name PARKING_VLAN
2	OSPF Routing
	Configuration HQ-Egde1(config)#router ospf 1 HQ-Egde1(config-router)#router-id 1.1.1.8 HQ-Egde1(config)#redistribute static subnets HQ-Egde1(config)#passive-interface GigabitEthernet0/0/2 HQ-Egde1(config-router)#area 0 authentication message-digest HQ-Egde1(config)#network 172.16.0.24 0.0.0.3 area 0 HQ-Egde1(config)#network 172.16.0.32 0.0.0.3 area 0
3	Interfaces IP Addresses

	Configuration
	HQ-DMZ-MLS(config)#ip routing
	HQ-DMZ-MLS(config)#interface loopback 0 HQ-DMZ-MLS(config-if)#ip address 1.1.1.6 255.255.255
	HQ-DMZ-MLS(config)#interface GigabitEthernet1/0/1 HQ-DMZ-MLS(config-if)#no switchport HQ-DMZ-MLS(config-if)#ip address 172.16.0.18 255.255.255.252 HQ-DMZ-MLS(config-if)#ip ospf authentication message-digest HQ-DMZ-MLS(config-if)#ip ospf message-digest-key 1 md5 DEPI
	HQ-DMZ-MLS(config)#interface GigabitEthernet1/0/2 HQ-DMZ-MLS(config-if)#no switchport HQ-DMZ-MLS(config-if)#ip address 172.16.0.22 255.255.255.252 HQ-DMZ-MLS(config-if)#ip ospf authentication message-digest HQ-DMZ-MLS(config-if)#ip ospf message-digest-key 1 md5 DEPI
	HQ-DMZ-MLS(config)#int vlan 40 HQ-DMZ-MLS(config-if)#ip address 195.1.1.1 255.255.255.240 HQ-DMZ-MLS(config-if)# ip ospf authentication message-digest HQ-DMZ-MLS(config-if)# ip ospf message-digest-key 1 md5 DEPI
4	STP
	Configuration
	HQ-DMZ-MLS(config)#no spanning-tree vlan 1,40,999 HQ-DMZ-MLS(config)#spanning-tree mode rapid-pvst HQ-DMZ-MLS(config)#spanning-tree portfast default HQ-DMZ-MLS(config)#spanning-tree portfast bpduguard default
5	OSPF Routing
5	OSPF Routing Configuration

6	Default Route
	Configuration
	HQ-DMZ-MLS(config)#ip route 0.0.0.0 0.0.0.0 172.16.0.17
7	Access Interfaces & Disabled Interfaces
	Configuration
	HQ-DMZ-MLS(config)#int range gigabitEthernet 1/0/3-9 HQ-DMZ-MLS(config-if-range)#switchport mode access HQ-DMZ-MLS(config-if-range)#switchport access vlan 50
	HQ-DMZ-MLS(config)#int range gigabitEthernet 1/0/10-24,g1/1/1-4 HQ-DMZ-MLS(config-if-range)#switchport mode access HQ-DMZ-MLS(config-if-range)#switchport access vlan 999 HQ-DMZ-MLS(config-if-range)#shutdown
8	NTP
	Configuration
	HQ-DMZ-MLS(config)#ntp authentication-key 123 md5 cisco HQ-DMZ-MLS(config)#ntp authenticate
	HQ-DMZ-MLS(config)#ntp authenticate HQ-DMZ-MLS(config)#ntp trusted-key 123 HQ-DMZ-MLS(config)#ntp server 195.1.1.8
9	Sys-logs
	Configuration
	HQ-DMZ-MLS(config)#service timestamps log datetime msec HQ-DMZ-MLS(config)#logging 195.1.1.5
10	AAA
	Configuration

HQ-DMZ-MLS(config)#username DEPI privilege 15 algorithm-type scrypt secret 123 HQ-DMZ-MLS(config)#enable algorithm-type scrypt secret depi

HQ-DMZ-MLS(config)#aaa new-model
HQ-DMZ-MLS(config)#tacacs-server host 195.1.1.7 key DEPI
HQ-DMZ-MLS(config)#aaa authentication login default group tacacs+ local
HQ-DMZ-MLS(config)#aaa authorization exec default group tacacs+ local
HQ-DMZ-MLS(config)#aaa accounting exec default start-stop group tacacs+

HQ-DMZ-MLS(config)#ip domain-name HQ-ACC-SW8.depi
HQ-DMZ-MLS(config)#crypto key generate rsa general-keys modulus 1024
HQ-DMZ-MLS(config)#lip ssh version 2

HQ-DMZ-MLS(config)#line vty 0 2
HQ-DMZ-MLS(config-line)#login authentication default
HQ-DMZ-MLS(config-line)#transport input ssh

HQ-DMZ-MLS

No	Description
1	Interfaces IP Addresses
	Configuration
	HQ-CORE-MLS1(config)#ip routing
	HQ-CORE-MLS1(config)#int loopback 0
	HQ-CORE-MLS1(config-if)#ip address 1.1.1.1 255.255.255
	HQ-CORE-MLS1(config)#interface GigabitEthernet1/0/2
	HQ-CORE-MLS1(config-if)#no switchport
	HQ-CORE-MLS1(config-if)#ip address 10.0.0.10 255.255.255
	HQ-CORE-MLS1(config-if)#ip ospf authentication message-digest
	HQ-CORE-MLS1(config-if)#ip ospf message-digest-key 1 md5 DEPI
	HQ-CORE-MLS1(config)#interface GigabitEthernet1/0/3
	HQ-CORE-MLS1(config-if)#no switchport
	HQ-CORE-MLS1(config-if)#ip address 10.0.0.18 255.255.255.252

	HQ-CORE-MLS1(config-if)#ip ospf authentication message-digest HQ-CORE-MLS1(config-if)#ip ospf message-digest-key 1 md5 DEPI
	HQ-CORE-MLS1(config)#interface GigabitEthernet1/0/4 HQ-CORE-MLS1(config-if)#no switchport
	HQ-CORE-MLS1(config-if)#ip address 172.16.0.1 255.255.252 HQ-CORE-MLS1(config-if)#ip ospf authentication message-digest
	HQ-CORE-MLS1(config-if)#ip ospf message-digest-key 1 md5 DEPI
	HQ-CORE-MLS1(config)#interface GigabitEthernet1/0/5 HQ-CORE-MLS1(config-if)#no switchport
	HQ-CORE-MLS1(config-if)#ip address 172.16.0.13 255.255.252
	HQ-CORE-MLS1(config-if)#ip ospf authentication message-digest HQ-CORE-MLS1(config-if)#ip ospf message-digest-key 1 md5 DEPI
2	OSPF Routing
	Configuration
	HQ-CORE-MLS1(config)#router ospf 1 HQ-CORE-MLS1(config-router)#router-id 1.1.1.1
	HQ-CORE-MLS1(config-router)#area 0 authentication message-digest
	HQ-CORE-MLS1(config-router)#network 10.0.0.8 0.0.0.3 area 0 HQ-CORE-MLS1(config-router)#network 10.0.0.16 0.0.0.3 area 0
	HQ-CORE-MLS1(config-router)#network 172.16.0.0 0.0.0.3 area 0 HQ-CORE-MLS1(config-router)#network 172.16.0.12 0.0.0.3 area 0
3	Default Route
	Configuration
	Configuration HQ-CORE-MLS1(config)#ip route 0.0.0.0 0.0.0.0 172.16.0.2 1 HQ-CORE-MLS1(config)#ip route 0.0.0.0 0.0.0.0 172.16.0.14 10
4	HQ-CORE-MLS1(config)#ip route 0.0.0.0 0.0.0.0 172.16.0.2 1
4	HQ-CORE-MLS1(config)#ip route 0.0.0.0 0.0.0.0 172.16.0.2 1 HQ-CORE-MLS1(config)#ip route 0.0.0.0 0.0.0.0 172.16.0.14 10
4	HQ-CORE-MLS1(config)#ip route 0.0.0.0 0.0.0.0 172.16.0.2 1 HQ-CORE-MLS1(config)#ip route 0.0.0.0 0.0.0.0 172.16.0.14 10 Disabled Interfaces

5	NTP
	Configuration
	HQ-CORE-MLS1(config)#ntp authentication-key 123 md5 cisco HQ-CORE-MLS1(config)#ntp authenticate HQ-CORE-MLS1(config)#ntp trusted-key 123 HQ-CORE-MLS1(config)#ntp server 195.1.1.8
6	Sys-logs
	Configuration
	HQ-CORE-MLS1(config)#service timestamps log datetime msec HQ-CORE-MLS1(config)#logging 195.1.1.5
7	AAA
	Configuration
	HQ-CORE-MLS1(config)#username DEPI privilege 15 algorithm-type scrypt secret 123 HQ-CORE-MLS1(config)#enable algorithm-type scrypt secret depi
	HQ-CORE-MLS1(config)#aaa new-model HQ-CORE-MLS1(config)#tacacs-server host 195.1.1.7 key DEPI HQ-CORE-MLS1(config)#aaa authentication login default group tacacs+ local HQ-CORE-MLS1(config)#aaa authorization exec default group tacacs+ local HQ-CORE-MLS1(config)#aaa accounting exec default start-stop group tacacs+
	HQ-CORE-MLS1(config)#ip domain-name HQ-CORE-MLS1.depi HQ-CORE-MLS1(config)#crypto key generate rsa general-keys modulus 1024 HQ-CORE-MLS1(config)#ip ssh version 2
	HQ-CORE-MLS1(config)#line vty 0 2 HQ-CORE-MLS1(config-line)#login authentication default HQ-CORE-MLS1(config-line)#transport input ssh

HQ-CORE-MLS2

No	Description
1	Interfaces IP Addresses
	Configuration
	HQ-CORE-MLS2(config)#ip routing
	HQ-CORE-MLS2(config)#interface GigabitEthernet1/0/2 HQ-CORE-MLS2(config-if)#no switchport HQ-CORE-MLS2(config-if)#ip address 10.0.0.14 255.255.255.252 HQ-CORE-MLS2(config-if)#ip ospf authentication message-digest HQ-CORE-MLS2(config-if)#ip ospf message-digest-key 1 md5 DEPI
	HQ-CORE-MLS2(config)#interface GigabitEthernet1/0/3 HQ-CORE-MLS2(config-if)#no switchport HQ-CORE-MLS2(config-if)#ip address 10.0.0.22 255.255.255.252 HQ-CORE-MLS2(config-if)#ip ospf authentication message-digest HQ-CORE-MLS2(config-if)#ip ospf message-digest-key 1 md5 DEPI
	HQ-CORE-MLS2(config)#interface GigabitEthernet1/0/4 HQ-CORE-MLS2(config-if)#no switchport HQ-CORE-MLS2(config-if)#ip address 172.16.0.5 255.255.0.0 HQ-CORE-MLS2(config-if)#ip ospf authentication message-digest HQ-CORE-MLS2(config-if)#ip ospf message-digest-key 1 md5 DEPI

	Configuration H HQ-CORE-MLS2(config)#ntp authentication-key 123 md5 cisco
5	NTP
	Configuration HQ-CORE-MLS2(config)#int range g1/0/6-24,g1/1/1-4 HQ-CORE-MLS2(config-if-range)#shutdown HQ-CORE-MLS2(config-if-range)#switchport access vlan 999
4	Disabled Interfaces
	Configuration HQ-CORE-MLS2(config)#ip route 0.0.0.0 0.0.0.0 172.16.0.6 1 HQ-CORE-MLS2(config)#ip route 0.0.0.0 0.0.0.0 172.16.0.10 10
3	Default Route
	Configuration HQ-CORE-MLS2(config)#router ospf 1 HQ-CORE-MLS2(config-router)#router-id 1.1.1.2 HQ-CORE-MLS1(config-router)#area 0 authentication message-digest HQ-CORE-MLS2(config-router)#network 10.0.0.12 0.0.0.3 area 0 HQ-CORE-MLS2(config-router)#network 10.0.0.20 0.0.0.3 area 0 HQ-CORE-MLS2(config-router)#network 172.16.0.4 0.0.0.3 area 0 HQ-CORE-MLS2(config-router)#network 172.16.0.8 0.0.0.3 area 0
2	OSPF Routing
	HQ-CORE-MLS2(config)#interface GigabitEthernet1/0/5 HQ-CORE-MLS2(config-if)#no switchport HQ-CORE-MLS2(config-if)#ip address 172.16.0.9 255.255.0.0 HQ-CORE-MLS2(config-if)#ip ospf authentication message-digest HQ-CORE-MLS2(config-if)#ip ospf message-digest-key 1 md5 DEPI

	HQ-CORE-MLS2(config)#ntp authenticate HQ-CORE-MLS2(config)#ntp trusted-key 123 HQ-CORE-MLS2(config)#ntp server 195.1.1.8
6	Sys-logs
	Configuration HQ-CORE-MLS2(config)#service timestamps log datetime msec HQ-CORE-MLS2(config)#logging 195.1.1.5
7	AAA
	Configuration HQ-CORE-MLS2(config)#username DEPI privilege 15 algorithm-type scrypt secret 123 HQ-CORE-MLS2(config)#enable algorithm-type scrypt secret depi HQ-CORE-MLS2(config)#aaa new-model HQ-CORE-MLS2(config)#tacacs-server host 195.1.1.7 key DEPI HQ-CORE-MLS2(config)#aaa authentication login default group tacacs+ local HQ-CORE-MLS2(config)#aaa authorization exec default group tacacs+ local HQ-CORE-MLS2(config)#aaa accounting exec default start-stop group tacacs+ HQ-CORE-MLS2(config)#ip domain-name HQ-CORE-MLS2.depi HQ-CORE-MLS2(config)#crypto key generate rsa general-keys modulus 1024 HQ-CORE-MLS2(config)#line vty 0 2 HQ-CORE-MLS2(config)#line vty 0 2 HQ-CORE-MLS2(config-line)#login authentication default HQ-CORE-MLS2(config-line)#transport input ssh

HQ-DIS-MLS1

No	Description

1	Create Vlans
	Configuration
	HQ-CORE-MLS2(config)#ip routing HQ-DIS-MLS1(config)#vlan 10
	HQ-DIS-MLS1(config-vlan)#name HR
	HQ-DIS-MLS1(config)#vlan 15
	HQ-DIS-MLS1(config-vlan)#name CCTV
	HQ-DIS-MLS1(config)#vlan 20 HQ-DIS-MLS1(config-vlan)#name Server
	HQ-DIS-MLS1(config)#vlan 30
	HQ-DIS-MLS1(config-vlan)#name Management
	HQ-DIS-MLS1(config)#vlan 40
	HQ-DIS-MLS1(config-vlan)#name Voice
	HQ-DIS-MLS1(config)#vlan 50
	HQ-DIS-MLS1(config-vlan)#name Guest HQ-DIS-MLS1(config)#vlan 60
	HQ-DIS-MLS1(config-vlan)#name Retail Banking
	HQ-DIS-MLS1(config)#vlan 70
	HQ-DIS-MLS1(config-vlan)#name Credits_and_Loans
	HQ-DIS-MLS1(config)#vlan 80
	HQ-DIS-MLS1(config-vlan)#name Customer_Service HQ-DIS-MLS1(config)#vlan 90
	HQ-DIS-MLS1(config-vian)#name IT
	HQ-DIS-MLS1(config)#vlan 100
	HQ-DIS-MLS1(config-vlan)#name Digital_Banking
	HQ-DIS-MLS1(config)#vlan 99
	HQ-DIS-MLS1(config-vlan)#name Native
	HQ-DIS-MLS1(config)#vlan 200 HQ-DIS-MLS1(config-vlan)#name Manage
	TiQ-Di3-ML31(comig-vian)#flame Manage
2	Port-Aggregation (Etherchannel) & Trunking
	Configuration
	HQ-DIS-MLS1(config)#int range gig1/0/1,gig1/0/2
	HQ-DIS-MLS1(config-if-range)#channel-group 1 mode desirable
	HQ-DIS-MLS1(config-if-range)#switchport mode trunk
	HQ-DIS-MLS1(config-if-range)#switchport trunk native vlan 99
	HO DIS MI \$1/config)#int range gig1/0/2 gig1/0/4
	HQ-DIS-MLS1(config)#int range gig1/0/3,gig1/0/4 HQ-DIS-MLS1(config-if-range)#channel-group 2 mode desirable
	HQ-DIS-MLS1(config-if-range)#switchport mode trunk
	HQ-DIS-MLS1(config-if-range)#switchport trunk native vlan 99
	22

	HQ-DIS-MLS1(config)#int range gig1/0/5,gig1/0/6 HQ-DIS-MLS1(config-if-range)#channel-group 3 mode desirable HQ-DIS-MLS1(config-if-range)#switchport mode trunk HQ-DIS-MLS1(config-ifrange)#switchport trunk native vlan 99 HQ-DIS-MLS1(config)#int gig1/0/8 HQ-DIS-MLS1(config-if)#switchport mode trunk HQ-DIS-MLS1(config-if)#switchport trunk native vlan 99
3	VTP
	Configuration HQ-DIS-MLS1(config)#vtp version 2 HQ-DIS-MLS1(config)#vtp domain DEPI HQ-DIS-MLS1(config)#vtp password 123 HQ-DIS-MLS2(config)#vtp mode server
4	STP
	Configuration HQ-DIS-MLS1(config)#spanning-tree mode rapid-pvst HQ-DIS-MLS1(config)#spanning-tree vlan 1,10,15,20,30,40,50,60,70,80,90,99,100 ,999 root primar
5	Vlans IP Addresses & HSRB
	Configuration HQ-DIS-MLS1(config)#int vlan 10 HQ-DIS-MLS1(config-if)#ip add 192.168.10.2 255.255.255.224 HQ-DIS-MLS1(config-if)#ip helper-address 195.1.1.2 HQ-DIS-MLS1(config-if)#standby version 2 HQ-DIS-MLS1(config-if)#standby 1 ip 192.168.10.1 HQ-DIS-MLS1(config-if)#standby 1 priority 150 HQ-DIS-MLS1(config-if)#standby 1 preempt HQ-DIS-MLS1(config)#int vlan 15 HQ-DIS-MLS1(config-if)#ip add 192.168.150.2 255.255.255.224

```
HQ-DIS-MLS1(config)#int vlan 20
HQ-DIS-MLS1(config-if)#ip add 192.168.20.2 255.255.255.240
HQ-DIS-MLS1(config-if)#ip helper-address 195.1.1.2
HQ-DIS-MLS1(config-if)#standby version 2
HQ-DIS-MLS1(config-if)#standby 2 ip 192.168.20.1
HQ-DIS-MLS1(config-if)#standby 2 priority 150
HQ-DIS-MLS1(config-if)#standby 2 preempt
HQ-DIS-MLS1(config)#int vlan 30
HQ-DIS-MLS1(config-if)#ip add 192.168.30.2 255.255.255.224
HQ-DIS-MLS1(config-if)#ip helper-address 195.1.1.2
HQ-DIS-MLS1(config-if)#standby version 2
HQ-DIS-MLS1(config-if)#standby 3 ip 192.168.30.1
HQ-DIS-MLS1(config-if)#standby 3 priority 150
HQ-DIS-MLS1(config-if)#standby 3 preempt
HQ-DIS-MLS1(config)#int vlan 40
HQ-DIS-MLS1(config-if)#ip add 192.168.40.2 255.255.255.224
HQ-DIS-MLS1(config-if)#ip helper-address 195.1.1.2
HQ-DIS-MLS1(config-if)#standby version 2
HQ-DIS-MLS1(config-if)#standby 4 ip 192.168.30.1
HQ-DIS-MLS1(config-if)#standby 4 priority 150
HQ-DIS-MLS1(config-if)#standby 4 preempt
HQ-DIS-MLS1(config)#int vlan 50
HQ-DIS-MLS1(config-if)#ip add 192.168.50.2 255.255.255.0
HQ-DIS-MLS1(config-if)#ip helper-address 195.1.1.2
HQ-DIS-MLS1(config-if)#standby version 2
HQ-DIS-MLS1(config-if)#standby 5 ip 192.168.50.1
HQ-DIS-MLS1(config-if)#standby 5 priority 150
HQ-DIS-MLS1(config-if)#standby 5 preempt
HQ-DIS-MLS1(config)#int vlan 60
HQ-DIS-MLS1(config-if)#ip add 192.168.60.3 255.255.255.192
HQ-DIS-MLS1(config-if)#standby version 2
HQ-DIS-MLS1(config-if)#standby 6 ip
HQ-DIS-MLS1(config)#int vlan 70
HQ-DIS-MLS1(config-if)#ip add 192.168.70.3 255.255.255.224
HQ-DIS-MLS1(config-if)#standby version 2
HQ-DIS-MLS1(config-if)#standby 7 ip
HQ-DIS-MLS1(config)#int vlan 80
HQ-DIS-MLS1(config-if)#ip add 192.168.80.3 255.255.255.224
HQ-DIS-MLS1(config-if)#standby version 2
HQ-DIS-MLS1(config-if)#standby 8 ip
HQ-DIS-MLS1(config)#int vlan 90
```

	HQ-DIS-MLS1(config-if)#ip add 192.168.90.3 255.255.255.224 HQ-DIS-MLS1(config-if)#standby version 2 HQ-DIS-MLS1(config)#int vlan 100 HQ-DIS-MLS1(config-if)#ip add 192.168.100.3 255.255.255.224 HQ-DIS-MLS1(config-if)#standby version 2 HQ-DIS-MLS1(config-if)#standby 10 ip HQ-DIS-MLS1(config)#int vlan 200 HQ-DIS-MLS1(config-if)#ip add 192.168.200.2 255.255.255.224 HQ-DIS-MLS1(config-if)#standby version 2 HQ-DIS-MLS1(config-if)#standby version 2 HQ-DIS-MLS1(config-if)#standby 200 ip 192.168.200.1 HQ-DIS-MLS1(config-if)#standby 200 priority 150 HQ-DIS-MLS1(config-if)#standby 200 preempt
6	Interfaces IP Addresses
	Configuration HQ-DIS-MLS1(config)#ip routing HQ-DIS-MLS1(config)#int loopback 0 HQ-DIS-MLS1(config-if)#ip address 1.1.1.4 HQ-DIS-MLS1(config)#interface GigabitEthernet1/0/7 HQ-DIS-MLS1(config-if)#no switchport HQ-DIS-MLS1(config-if)#ip address 10.0.0.9 255.255.255.252 HQ-DIS-MLS1(config-if)#ip ospf authentication message-digest HQ-DIS-MLS1(config-if)#ip ospf message-digest-key 1 md5 DEPI HQ-DIS-MLS1(config)#interface GigabitEthernet1/0/9 HQ-DIS-MLS1(config-if)#no switchport HQ-DIS-MLS1(config-if)#ip address 10.0.0.21 255.255.255.252 HQ-DIS-MLS1(config-if)#ip ospf authentication message-digest HQ-DIS-MLS1(config-if)#ip ospf message-digest-key 1 md5 DEPI
7	OSPF Routing
	Configuration HQ-DIS-MLS1(config)#router ospf 1 HQ-DIS-MLS1(config-router)#router-id 1.1.1.3 HQ-DIS-MLS1(config-router)#area 0 authentication message-digest

	HQ-DIS-MLS1(config-router)#passive-interface default HQ-DIS-MLS1(config-router)#no passive-interface gigabitEthernet 1/0/7 HQ-DIS-MLS1(config-router)#no passive-interface gigabitEthernet 1/0/9 HQ-DIS-MLS1(config-router)#network 10.0.0.8 0.0.0.3 area 0 HQ-DIS-MLS1(config-router)#network 10.0.0.20 0.0.0.3 area 0 HQ-DIS-MLS1(config-router)#network 192.168.150.0 0.0.0.31 area 0 HQ-DIS-MLS1(config-router)#network 192.168.10.0 0.0.0.31 area 0 HQ-DIS-MLS1(config-router)#network 192.168.20.0 0.0.0.15 area 0 HQ-DIS-MLS1(config-router)#network 192.168.30.0 0.0.0.31 area 0 HQ-DIS-MLS1(config-router)#network 192.168.40.0 0.0.0.31 area 0 HQ-DIS-MLS1(config-router)#network 192.168.50.0 0.0.0.255 area 0 HQ-DIS-MLS1(config-router)#network 192.168.60.0 0.0.0.63 area 0 HQ-DIS-MLS1(config-router)#network 192.168.80.0 0.0.0.31 area 0 HQ-DIS-MLS1(config-router)#network 192.168.80.0 0.0.0.31 area 0 HQ-DIS-MLS1(config-router)#network 192.168.90.0 0.0.0.31 area 0 HQ-DIS-MLS1(config-router)#network 192.168.90.0 0.0.0.31 area 0 HQ-DIS-MLS1(config-router)#network 192.168.200.0 0.0.0.31 area 0
8	Default Route
	Configuration HQ-DIS-MLS1(config)#ip route 0.0.0.0 0.0.0.0 10.0.0.10 HQ-DIS-MLS1(config)#ip route 0.0.0.0 0.0.0.0 10.0.0.22 10
9	Disabled Interfaces
	Configuration HQ-DIS-MLS1(config)#int range g1/0/10-24,g1/1/1-4 HQ-DIS-MLS1(config-if-range)#shutdown HQ-DIS-MLS1(config-if-range)#switchport access vlan 999
10	NTP
	Configuration HQ-DIS-MLS1(config)#ntp authentication-key 123 md5 cisco HQ-DIS-MLS1(config)#ntp authenticate HQ-DIS-MLS1(config)#ntp trusted-key 123 HQ-DIS-MLS1(config)#ntp server 195.1.1.8

11	Sys-logs
	Configuration
	HQ-DIS-MLS1(config)#service timestamps log datetime msec HQ-DIS-MLS1(config)#logging 195.1.1.5
12	AAA
	Configuration
	HQ-DIS-MLS1(config)#username DEPI privilege 15 algorithm-type scrypt secret 123 HQ-DIS-MLS1(config)#enable algorithm-type scrypt secret depi
	HQ-DIS-MLS1(config)#aaa new-model HQ-DIS-MLS1(config)#tacacs-server host 195.1.1.7 key DEPI HQ-DIS-MLS1(config)#aaa authentication login default group tacacs+ local HQ-DIS-MLS1(config)#aaa authorization exec default group tacacs+ local HQ-DIS-MLS1(config)#aaa accounting exec default start-stop group tacacs+
	HQ-DIS-MLS1(config)#ip domain-name HQ-DIS-MLS1.depi HQ-DIS-MLS1(config)#crypto key generate rsa general-keys modulus 1024 HQ-DIS-MLS1(config)#ip ssh version 2
	HQ-DIS-MLS1(config)#line vty 0 2 HQ-DIS-MLS1(config-line)#login authentication default HQ-DIS-MLS1(config-line)#transport input ssh

HQ-DIS-MLS2

No	Description
1	Port-Aggregation (Etherchannel) & Trunking
	Configuration

IQ-DIS-MLS2(config)#int range gig1/0/1,gig1/0/2
IQ-DIS-MLS2(config-if-range)#channel-group 1 mode desirable
IQ-DIS-MLS2(config-if-range)#switchport mode trunk
IQ-DIS-MLS2(config-if-range)#switchport trunk native vlan 99
10 DIS MI S2/ (5:) III at a see site 4/0/2 site 4/0/4
IQ-DIS-MLS2(config)#int range gig1/0/3,gig1/0/4
IQ-DIS-MLS2(config-if-range)#channel-group 2 mode desirable
IQ-DIS-MLS2(config-if-range)#switchport mode trunk
IQ-DIS-MLS2(config-if-range)#switchport trunk native vlan 99
IQ-DIS-MLS2(config)#int range gig1/0/5,gig1/0/6
IQ-DIS-MLS2(config-if-range)#channel-group 3 mode desirable
IQ-DIS-MLS2(config-if-range)#switchport mode trunk
IQ-DIS-MLS2(config-if-range)#switchport trunk native vlan 99
IQ-DIS-MLS2(config)#interface GigabitEthernet1/0/8
IQ-DIS-MLS2(config-if)#switchport mode trunk
IQ-DIS-MLS2(config-if)#switchport trunk native vlan 99
VTP
Configuration
HQ-DIS-MLS2(config)#vtp version 2
HQ-DIS-MLS2(config)#vtp domain DEPI
HQ-DIS-MLS2(config)#vtp password 123
HQ-DIS-MLS2(config)#vtp mode client
CTD
STP
Configuration
Joinigulation
IQ-DIS-MLS2(config)#spanning-tree mode rapid-pvst
IQ-DIS-MLS2(config)#spanning-tree vlan 1,10,15,20,30,40,50,60,70,80,90,99,100
999 root secondary
•
Vians IP Addresses & HSRB
Configuration
HQ-DIS-MLS2(config)#int vlan 10

HQ-DIS-MLS2(config-if)#standby 1 ip HQ-DIS-MLS2(config)#int vlan 15 HQ-DIS-MLS2(config-if)#ip add 192.168.150.3 255.255.255.224 HQ-DIS-MLS2(config-if)#ip helper-address 195.1.1.2 HQ-DIS-MLS2(config-if)#standby version 2 HQ-DIS-MLS2(config-if)#standby 15 ip 192.168.60.1 HQ-DIS-MLS2(config-if)#standby 15 priority 150 HQ-DIS-MLS2(config-if)#standby 15 preempt HQ-DIS-MLS2(config)#int vlan 20 HQ-DIS-MLS2(config-if)#ip add 192.168.20.3 255.255.255.240 HQ-DIS-MLS2(config-if)#standby version 2 HQ-DIS-MLS2(config-if)#standby 2 ip HQ-DIS-MLS2(config)#int vlan 30 HQ-DIS-MLS2(config-if)#ip add 192.168.30.3 255.255.255.224 HQ-DIS-MLS2(config-if)#standby version 2 HQ-DIS-MLS2(config-if)#standby 3 ip HQ-DIS-MLS2(config)#int vlan 40 HQ-DIS-MLS2(config-if)#ip add 192.168.40.3 255.255.255.224 HQ-DIS-MLS2(config-if)#standby version 2 HQ-DIS-MLS2(config-if)#standby 4 ip HQ-DIS-MLS2(config)#int vlan 50 HQ-DIS-MLS2(config-if)#ip add 192.168.50.3 255.255.255.0 HQ-DIS-MLS2(config-if)#standby version 2 HQ-DIS-MLS2(config-if)#standby 5 ip HQ-DIS-MLS2(config)#int vlan 60 HQ-DIS-MLS2(config-if)#ip add 192.168.60.3 255.255.255.192 HQ-DIS-MLS2(config-if)#standby version 2 HQ-DIS-MLS2(config-if)#standby 6 ip 192.168.60.1 HQ-DIS-MLS2(config-if)#standby 6 priority 150 HQ-DIS-MLS2(config-if)#standby 6 preempt HQ-DIS-MLS2(config)#int vlan 70 HQ-DIS-MLS2(config-if)#ip add 192.168.70.3 255.255.255.224 HQ-DIS-MLS2(config-if)#ip helper-address 195.1.1.2 HQ-DIS-MLS2(config-if)#standby version 2 HQ-DIS-MLS2(config-if)#standby 7 ip 192.168.70.1 HQ-DIS-MLS2(config-if)#standby 7 priority 150 HQ-DIS-MLS2(config-if)#standby 7 preempt

	HQ-DIS-MLS2(config)#int vlan 80 HQ-DIS-MLS2(config-if)#ip add 192.168.80.3 255.255.255.224 HQ-DIS-MLS2(config-if)#ip helper-address 195.1.1.2 HQ-DIS-MLS2(config-if)#standby version 2 HQ-DIS-MLS2(config-if)#standby 8 ip 192.168.80.1 HQ-DIS-MLS2(config-if)#standby 8 priority 150 HQ-DIS-MLS2(config-if)#standby 8 preempt HQ-DIS-MLS2(config-if)#ip add 192.168.90.3 255.255.255.224 HQ-DIS-MLS2(config-if)#ip helper-address 195.1.1.2 HQ-DIS-MLS2(config-if)#standby version 2 HQ-DIS-MLS2(config-if)#standby 9 priority 150 HQ-DIS-MLS2(config-if)#standby 9 priority 150 HQ-DIS-MLS2(config-if)#standby 9 preempt HQ-DIS-MLS2(config-if)#standby 9 preempt HQ-DIS-MLS2(config-if)#ip add 192.168.100.3 255.255.255.224 HQ-DIS-MLS2(config-if)#ip helper-address 195.1.1.2 HQ-DIS-MLS2(config-if)#ip helper-address 195.1.1.2 HQ-DIS-MLS2(config-if)#standby version 2 HQ-DIS-MLS2(config-if)#standby 10 ip 192.168.100.1 HQ-DIS-MLS2(config-if)#standby 10 priority 150 HQ-DIS-MLS2(config-if)#standby 10 priority 150 HQ-DIS-MLS2(config-if)#standby 10 preempt HQ-DIS-MLS2(config-if)#standby 10 preempt HQ-DIS-MLS2(config-if)#standby 10 preempt HQ-DIS-MLS2(config-if)#standby version 2
5	Interfaces IP Addresses
	Configuration
	HQ-DIS-MLS2(config)#ip routing
	HQ-DIS-MLS2(config)#int loopback 0 HQ-DIS-MLS2(config-if)#ip address 1.1.1.4 255.255.255
	HQ-DIS-MLS2(config)#interface GigabitEthernet1/0/7 HQ-DIS-MLS2(config-if)#no switchport HQ-DIS-MLS2(config-if)#ip address 10.0.0.13 255.255.255.252 HQ-DIS-MLS2(config-if)#ip ospf authentication message-digest HQ-DIS-MLS2(config-if)#ip ospf message-digest-key 1 md5 DEPI

	HQ-DIS-MLS2(config)#interface GigabitEthernet1/0/9 HQ-DIS-MLS2(config-if)#no switchport HQ-DIS-MLS2(config-if)#ip address 10.0.0.17 255.255.255.252 HQ-DIS-MLS2(config-if)#ip ospf authentication message-digest HQ-DIS-MLS2(config-if)#ip ospf message-digest-key 1 md5 DEPI
6	OSPF Routing
	Configuration HQ-DIS-MLS2(config)#router ospf 1 HQ-DIS-MLS2(config-router)#router-id 1.1.1.4 HQ-DIS-MLS2(config-router)#area 0 authentication message-digest HQ-DIS-MLS2(config-router)#passive-interface default HQ-DIS-MLS2(config-router)#no passive-interface gigabitEthernet 1/0/7 HQ-DIS-MLS2(config-router)#no passive-interface gigabitEthernet 1/0/9 HQ-DIS-MLS2(config-router)#network 10.0.0.12 0.0.0.3 area 0 HQ-DIS-MLS2(config-router)#network 10.0.0.16 0.0.0.3 area 0 HQ-DIS-MLS2(config-router)#network 192.168.150.0 0.0.0.31 area 0 HQ-DIS-MLS2(config-router)#network 192.168.150.0 0.0.0.31 area 0 HQ-DIS-MLS2(config-router)#network 192.168.20.0 0.0.0.15 area 0 HQ-DIS-MLS2(config-router)#network 192.168.30.0 0.0.0.31 area 0 HQ-DIS-MLS2(config-router)#network 192.168.30.0 0.0.0.31 area 0 HQ-DIS-MLS2(config-router)#network 192.168.50.0 0.0.0.255 area 0 HQ-DIS-MLS2(config-router)#network 192.168.50.0 0.0.0.31 area 0 HQ-DIS-MLS2(config-router)#network 192.168.70.0 0.0.0.31 area 0 HQ-DIS-MLS2(config-router)#network 192.168.80.0 0.0.0.31 area 0 HQ-DIS-MLS2(config-router)#network 192.168.200.0 0.0.0.31 area 0
7	Default Route
	Configuration HQ-DIS-MLS2(config)#ip route 0.0.0.0 0.0.0.0 10.0.0.14 1 HQ-DIS-MLS2(config)#ip route 0.0.0.0 0.0.0.0 10.0.0.18 10
8	Disabled Interfaces

	Configuration HQ-DIS-MLS2(config)#int range g1/0/10-24,g1/1/1-4 HQ-DIS-MLS2(config-if-range)#shutdown HQ-DIS-MLS2(config-if-range)#switchport access vlan 999
9	NTP
	Configuration
	HQ-DIS-MLS2(config)#ntp authentication-key 123 md5 cisco HQ-DIS-MLS2(config)#ntp authenticate HQ-DIS-MLS2(config)#ntp trusted-key 123 HQ-DIS-MLS2(config)#ntp server 195.1.1.8
10	Sys-logs
	Configuration
	HQ-DIS-MLS2(config)#service timestamps log datetime msec HQ-DIS-MLS2(config)#logging 195.1.1.5
11	AAA
	Configuration
	HQ-DIS-MLS2(config)#username DEPI privilege 15 algorithm-type scrypt secret 123 HQ-DIS-MLS2(config)#enable algorithm-type scrypt secret depi
	HQ-DIS-MLS2(config)#aaa new-model HQ-DIS-MLS2(config)#tacacs-server host 195.1.1.7 key DEPI HQ-DIS-MLS2(config)#aaa authentication login default group tacacs+ local HQ-DIS-MLS2(config)#aaa authorization exec default group tacacs+ local HQ-DIS-MLS2(config)#aaa accounting exec default start-stop group tacacs+
	HQ-DIS-MLS2(config)#ip domain-name HQ-DIS-MLS2.depi HQ-DIS-MLS2(config)#crypto key generate rsa general-keys modulus 1024 HQ-DIS-MLS2(config)#ip ssh version 2
	HQ-DIS-MLS2(config)#line vty 0 2 HQ-DIS-MLS2(config-line)#login authentication default

HQ-ACC-SW1

No	Description
1	Port-Aggregation (Etherchannel) & Trunking
	Configuration HQ-ACC-SW1(config)#int range gig0/1,gig1/1 HQ-ACC-SW1(config-if-range)#channel-group 1 mode desirable HQ-ACC-SW1(config-if-range)#switchport mode trunk HQ-ACC-SW1(config-if-range)#switchport trunk native vlan 99 HQ-ACC-SW1(config-if-range)#ip dhcp snooping trust HQ-ACC-SW1(config)#int range gig2/1,gig3/1 HQ-ACC-SW1(config-if-range)#channel-group 2 mode desirable HQ-ACC-SW1(config-if-range)#switchport mode trunk HQ-ACC-SW1(config-if-range)#switchport trunk native vlan 99 HQ-ACC-SW1(config-if-range)#ip dhcp snooping trust HQ-ACC-SW1(config)#int gig4/1 HQ-ACC-SW1(config-if)#switchport trunk native vlan 99 HQ-ACC-SW1(config-if-range)#ip dhcp snooping trust HQ-ACC-SW1(config)#int gig6/1
	HQ-ACC-SW1(config)#int gig6/1 HQ-ACC-SW1(config-if)#switchport mode trunk HQ-ACC-SW1(config-if)#switchport trunk native vlan 99 HQ-ACC-SW1(config-if)#switchport trunk allowed vlan 15,200 HQ-ACC-SW1(config-if-range)#ip dhcp snooping trust
2	VTP
	Configuration
	HQ-ACC-SW1(config)#vtp version 2

	HQ-ACC-SW1(config)#vtp domain DEPI HQ-ACC-SW1(config)#vtp password 123 HQ-ACC-SW1(config)#vtp mode client
3	STP
	Configuration
	HQ-ACC-SW1(config)#spanning-tree mode rapid-pvst
4	Interfaces IP Addresses & Default Gateway
	Configuration HQ-ACC-SW1(config)#ip default-gateway 192.168.200.1 HQ-ACC-SW1(config-if)#int vlan 200 HQ-ACC-SW1(config-if)#ip address 192.168.200.4 255.255.255.224
5	Disabled Interfaces
	Configuration
	HQ-ACC-SW1(config)#int range g7/1,g8/1,g9/1 HQ-ACC-SW1(config-if-range)#shutdown HQ-ACC-SW1(config-if-range)#switchport access vlan 999
6	HQ-ACC-SW1(config)#int range g7/1,g8/1,g9/1 HQ-ACC-SW1(config-if-range)#shutdown
6	HQ-ACC-SW1(config)#int range g7/1,g8/1,g9/1 HQ-ACC-SW1(config-if-range)#shutdown HQ-ACC-SW1(config-if-range)#switchport access vlan 999

7	Sys-logs
	Configuration HQ-ACC-SW1(config)#service timestamps log datetime msec
	HQ-ACC-SW1(config)#logging 195.1.1.5
8	Access Interfaces
	Configuration HQ-ACC-SW1(config)#interface GigabitEthernet5/1 HQ-ACC-SW1(config-if)#switchport Access Vlan 50
9	DHCP Snooping & Dynamic Arp Inspection
	Configuration
	HQ-ACC-SW1(config)#ip dhcp snooping HQ-ACC-SW1(config)#ip dhcp snooping vlan 10,15,20,30,40,50,60,70,80,90,100
10	Disable CDP
	Configuration
	HQ-ACC-SW1(config)#int g5/1 HQ-ACC-SW1(config-if)#no cdp enable
11	AAA
	Configuration
	HQ-ACC-SW1(config)#enable secret level 15 depi HQ-ACC-SW1(config)#username DEPI privilege 15 secret 123
	HQ-ACC-SW1(config)#aaa new-model HQ-ACC-SW1(config)#tacacs-server host 195.1.1.7 key DEPI HQ-ACC-SW1(config)#aaa authentication login default group tacacs+ local HQ-ACC-SW1(config)#aaa authorization exec default group tacacs+ local

HQ-ACC-SW1(config)#aaa accounting exec default start-stop group tacacs+

HQ-ACC-SW1(config)#ip domain-name HQ-ACC-SW1.depi
HQ-ACC-SW1(config)#crypto key generate rsa general-keys modulus 1024
HQ-ACC-SW1(config)#ip ssh version 2

HQ-ACC-SW1(config)#line vty 0 2
HQ-ACC-SW1(config-line)#login authentication default
HQ-ACC-SW1(config-line)#transport input ssh

HQ-ACC-SW2

No	Description
1	Port-Aggregation (Etherchannel) & Trunking
	Configuration
	HQ-ACC-SW2(config)#int range gig0/1,gig1/1 HQ-ACC-SW2(config-if-range)#channel-group 1 mode desirable HQ-ACC-SW2(config-if-range)#switchport mode trunk

4	Interfaces IP Addresses & Default Gateway
	HQ-ACC-SW2(config)#spanning-tree mode rapid-pvst
	Configuration
3	STP
	Configuration HQ-ACC-SW2(config)#vtp version 2 HQ-ACC-SW2(config)#vtp domain DEPI HQ-ACC-SW2(config)#vtp password 123 HQ-ACC-SW2(config)#vtp mode client
2	VTP
	HQ-ACC-SW2(config-if-range)#ip dhcp snooping trust HQ-ACC-SW2(config)#int range gig2/1,gig3/1 HQ-ACC-SW2(config-if-range)#channel-group 2 mode desirable HQ-ACC-SW2(config-if-range)#switchport mode trunk HQ-ACC-SW2(config-if-range)#switchport trunk native vlan 99 HQ-ACC-SW2(config-if-range)#ip dhcp snooping trust HQ-ACC-SW2(config)#int gig4/1 HQ-ACC-SW2(config-if)#switchport mode trunk HQ-ACC-SW2(config-if)#switchport trunk native vlan 99 HQ-ACC-SW2(config-if-range)#ip dhcp snooping trust HQ-ACC-SW2(config-if)#switchport mode trunk HQ-ACC-SW2(config-if)#switchport mode trunk HQ-ACC-SW2(config-if)#switchport trunk native vlan 99 HQ-ACC-SW2(config-if)#switchport trunk native vlan 99 HQ-ACC-SW2(config-if)#switchport trunk allowed vlan 15,200 HQ-ACC-SW2(config-if-range)#ip dhcp snooping trust

5	Disabled Interfaces
	Configuration HQ-ACC-SW2(config)#int range g7/1,g8/1,g9/1
	HQ-ACC-SW2(config-if-range)#shutdown HQ-ACC-SW2(config-if-range)#switchport access vlan 999
6	NTP
	Configuration HQ-ACC-SW2(config)#ntp authentication-key 123 md5 cisco HQ-ACC-SW2(config)#ntp authenticate HQ-ACC-SW2(config)#ntp trusted-key 123 HQ-ACC-SW2(config)#ntp server 195.1.1.8
7	Sys-logs
	Configuration HQ-ACC-SW2(config)#service timestamps log datetime msec HQ-ACC-SW2(config)#logging 195.1.1.5
8	Access Interfaces
	Configuration
	HQ-ACC-SW2(config)#interface GigabitEthernet5/1 HQ-ACC-SW2(config-if)#SWitchport Access Vlan 50
9	DHCP Snooping & Dynamic Arp Inspection
	Configuration
	HQ-ACC-SW2(config)#ip dhcp snooping

	HQ-ACC-SW2(config)#ip dhcp snooping vlan 10,15,20,30,40,50,60,70,80,90,100
10	Disable CDP
	Configuration
	HQ-ACC-SW2(config)#int g5/1
	HQ-ACC-SW2(config-if)#no cdp enable
11	AAA
	Configuration
	HQ-ACC-SW2(config)#enable secret level 15 depi HQ-ACC-SW2(config)#username DEPI privilege 15 secret 123
	HQ-ACC-SW2(config)#aaa new-model HQ-ACC-SW2(config)#tacacs-server host 195.1.1.7 key DEPI
	HQ-ACC-SW2(config)#aaa authentication login default group tacacs+ local
	HQ-ACC-SW2(config)#aaa authorization exec default group tacacs+ local
	HQ-ACC-SW2(config)#aaa accounting exec default start-stop group tacacs+
	HQ-ACC-SW2(config)#ip domain-name HQ-ACC-SW2.depi
	HQ-ACC-SW2(config)#crypto key generate rsa general-keys modulus 1024
	HQ-ACC-SW2(config)#ip ssh version 2
	HQ-ACC-SW2(config)#line vty 0 2
	HQ-ACC-SW2(config-line)#login authentication default
	HQ-ACC-SW2(config-line)#transport input ssh

No	Description
1	Port-Aggregation (Etherchannel) & Trunking
	Configuration

1	IQ-ACC-SW3(config)#int range gig0/1,gig1/1
H	IQ-ACC-SW3(config-if-range)#channel-group 1 mode desirable
	IQ-ACC-SW3(config-if-range)#switchport mode trunk
	IQ-ACC-SW3(config-if-range)#switchport trunk native vlan 99
H	IQ-ACC-SW3(config-if-range)#ip dhcp snooping trust
Н	IQ-ACC-SW3(config)#int range gig2/1,gig3/1
Н	IQ-ACC-SW3(config-if-range)#channel-group 2 mode desirable
Н	IQ-ACC-SW3(config-if-range)#switchport mode trunk
-i	if-range)#switchport trunk native vlan 99 HQ-ACC-SW3(config
Н	IQ-ACC-SW3(config-if-range)#ip dhcp snooping trust
Н	IQ-ACC-SW3(config)#int gig4/1
Н	IQ-ACC-SW3(config-if)#switchport mode trunk
Н	IQ-ACC-SW3(config-if)#switchport trunk native vlan 99
	IQ-ACC-SW3(config-if-range)#ip dhcp snooping trust
H	IQ-ACC-SW3(config)#int gig6/1
	IQ-ACC-SW3(config-if)#switchport mode trunk
	IQ-ACC-SW3(config-if)#switchport trunk native vlan 99
	IQ-ACC-SW3(config-if)#switchport trunk allowed vlan 15,200
	IQ-ACC-SW3(config-if-range)#ip dhcp snooping trust
2	VTP
C	Configuration
Н	IQ-ACC-SW3(config)#vtp version 2
	IQ-ACC-SW3(config)#vtp domain DEPI
	IQ-ACC-SW3(config)#vtp password 123
H	IQ-ACC-SW3(config)#vtp mode client
3	et D
3	STP
C	Configuration
	203
Н	IQ-ACC-SW3(config)#spanning-tree mode rapid-pvst
4	Interfaces ID Addresses & Default Category
-	Interfaces IP Addresses & Default Gateway
1	

	HQ-ACC-SW3(config)#ip default-gateway 192.168.200.1 HQ-ACC-SW3(config-if)#int vlan 200 HQ-ACC-SW3(config-if)#ip address 192.168.200.8 255.255.255.224
5	Disabled Interfaces
	Configuration HQ-ACC-SW3(config)#int range g7/1,g8/1,g9/1 HQ-ACC-SW3(config-if-range)#shutdown HQ-ACC-SW3(config-if-range)#switchport access vlan 999
6	NTP
	Configuration HQ-ACC-SW3(config)#ntp authentication-key 123 md5 cisco HQ-ACC-SW3(config)#ntp authenticate HQ-ACC-SW3(config)#ntp trusted-key 123 HQ-ACC-SW3(config)#ntp server 195.1.1.8
7	Sys-logs Sys-logs
	Configuration HQ-ACC-SW3(config)#service timestamps log datetime msec HQ-ACC-SW3(config)#logging 195.1.1.
8	Access Interfaces
	Configuration HQ-ACC-SW3(config)#interface GigabitEthernet5/1 HQ-ACC-SW3(config-if)#SWitchport Access Vlan 50
9	DHCP Snooping & Dynamic Arp Inspection
	41

	Configuration
	HQ-ACC-SW3(config)#ip dhcp snooping HQ-ACC-SW3(config)#ip dhcp snooping vlan 10,15,20,30,40,50,60,70,80,90,100
10	Disable CDP
	Configuration
	HQ-ACC-SW3(config)#int g5/1 HQ-ACC-SW3(config-if)#no cdp enable
11	AAA
	Configuration
	HQ-ACC-SW3(config)#enable secret level 15 depi HQ-ACC-SW3(config)#username DEPI privilege 15 secret 123
	HQ-ACC-SW3(config)#aaa new-model HQ-ACC-SW3(config)#tacacs-server host 195.1.1.7 key DEPI
	HQ-ACC-SW3(config)#aaa authentication login default group tacacs+ local
	HQ-ACC-SW3(config)#aaa authorization exec default group tacacs+ local HQ-ACC-SW3(config)#aaa accounting exec default start-stop group tacacs+
	HQ-ACC-SW3(config)#ip domain-name HQ-ACC-SW3.depi
	HQ-ACC-SW3(config)#crypto key generate rsa general-keys modulus 1024 HQ-ACC-SW3(config)#ip ssh version 2
	HQ-ACC-SW3(config)#line vty 0 2
	HQ-ACC-SW3(config-line)#login authentication default HQ-ACC-SW3(config-line)#transport input ssh

No	Description
1	Port-Aggregation (Etherchannel) & Trunking

	Configuration
	HQ-ACC-SW4(config)#int gig0/1 HQ-ACC-SW4(config-if)#switchport mode trunk HQ-ACC-SW4(config-if)#switchport trunk native vlan 99 HQ-ACC-SW4(config-if-range)#ip dhcp snooping trust
2	VTP
	Configuration
	H HQ-ACC-SW4(config)#vtp version 2 HQ-ACC-SW4(config)#vtp domain DEPI HQ-ACC-SW4(config)#vtp password 123 HQ-ACC-SW4(config)#vtp mode client
3	STP & Portfast
	Configuration
	HQ-ACC-SW4(config)#spanning-tree mode rapid-pvst HQ-ACC-SW4(config)#spanning-tree portfast default HQ-ACC-SW4(config)#spanning-tree portfast bpduguard default
4	Port Security & Assign Vlan & Voice Vlan
	Configuration
	HQ-ACC-SW4(config)#int range fastEthernet 0/1-6 HQ-ACC-SW4(config-if-range)#switchport mode access HQ-ACC-SW4(config-if-range)#switchport access vlan 10 HQ-ACC-SW4(config-if-range)#switchport voice vlan 40 HQ-ACC-SW4(config-if-range)#ip dhcp snooping limit rate 10 HQ-ACC-SW4(config-if-range)#switchport port-security HQ-ACC-SW4(config-if-range)#switchport port-security maximum 2 HQ-ACC-SW4(config-if-range)#switchport port-security mac-address sticky HQ-ACC-SW4(config-if-range)#switchport port-security violation restrict HQ-ACC-SW4(config)#int range fastEthernet 0/7-11
	HQ-ACC-SW4(config-if-range)#switchport mode access HQ-ACC-SW4(config-if-range)#switchport access vlan 20 43

	HQ-ACC-SW4(config-if-range)#ip dhcp snooping limit rate 10 HQ-ACC-SW4(config-if-range)#switchport port-security HQ-ACC-SW4(config-if-range)#switchport port-security maximum 1 HQ-ACC-SW4(config-if-range)#switchport port-security mac-address sticky HQ-ACC-SW4(config-if-range)#switchport port-security violation restrict
5	Disabled Interfaces
	Configuration HQ-ACC-SW4(config)#int range f0/12-24,g0/2 HQ-ACC-SW4(config-if-range)#shutdown HQ-ACC-SW4(config-if-range)#switchport access vlan 999
6	Interfaces IP Addresses & Default Gateway
	Configuration
	HQ-ACC-SW4(config)#ip default-gateway 192.168.200.1 HQ-ACC-SW4(config-if)#int vlan 200 HQ-ACC-SW4(config-if)#ip address 192.168.200.5 255.255.254
7	NTP
	Configuration HQ-ACC-SW4(config)#ntp authentication-key 123 md5 cisco HQ-ACC-SW4(config)#ntp authenticate HQ-ACC-SW4(config)#ntp trusted-key 123 HQ-ACC-SW4(config)#ntp server 195.1.1.8
8	Sys-logs
	Configuration
	HQ-ACC-SW4(config)#service timestamps log datetime msec HQ-ACC-SW4(config)#logging 195.1.1.5
	ΔΔ

9	DHCP Snooping & Dynamic Arp Inspection
	Configuration
	HQ-ACC-SW4(config)#ip dhcp snooping HQ-ACC-SW4(config)#ip dhcp snooping vlan 10,15,20,30,40,50,60,70,80,90,100 HQ-ACC-SW4(config)#ip arp inspection vlan 10,15,20,30,40,50,60,70,80,90,100
10	Disable CDP
	Configuration
	HQ-ACC-SW4(config)#no cdp run HQ-ACC-SW4(config)#int g0/1 HQ-ACC-SW4(config-if)#cdp enable
11	AAA
	Configuration
	HQ-ACC-SW4(config)#enable secret level 15 depi HQ-ACC-SW4(config)#username DEPI privilege 15 secret 123
	HQ-ACC-SW4(config)#aaa new-model HQ-ACC-SW4(config)#tacacs-server host 195.1.1.7 key DEPI HQ-ACC-SW4(config)#aaa authentication login default group tacacs+ local HQ-ACC-SW4(config)#aaa authorization exec default group tacacs+ local HQ-ACC-SW4(config)#aaa accounting exec default start-stop group tacacs+
	HQ-ACC-SW4(config)#ip domain-name HQ-ACC-SW4.depi HQ-ACC-SW4(config)#crypto key generate rsa general-keys modulus 1024 HQ-ACC-SW4(config)#ip ssh version 2
	HQ-ACC-SW4(config)#line vty 0 2 HQ-ACC-SW4(config-line)#login authentication default HQ-ACC-SW4(config-line)#transport input ssh

No	Description
1	Trunking
	Configuration
	HQ-ACC-SW5(config)#int gig0/1 HQ-ACC-SW5(config-if)#switchport mode trunk HQ-ACC-SW5(config-if)#switchport trunk native vlan 99 HQ-ACC-SW5(config-if-range)#ip dhcp snooping trust
2	VTP
	Configuration
	HQ-ACC-SW5(config)#vtp version 2 HQ-ACC-SW5(config)#vtp domain DEPI HQ-ACC-SW5(config)#vtp password 123 HQ-ACC-SW5(config)#vtp mode client
3	STP & Portfast
	Configuration
	HQ-ACC-SW5(config)#spanning-tree mode rapid-pvst HQ-ACC-SW5(config)#spanning-tree portfast default HQ-ACC-SW5(config)#spanning-tree portfast bpduguard default
4	Port Security & Assign Vlan & Voice Vlan
	Configuration
	HQ-ACC-SW5(config)#int range fastEthernet 0/1-6 HQ-ACC-SW5(config-if-range)#switchport mode access HQ-ACC-SW5(config-if-range)#switchport access vlan 80 HQ-ACC-SW5(config-if-range)#switchport voice vlan 40 HQ-ACC-SW5(config-if-range)#ip dhcp snooping limit rate 10 HQ-ACC-SW5(config-if-range)#switchport port-security HQ-ACC-SW5(config-if-range)#switchport port-security maximum 2 HQ-ACC-SW5(config-if-range)#switchport port-security mac-address sticky

	HQ-ACC-SW5(config-if-range)#switchport port-security violation restrict
	HQ-ACC-SW5(config)#int range fastEthernet 0/7-12 HQ-ACC-SW5(config-if-range)#switchport mode access HQ-ACC-SW5(config-if-range)#switchport access vlan 70 HQ-ACC-SW5(config-if-range)#switchport voice vlan 40 HQ-ACC-SW5(config-if-range)#ip dhcp snooping limit rate 10 HQ-ACC-SW5(config-if-range)#switchport port-security HQ-ACC-SW5(config-if-range)#switchport port-security maximum 2 HQ-ACC-SW5(config-if-range)#switchport port-security mac-address sticky HQ-ACC-SW5(config-if-range)#switchport port-security violation restrict
	HQ-ACC-SW5(config)#int range fastEthernet 0/13-18 HQ-ACC-SW5(config-if-range)#switchport mode access HQ-ACC-SW5(config-if-range)#switchport access vlan 60 HQ-ACC-SW5(config-if-range)#switchport voice vlan 40 HQ-ACC-SW5(config-if-range)#ip dhcp snooping limit rate 10 HQ-ACC-SW5(config-if-range)#switchport port-security HQ-ACC-SW5(config-if-range)#switchport port-security maximum 2 HQ-ACC-SW5(config-if-range)#switchport port-security mac-address sticky HQ-ACC-SW5(config-if-range)#switchport port-security violation restrict HQ-ACC-SW5(config)#int fa0/6,fa0/12,fa0/18 HQ-ACC-SW5(config-if-range)#switchport port-security maximum 1
5	Disabled Interfaces
	Configuration
	HQ-ACC-SW5(config)#int range f0/19-24,g0/2 HQ-ACC-SW5(config-if-range)#shutdown HQ-ACC-SW5(config-if-range)#switchport access vlan 999
6	Interfaces IP Addresses & Default Gateway
	Configuration
	HQ-ACC-SW5(config)#ip default-gateway 192.168.200.1

	HQ-ACC-SW5(config-if)#int vlan 200 HQ-ACC-SW5(config-if)#ip address 192.168.200.7 255.255.254
7	NTP
	Configuration HQ-ACC-SW5(config)#ntp authentication-key 123 md5 cisco HQ-ACC-SW5(config)#ntp authenticate HQ-ACC-SW5(config)#ntp trusted-key 123 HQ-ACC-SW5(config)#ntp server 195.1.1.8
8	Sys-logs
	Configuration HQ-ACC-SW5(config)#service timestamps log datetime msec HQ-ACC-SW5(config)#logging 195.1.1.5
9	DHCP Snooping & Dynamic Arp Inspection
	Configuration HQ-ACC-SW5(config)#ip dhcp snooping HQ-ACC-SW5(config)#ip dhcp snooping vlan 10,15,20,30,40,50,60,70,80,90,100 HQ-ACC-SW5(config)#ip arp inspection vlan 10,15,20,30,40,50,60,70,80,90,100
10	Disable CDP
	Configuration HQ-ACC-SW5(config)#no cdp run HQ-ACC-SW5(config)#int g0/1 HQ-ACC-SW5(config-if)#cdp enable
11	

AAA
Configuration
HQ-ACC-SW5(config)#enable secret level 15 depi
HQ-ACC-SW5(config)#username DEPI privilege 15 secret 123
HQ-ACC-SW5(config)#aaa new-model
HQ-ACC-SW5(config)#tacacs-server host 195.1.1.7 key DEPI
HQ-ACC-SW5(config)#aaa authentication login default group tacacs+ local
HQ-ACC-SW5(config)#aaa authorization exec default group tacacs+ local
HQ-ACC-SW5(config)#aaa accounting exec default start-stop group tacacs+
HQ-ACC-SW5(config)#ip domain-name HQ-ACC-SW5.depi
HQ-ACC-SW5(config)#crypto key generate rsa general-keys modulus 1024
HQ-ACC-SW5(config)#ip ssh version 2
HQ-ACC-SW5(config)#line vty 0 2
HQ-ACC-SW5(config-line)#login authentication default
HQ-ACC-SW5(config-line)#transport input ssh

No	Description
1	Trunking
	Configuration HQ-ACC-SW6(config)#int gig0/1 HQ-ACC-SW6(config-if)#switchport mode trunk HQ-ACC-SW6(config-if)#switchport trunk native vlan 99 HQ-ACC-SW6(config-if)#ip dhcp snooping trust
2	VTP

	Configuration
	HQ-ACC-SW6(config)#vtp version 2 HQ-ACC-SW6(config)#vtp domain DEPI HQ-ACC-SW6(config)#vtp password 123 HQ-ACC-SW6(config)#vtp mode client
3	STP & Portfast
	Configuration
	HQ-ACC-SW6(config)#spanning-tree mode rapid-pvst HQ-ACC-SW6(config)#spanning-tree portfast default HQ-ACC-SW6(config)#spanning-tree portfast bpduguard default
4	Port Security
	Configuration
	HQ-ACC-SW6(config)#int range fastEthernet 0/1-5 HQ-ACC-SW6(config-if-range)#switchport mode access HQ-ACC-SW6(config-if-range)#switchport access vlan 30 HQ-ACC-SW6(config-if-range)#switchport voice vlan 40 HQ-ACC-SW6(config-if-range)#ip dhcp snooping limit rate 10 HQ-ACC-SW6(config-if-range)#switchport port-security HQ-ACC-SW6(config-if-range)#switchport port-security maximum 2 HQ-ACC-SW6(config-if-range)#switchport port-security mac-address sticky HQ-ACC-SW6(config-if-range)#switchport port-security violation restrict
	HQ-ACC-SW6(config)#int range fastEthernet 0/6-10 HQ-ACC-SW6(config-if-range)#switchport mode access HQ-ACC-SW6(config-if-range)#switchport access vlan 30 HQ-ACC-SW6(config-if-range)#switchport voice vlan 40 HQ-ACC-SW6(config-if-range)#ip dhcp snooping limit rate 10 HQ-ACC-SW6(config-if-range)#switchport port-security HQ-ACC-SW6(config-if-range)#switchport port-security maximum 2 HQ-ACC-SW6(config-if-range)#switchport port-security violation restrict

5	Disabled Interfaces
	Configuration HQ-ACC-SW6(config)#int range f0/11-24,g0/2
	HQ-ACC-SW6(config-if-range)#shutdown HQ-ACC-SW6(config-if-range)#switchport access vlan 999
6	Interfaces IP Addresses & Default Gateway
	Configuration
	HQ-ACC-SW6(config)#ip default-gateway 192.168.200.1 HQ-ACC-SW6(config-if)#int vlan 200 HQ-ACC-SW6(config-if)#ip address 192.168.200.9 255.255.254
7	NTP
	Configuration HQ-ACC-SW6(config)#ntp authentication-key 123 md5 cisco HQ-ACC-SW6(config)#ntp authenticate HQ-ACC-SW6(config)#ntp trusted-key 123 HQ-ACC-SW6(config)#ntp server 195.1.1.8
8	Sys-logs
	Configuration
	HQ-ACC-SW6(config)#service timestamps log datetime msec HQ-ACC-SW6(config)#logging 195.1.1.5
9	DHCP Snooping & Dynamic Arp Inspection
	Configuration

	HQ-ACC-SW4(config)#ip dhcp snooping HQ-ACC-SW6(config)#ip dhcp snooping HQ-ACC-SW6(config)#ip dhcp snooping vlan 10,15,20,30,40,50,60,70,80,90,100 HQ-ACC-SW6(config)#ip arp inspection vlan 10,15,20,30,40,50,60,70,80,90,100
10	Disable CDP
	Configuration
	HQ-ACC-SW6(config)#no cdp run HQ-ACC-SW6(config)#int g0/1 HQ-ACC-SW6(config-if)#cdp enable
11	AAA
	Configuration
	HQ-ACC-SW6(config)#enable secret level 15 depi HQ-ACC-SW6(config)#username DEPI privilege 15 secret 123
	HQ-ACC-SW6(config)#aaa new-model HQ-ACC-SW6(config)#tacacs-server host 195.1.1.7 key DEPI
	HQ-ACC-SW6(config)#aaa authentication login default group tacacs+ local HQ-ACC-SW6(config)#aaa authorization exec default group tacacs+ local
	HQ-ACC-SW6(config)#aaa accounting exec default start-stop group tacacs+
	HQ-ACC-SW6(config)#ip domain-name HQ-ACC-SW6.depi HQ-ACC-SW6(config)#crypto key generate rsa general-keys modulus 1024
	HQ-ACC-SW6(config)#ip ssh version 2
	HQ-ACC-SW6(config)#line vty 0 2 HQ-ACC-SW6(config-line)#login authentication default
	HQ-ACC-SW6(config-line)#transport input ssh

No	Description
1	Trunking
	Configuration
	HQ-ACC-SW7(config)#int range g0/1,g1/1,g2/1,g3/1 HQ-ACC-SW7(config-if-range)#switchport mode trunk HQ-ACC-SW7(config-if-range)#switchport trunk native vlan 99 HQ-ACC-SW7(config-if-range)#ip dhcp snooping trust
	HQ-ACC-SW7(config)#int g3/1 HQ-ACC-SW7(config-if)#switchport trunk allowed vlan 15,200
2	VTP
	Configuration
	HQ-ACC-SW7(config)#vtp version 2 HQ-ACC-SW7(config)#vtp domain DEPI HQ-ACC-SW7(config)#vtp password 123 HQ-ACC-SW7(config)#vtp mode client
3	STP
	Configuration
	HQ-ACC-SW7(config)#spanning-tree mode rapid-pvst
4	Interfaces IP Addresses & Default Gateway
	Configuration

	HQ-ACC-SW7(config)#ip default-gateway 192.168.200.1 HQ-ACC-SW7(config-if)#int vlan 200 HQ-ACC-SW7(config-if)#ip address 192.168.200.14 255.255.255.224
5	Disabled Interfaces
	Configuration HQ-ACC-SW7(config)#int range g4/1,g5/1,g6/1,g7/1,g8/1,g9/1 HQ-ACC-SW7(config-if-range)#shutdown HQ-ACC-SW7(config-if-range)#switchport access vlan 999
7	NTP
	Configuration HQ-ACC-SW7(config)#ntp authentication-key 123 md5 cisco HQ-ACC-SW7(config)#ntp authenticate HQ-ACC-SW7(config)#ntp trusted-key 123 HQ-ACC-SW7(config)#ntp server 195.1.1.8
8	Sys-logs
	Configuration HQ-ACC-SW7(config)#service timestamps log datetime msec HQ-ACC-SW7(config)#logging 195.1.1.5
9	DHCP Snooping & Dynamic Arp Inspection
	Configuration HQ-ACC-SW7(config)#ip dhcp snooping HQ-ACC-SW7(config)#ip dhcp snooping vlan 10,15,20,30,40,50,60,70,80,90,100 HQ-ACC-SW7(config)#ip arp inspection vlan 10,15,20,30,40,50,60,70,80,90,100
11	AAA 54

Con	figuration
HQ-	ACC-SW7(config)#enable secret level 15 depi
HQ-	ACC-SW7(config)#username DEPI privilege 15 secret 123
HQ-	ACC-SW7(config)#aaa new-model
HQ-	ACC-SW7(config)#tacacs-server host 195.1.1.7 key DEPI
HQ-	ACC-SW7(config)#aaa authentication login default group tacacs+ local
HQ-	ACC-SW7(config)#aaa authorization exec default group tacacs+ local
HQ-	ACC-SW7(config)#aaa accounting exec default start-stop group tacacs+
HQ-	ACC-SW7(config)#ip domain-name HQ-ACC-SW7.depi
HQ-	ACC-SW7(config)#crypto key generate rsa general-keys modulus 1024
HQ-	ACC-SW7(config)#ip ssh version 2
HQ-	ACC-SW7(config)#line vty 0 2
HQ-	ACC-SW7(config-line)#login authentication default
	ACC-SW7(config-line)#transport input ssh

No	Description
1	Trunking
	Configuration HQ-ACC-SW8(config)int g0/1 HQ-ACC-SW8(config-if)#switchport mode trunk HQ-ACC-SW8(config-if)#switchport trunk native vlan 99 HQ-ACC-SW8(config-if)#ip dhcp snooping trust
2	VTP
	Configuration

	HQ-ACC-SW8(config)#vtp version 2 HQ-ACC-SW8(config)#vtp domain DEPI HQ-ACC-SW8(config)#vtp password 123 HQ-ACC-SW8(config)#vtp mode client
3	STP
	Configuration HQ-ACC-SW8(config)#spanning-tree mode rapid-pvst HQ-ACC-SW8(config)#spanning-tree portfast default HQ-ACC-SW8(config)#spanning-tree portfast bpduguard default
4	Interfaces IP Addresses & Default Gateway
	Configuration HQ-ACC-SW7(config)#ip default-gateway 192.168.200.1 HQ-ACC-SW8(config)#ip default-gateway 192.168.200.1 HQ-ACC-SW8(config-if)#int vlan 200 HQ-ACC-SW8(config-if)#ip address 192.168.200.10 255.255.255.224
5	Disabled Interfaces
	Configuration HQ-ACC-SW8(config)#int range f0/8-24,g0/2 HQ-ACC-SW8(config-if-range)#shutdown HQ-ACC-SW8(config-if-range)#switchport access vlan 999
7	NTP
	Configuration H HQ-ACC-SW8(config)#ntp authentication-key 123 md5 cisco HQ-ACC-SW8(config)#ntp authenticate HQ-ACC-SW8(config)#ntp trusted-key 123

	HQ-ACC-SW8(config)#ntp server 195.1.1.8
8	Sys-logs Sys-logs
	Configuration HQ-ACC-SW8(config)#service timestamps log datetime msec HQ-ACC-SW8(config)#logging 195.1.1.5
9	DHCP Snooping & Dynamic Arp Inspection
	Configuration HQ-ACC-SW8(config)#ip dhcp snooping HQ-ACC-SW8(config)#ip dhcp snooping vlan 10,15,20,30,40,50,60,70,80,90,100 HQ-ACC-SW8(config)#ip arp inspection vlan 10,15,20,30,40,50,60,70,80,90,100
10	Disable CDP
	Configuration HQ-ACC-SW8(config)#no cdp run HQ-ACC-SW8(config)#int g0/1 HQ-ACC-SW8(config-if)#cdp enable
11	AAA
	Configuration
	Configuration HQ-ACC-SW8(config)#enable secret level 15 depi HQ-ACC-SW8(config)#username DEPI privilege 15 secret 123
	HQ-ACC-SW8(config)#enable secret level 15 depi

HQ-ACC-SW8(config)#crypto key generate rsa general-keys modulus 1024
HQ-ACC-SW8(config)#ip ssh version 2

HQ-ACC-SW8(config)#line vty 0 2
HQ-ACC-SW8(config-line)#login authentication default
HQ-ACC-SW8(config-line)#transport input ssh

Description
Trunking
Configuration HQ-SW-CAM-F1(config)int range g0/1 HQ-SW-CAM-F1(config-if)#switchport mode trunk HQ-SW-CAM-F1(config-if)#switchport trunk native vlan 99 HQ-SW-CAM-F1(config-if)#switchport trunk allowed vlan 15,200 HQ-SW-CAM-F1(config-if-range)#ip dhcp snooping trust
Access Interfaces
Configuration HQ-SW-CAM-F1(config)#int range fa0/1-24 HQ-SW-CAM-F1(config-if-range)#switchport mode access HQ-SW-CAM-F1(config-if-range)#switchport access vlan 15
VTP
Configuration
HQ-SW-CAM-F1(config)#vtp version 2 HQ-SW-CAM-F1(config)#vtp domain DEPI HQ-SW-CAM-F1(config)#vtp password 123 HQ-SW-CAM-F1(config)#vtp mode client

4	Interfaces IP Addresses & Default Gateway
	Configuration H HQ-SW-CAM-F1(config)#ip default-gateway 192.168.200.1 HQ-SW-CAM-F1(config-if)#int vlan 200 HQ-SW-CAM-F1(config-if)#ip address 192.168.200.11 255.255.255.224
5	Disabled Interfaces
	Configuration HQ-SW-CAM-F1(config)#int range fa0/4-24,g0/2 HQ-SW-CAM-F1(config-if-range)#shutdown HQ-SW-CAM-F1(config-if-range)#switchport mode access HQ-SW-CAM-F1(config-if-range)#switchport access vlan 999
6	NTP
	Configuration HQ-SW-CAM-F1(config)#ntp authentication-key 123 md5 cisco HQ-SW-CAM-F1(config)#ntp authenticate HQ-SW-CAM-F1(config)#ntp trusted-key 123 HQ-SW-CAM-F1(config)#ntp server 195.1.1.8
7	Sys-logs
	Configuration HQ-SW-CAM-F1(config)#service timestamps log datetime msec
8	HQ-SW-CAM-F1(config)#logging 195.1.1.5 DHCP Snooping & Dynamic Arp Inspection
	59

	Configuration HQ-SW-CAM-F1(config)#ip dhcp snooping HQ-SW-CAM-F1(config)#ip dhcp snooping vlan 10,15,20,30,40,50,60,70,80,90,100 HQ-SW-CAM-F1(config)#ip arp inspection vlan 10,15,20,30,40,50,60,70,80,90,100
9	Disable CDP
	Configuration
	H HQ-SW-CAM-F1(config)#no cdp run HQ-SW-CAM-F1(config)#int g0/1 HQ-SW-CAM-F1(config-if)#cdp enable
10	AAA
	Configuration
	HQ-SW-CAM-F1(config)#enable secret level 15 depi HQ-SW-CAM-F1(config)#username DEPI privilege 15 secret 123
	HQ-SW-CAM-F1(config)#aaa new-model
	HQ-SW-CAM-F1(config)#tacacs-server host 195.1.1.7 key DEPI
	HQ-SW-CAM-F1(config)#tacacs-server host 195.1.1.7 key DEPI HQ-SW-CAM-F1(config)#aaa authentication login default group tacacs+ local
	HQ-SW-CAM-F1(config)#tacacs-server host 195.1.1.7 key DEPI
	HQ-SW-CAM-F1(config)#tacacs-server host 195.1.1.7 key DEPI HQ-SW-CAM-F1(config)#aaa authentication login default group tacacs+ local HQ-SW-CAM-F1(config)#aaa authorization exec default group tacacs+ local HQ-SW-CAM-F1(config)#aaa accounting exec default start-stop group tacacs+ HQ-SW-CAM-F1(config)#ip domain-name HQ-SW-CAM-F1.depi
	HQ-SW-CAM-F1(config)#tacacs-server host 195.1.1.7 key DEPI HQ-SW-CAM-F1(config)#aaa authentication login default group tacacs+ local HQ-SW-CAM-F1(config)#aaa authorization exec default group tacacs+ local HQ-SW-CAM-F1(config)#aaa accounting exec default start-stop group tacacs+ HQ-SW-CAM-F1(config)#ip domain-name HQ-SW-CAM-F1.depi HQ-SW-CAM-F1(config)#crypto key generate rsa general-keys modulus 1024
	HQ-SW-CAM-F1(config)#tacacs-server host 195.1.1.7 key DEPI HQ-SW-CAM-F1(config)#aaa authentication login default group tacacs+ local HQ-SW-CAM-F1(config)#aaa authorization exec default group tacacs+ local HQ-SW-CAM-F1(config)#aaa accounting exec default start-stop group tacacs+ HQ-SW-CAM-F1(config)#ip domain-name HQ-SW-CAM-F1.depi
	HQ-SW-CAM-F1(config)#tacacs-server host 195.1.1.7 key DEPI HQ-SW-CAM-F1(config)#aaa authentication login default group tacacs+ local HQ-SW-CAM-F1(config)#aaa authorization exec default group tacacs+ local HQ-SW-CAM-F1(config)#aaa accounting exec default start-stop group tacacs+ HQ-SW-CAM-F1(config)#ip domain-name HQ-SW-CAM-F1.depi HQ-SW-CAM-F1(config)#crypto key generate rsa general-keys modulus 1024

No	Description
1	Trunking
	Configuration HQ-SW-CAM-F2(config)#int g0/1 HQ-SW-CAM-F2(config-if)#switchport mode trunk HQ-SW-CAM-F2(config-if)#switchport trunk native vlan 99 HQ-SW-CAM-F2(config-if)#switchport trunk allowed vlan 15,200 HQ-SW-CAM-F2(config-if)#ip dhcp snooping trust
2	Access Interfaces
	Configuration HQ-SW-CAM-F2(config)#int range fa0/1-24 HQ-SW-CAM-F2(config-if-range)#switchport mode access HQ-SW-CAM-F2(config-if-range)#switchport access vlan 15 HQ-SW-CAM-F2(config-if-range)#ip dhcp snooping limit rate 10
3	VTP
	Configuration HQ-SW-CAM-F2(config)#vtp version 2

7	Sys-logs Configuration
	Configuration H HQ-SW-CAM-F2(config)#ntp authentication-key 123 md5 cisco HQ-SW-CAM-F2(config)#ntp authenticate HQ-SW-CAM-F2(config)#ntp trusted-key 123 HQ-SW-CAM-F2(config)#ntp server 195.1.1.8
6	NTP
	Configuration HQ-SW-CAM-F2(config)#int range fa0/4-24,g0/2 HQ-SW-CAM-F2(config-if-range)#shutdown HQ-SW-CAM-F2(config-if-range)#switchport mode access HQ-SW-CAM-F2(config-if-range)#switchport access vlan 999
5	Disabled Interfaces
	Configuration HQ-SW-CAM-F2(config)#ip default-gateway 192.168.200.1 HQ-SW-CAM-F2(config-if)#int vlan 200 HQ-SW-CAM-F2(config-if)#ip address 192.168.200.12 255.255.255.2
4	Interfaces IP Addresses & Default Gateway
	HQ-SW-CAM-F2(config)#vtp domain DEPI HQ-SW-CAM-F2(config)#vtp password 123 HQ-SW-CAM-F2(config)#vtp mode client

	HQ-SW-CAM-F2(config)#logging 195.1.1.5
8	DHCP Snooping & Dynamic Arp Inspection
	Configuration
	HQ-SW-CAM-F2(config)#ip dhcp snooping HQ-SW-CAM-F2(config)#ip dhcp snooping vlan 10,15,20,30,40,50,60,70,80,90,100 HQ-SW-CAM-F2(config)#ip arp inspection vlan 10,15,20,30,40,50,60,70,80,90,100
9	Disable CDP
	Configuration
	HQ-SW-CAM-F2(config)#no cdp run
	HQ-SW-CAM-F2(config)#int g0/1
	HQ-SW-CAM-F2(config-if)#cdp enable
10	AAA
	Configuration
	HQ-SW-CAM-F2(config)#enable secret level 15 depi
	HQ-SW-CAM-F2(config)#username DEPI privilege 15 secret 123
	HQ-SW-CAM-F2(config)#aaa new-model
	HQ-SW-CAM-F2(config)#tacacs-server host 195.1.1.7 key DEPI
	,
	HQ-SW-CAM-F2(config)#aaa authentication login default group tacacs+ local
	HQ-SW-CAM-F2(config)#aaa authentication login default group tacacs+ local HQ-SW-CAM-F2(config)#aaa authorization exec default group tacacs+ local HQ-SW-CAM-F2(config)#aaa accounting exec default start-stop group tacacs+
	HQ-SW-CAM-F2(config)#aaa authorization exec default group tacacs+ local HQ-SW-CAM-F2(config)#aaa accounting exec default start-stop group tacacs+
	HQ-SW-CAM-F2(config)#aaa authorization exec default group tacacs+ local HQ-SW-CAM-F2(config)#aaa accounting exec default start-stop group tacacs+ HQ-SW-CAM-F2(config)#ip domain-name HQ-SW-CAM-F2.depi
	HQ-SW-CAM-F2(config)#aaa authorization exec default group tacacs+ local HQ-SW-CAM-F2(config)#aaa accounting exec default start-stop group tacacs+
	HQ-SW-CAM-F2(config)#aaa authorization exec default group tacacs+ local HQ-SW-CAM-F2(config)#aaa accounting exec default start-stop group tacacs+ HQ-SW-CAM-F2(config)#ip domain-name HQ-SW-CAM-F2.depi HQ-SW-CAM-F2(config)#crypto key generate rsa general-keys modulus 1024
	HQ-SW-CAM-F2(config)#aaa authorization exec default group tacacs+ local HQ-SW-CAM-F2(config)#aaa accounting exec default start-stop group tacacs+ HQ-SW-CAM-F2(config)#ip domain-name HQ-SW-CAM-F2.depi HQ-SW-CAM-F2(config)#crypto key generate rsa general-keys modulus 1024 HQ-SW-CAM-F2(config)#ip ssh version 2 HQ-SW-CAM-F2(config)#line vty 0 2 HQ-SW-CAM-F2(config-line)#login authentication default
	HQ-SW-CAM-F2(config)#aaa authorization exec default group tacacs+ local HQ-SW-CAM-F2(config)#aaa accounting exec default start-stop group tacacs+ HQ-SW-CAM-F2(config)#ip domain-name HQ-SW-CAM-F2.depi HQ-SW-CAM-F2(config)#crypto key generate rsa general-keys modulus 1024 HQ-SW-CAM-F2(config)#ip ssh version 2 HQ-SW-CAM-F2(config)#line vty 0 2

HQ-SW-CAM-F1(config-line)#login authentication default HQ-SW-CAM-F1(config-line)#transport input ssh

No	Description
1	Trunking
	Configuration HQ-SW-CAM-F3(config)#int g0/1 HQ-SW-CAM-F3(config-if)#switchport mode trunk HQ-SW-CAM-F3(config-if)#switchport trunk native vlan 99 HQ-SW-CAM-F3(config-if)#switchport trunk allowed vlan 15,200
2	Access Interfaces
	Configuration HQ-SW-CAM-F3(config)#int range fa0/1-24 HQ-SW-CAM-F3(config-if-range)#switchport mode access HQ-SW-CAM-F3(config-if-range)#switchport access vlan 15
3	VTP
	Configuration
	HQ-SW-CAM-F3(config)#vtp version 2

	LIO SW CAM F2/config/thith domain DEDI
	HQ-SW-CAM-F3(config)#vtp domain DEPI HQ-SW-CAM-F3(config)#vtp password 123
	HQ-SW-CAM-F3(config)#vtp password 123
4	Interfaces IP Addresses & Default Gateway
	Configuration HQ-SW-CAM-F3(config)#ip default-gateway 192.168.200.1 HQ-SW-CAM-F3(config-if)#int vlan 200 HQ-SW-CAM-F3(config-if)#ip address 192.168.200.13 255.255.255.224
5	Disabled Interfaces
	Configuration
	HQ-SW-CAM-F3(config)#int range fa0/4-24,g0/2 HQ-SW-CAM-F3(config-if-range)#shutdown HQ-SW-CAM-F3(config-if-range)#switchport mode access HQ-SW-CAM-F3(config-if-range)#switchport access vlan 999
6	NTP
	Configuration
	HQ-SW-CAM-F3(config)#ntp authentication-key 123 md5 cisco HQ-SW-CAM-F3(config)#ntp authenticate HQ-SW-CAM-F3(config)#ntp trusted-key 123 HQ-SW-CAM-F3(config)#ntp server 195.1.1.8
7	Sys-logs
	Configuration
	HO SW CAM E2(config)#sonvice timestowns les detetime rese
	HQ-SW-CAM-F3(config)#service timestamps log datetime msec HQ-SW-CAM-F3(config)#logging 195.1.1.5
	65

8	DHCP Snooping & Dynamic Arp Inspection
	Configuration HQ-SW-CAM-F3(config)#ip dhcp snooping HQ-SW-CAM-F3(config)#ip dhcp snooping vlan 10,15,20,30,40,50,60,70,80,90,100 HQ-SW-CAM-F3(config)#ip arp inspection vlan 10,15,20,30,40,50,60,70,80,90,100
9	Disable CDP
	Configuration HQ-SW-CAM-F3(config)#no cdp run HQ-SW-CAM-F3(config)#int g0/1
10	HQ-SW-CAM-F3(config-if)#cdp enable AAA
	Configuration
	HQ-SW-CAM-F3(config)#enable secret level 15 depi HQ-SW-CAM-F3(config)#username DEPI privilege 15 secret 123 HQ-SW-CAM-F3(config)#aaa new-model HQ-SW-CAM-F3(config)#tacacs-server host 195.1.1.7 key DEPI HQ-SW-CAM-F3(config)#aaa authentication login default group tacacs+ local HQ-SW-CAM-F3(config)#aaa authorization exec default group tacacs+ local HQ-SW-CAM-F3(config)#aaa accounting exec default start-stop group tacacs+ HQ-SW-CAM-F3(config)#ip domain-name HQ-SW-CAM-F3.depi HQ-SW-CAM-F3(config)#crypto key generate rsa general-keys modulus 1024 HQ-SW-CAM-F3(config)#ip ssh version 2
	HQ-SW-CAM-F3(config)#line vty 0 2 HQ-SW-CAM-F3(config-line)#login authentication default

HQ-SW-CAM-F3(config-line)#transport input ssh

No	Description
1	Trunking
	Configuration HQ-SW-CAM-F4(config)#int g0/1 HQ-SW-CAM-F4(config-if)#switchport mode trunk HQ-SW-CAM-F4(config-if)#switchport trunk native vlan 99 HQ-SW-CAM-F4(config-if)#switchport trunk allowed vlan 15,200 HQ-SW-CAM-F4(config-if)#ip dhcp snooping trust
2	Access Interfaces
	Configuration H HQ-SW-CAM-F4(config)#int range fa0/1-24 HQ-SW-CAM-F4(config-if-range)#switchport mode access HQ-SW-CAM-F4(config-if-range)#switchport access vlan 15 HQ-SW-CAM-F4(config-if-range)#ip dhcp snooping limit rate 10
3	VTP

	Configuration HQ-SW-CAM-F4(config)#vtp version 2 HQ-SW-CAM-F4(config)#vtp domain DEPI HQ-SW-CAM-F4(config)#vtp password 123 HQ-SW-CAM-F4(config)#vtp mode client
4	Interfaces IP Addresses & Default Gateway
	Configuration HQ-SW-CAM-F4(config)#ip default-gateway 192.168.200.1 HQ-SW-CAM-F4(config-if)#int vlan 200 HQ-SW-CAM-F4(config-if)#ip address 192.168.200.15 255.255.255.224
5	Disabled Interfaces
	Configuration HQ-SW-CAM-F4(config)#int range fa0/4-24,g0/2 HQ-SW-CAM-F4(config-if-range)#shutdown HQ-SW-CAM-F4(config-if-range)#switchport mode access HQ-SW-CAM-F4(config-if-range)#switchport access vlan 999
6	NTP
	Configuration HQ-SW-CAM-F4(config)#ntp authentication-key 123 md5 cisco HQ-SW-CAM-F4(config)#ntp authenticate HQ-SW-CAM-F4(config)#ntp trusted-key 123 HQ-SW-CAM-F4(config)#ntp server 195.1.1.8
7	Sys-logs
	68

	Configuration
	HQ-SW-CAM-F4(config)#service timestamps log datetime msec
	HQ-SW-CAM-F4(config)#logging 195.1.1.5
8	DHCP Snooping & Dynamic Arp Inspection
	Configuration
	W-CAM-F4(config)#ip dhcp snooping
	HQ-SW-CAM-F4(config)#ip dhcp snooping vlan 10,15,20,30,40,50,60,70,80,90,100
	HQ-SW-CAM-F4(config)#ip arp inspection vlan 10,15,20,30,40,50,60,70,80,90,100
9	Disable CDP
	Configuration
	HQ-SW-CAM-F4(config)#no cdp run
	HQ-SW-CAM-F4(config)#int g0/1
	HQ-SW-CAM-F4(config-if)#cdp enable
10	AAA
10	AAA Configuration
10	
10	Configuration
10	Configuration HQ-SW-CAM-F4(config)#enable secret level 15 depi
10	Configuration HQ-SW-CAM-F4(config)#enable secret level 15 depi HQ-SW-CAM-F4(config)#username DEPI privilege 15 secret 123 HQ-SW-CAM-F4(config)#aaa new-model HQ-SW-CAM-F4(config)#tacacs-server host 195.1.1.7 key DEPI
10	Configuration HQ-SW-CAM-F4(config)#enable secret level 15 depi HQ-SW-CAM-F4(config)#username DEPI privilege 15 secret 123 HQ-SW-CAM-F4(config)#aaa new-model HQ-SW-CAM-F4(config)#tacacs-server host 195.1.1.7 key DEPI HQ-SW-CAM-F4(config)#aaa authentication login default group tacacs+ local
10	Configuration HQ-SW-CAM-F4(config)#enable secret level 15 depi HQ-SW-CAM-F4(config)#username DEPI privilege 15 secret 123 HQ-SW-CAM-F4(config)#aaa new-model HQ-SW-CAM-F4(config)#tacacs-server host 195.1.1.7 key DEPI
10	Configuration HQ-SW-CAM-F4(config)#enable secret level 15 depi HQ-SW-CAM-F4(config)#username DEPI privilege 15 secret 123 HQ-SW-CAM-F4(config)#aaa new-model HQ-SW-CAM-F4(config)#tacacs-server host 195.1.1.7 key DEPI HQ-SW-CAM-F4(config)#aaa authentication login default group tacacs+ local HQ-SW-CAM-F4(config)#aaa authorization exec default group tacacs+ local
10	Configuration HQ-SW-CAM-F4(config)#enable secret level 15 depi HQ-SW-CAM-F4(config)#username DEPI privilege 15 secret 123 HQ-SW-CAM-F4(config)#aaa new-model HQ-SW-CAM-F4(config)#tacacs-server host 195.1.1.7 key DEPI HQ-SW-CAM-F4(config)#aaa authentication login default group tacacs+ local HQ-SW-CAM-F4(config)#aaa authorization exec default group tacacs+ local HQ-SW-CAM-F4(config)#aaa accounting exec default start-stop group tacacs+ HQ-SW-CAM-F4(config)#ip domain-name HQ-SW-CAM-F4.depi HQ-SW-CAM-F4(config)#crypto key generate rsa general-keys modulus 1024
10	Configuration HQ-SW-CAM-F4(config)#enable secret level 15 depi HQ-SW-CAM-F4(config)#username DEPI privilege 15 secret 123 HQ-SW-CAM-F4(config)#aaa new-model HQ-SW-CAM-F4(config)#tacacs-server host 195.1.1.7 key DEPI HQ-SW-CAM-F4(config)#aaa authentication login default group tacacs+ local HQ-SW-CAM-F4(config)#aaa authorization exec default group tacacs+ local HQ-SW-CAM-F4(config)#aaa accounting exec default start-stop group tacacs+ HQ-SW-CAM-F4(config)#ip domain-name HQ-SW-CAM-F4.depi
10	Configuration HQ-SW-CAM-F4(config)#enable secret level 15 depi HQ-SW-CAM-F4(config)#username DEPI privilege 15 secret 123 HQ-SW-CAM-F4(config)#aaa new-model HQ-SW-CAM-F4(config)#tacacs-server host 195.1.1.7 key DEPI HQ-SW-CAM-F4(config)#aaa authentication login default group tacacs+ local HQ-SW-CAM-F4(config)#aaa authorization exec default group tacacs+ local HQ-SW-CAM-F4(config)#aaa accounting exec default start-stop group tacacs+ HQ-SW-CAM-F4(config)#ip domain-name HQ-SW-CAM-F4.depi HQ-SW-CAM-F4(config)#crypto key generate rsa general-keys modulus 1024

HQ-SW-CAM-F4(config-line)#transport input ssh

B1-EdgeRouter

No	Description
1	Interfaces IP Addresses
	Configuration
	B1-EdgeRouter(config)#interface GigabitEthernet0/0/0 B1-EdgeRouter(config-if)#no shutdown B1-EdgeRouter(config-if)#ip address 10.1.0.1 255.255.252 B1-EdgeRouter(config-if)#ip ospf authentication message-digest B1-EdgeRouter(config-if)#ip ospf message-digest-key 1 md5 DEPI
	B1-EdgeRouter(config)#interface GigabitEthernet0/0/2 B1-EdgeRouter(config-if)#shutdown B1-EdgeRouter(config-if)#ip address 50.24.32.26 255.255.252
	B1-EdgeRouter(config)#int loopback 1 B1-EdgeRouter(config-if)#ip address 1.2.1.2 255.255.255

2	Default Route
	Configuration
	B1-EdgeRouter(config)#ip route 0.0.0.0 0.0.0.0 50.24.32.25
3	OSPF Routing
	Configuration
	B1-EdgeRouter(config)#router ospf 1
	B1-EdgeRouter(config-router)#router-id 1.2.1.2
	B1-EdgeRouter(config-router)#network 10.1.0.0 0.0.0.3 area 0 B1-EdgeRouter(config-router)#area 0 authentication message-digest
	22 Eagenoater (coming router) marea o authenticution message digest
4	
4	NTP
	Configuration
	B1-EdgeRouter(config)#ntp authentication-key 123 md5 cisco
	B1-EdgeRouter(config)#ntp authenticate B1-EdgeRouter(config)#ntp trusted-key 123
	B1-EdgeRouter(config)#ntp server 195.1.1.8
5	Sys-logs
	Configuration
	B1-EdgeRouter(config)#service timestamps log datetime msec
	B1-EdgeRouter(config)#logging 195.1.1.5
6	Disable CDP
	Configuration

	HQ-EdgeRouter(config)#int g0/0/2 HQ-EdgeRouter(config-if)#no cdp ena
9	AAA
	Configuration
	B1-EdgeRouter(config)#username DEPI privilege 15 secret 123 B1-EdgeRouter(config)#enable secret level 15 depi
	B1-EdgeRouter(config)#aaa new-model B1-EdgeRouter(config)#tacacs-server host 10.10.0.4 key DEPI B1-EdgeRouter(config)#aaa authentication login default group tacacs+ local B1-EdgeRouter(config)#aaa authorization exec default group tacacs+ local B1-EdgeRouter(config)#aaa accounting exec default start-stop group tacacs+
	B1-EdgeRouter(config)#ip domain-name B1-CORE-MLS1.depi B1-EdgeRouter(config)#crypto key generate rsa general-keys modulus 1024 B1-EdgeRouter(config)#ip ssh version 2
	B1-EdgeRouter(config)#line vty 0 2 B1-EdgeRouter(config-line)#login authentication default B1-EdgeRouter(config-line)#transport input ssh

B1-NGFW

No	Description
1	Interfaces IP Addresses
	Configuration B1-NGFW(config)#interface GigabitEthernet1/1 B1-NGFW(config-if)#no shutdown B1-NGFW(config-if)#ip address 10.1.0.2 255.255.255.252 B1-NGFW(config-if)#nameif OUTSIDE B1-NGFW(config-if)#security-level 0

	B1-NGFW(config-if)#ip ospf authentication message-digest B1-NGFW(config-if)#ip ospf message-digest-key 1 md5 DEPI B1-NGFW(config-if)#in oshutdown B1-NGFW(config-if)#ip address 10.1.0.9 255.255.255.252 B1-NGFW(config-if)#ip address 10.1.0.9 255.255.255.252 B1-NGFW(config-if)#ip ospf authentication message-digest B1-NGFW(config-if)#ip ospf authentication message-digest B1-NGFW(config-if)#ip ospf message-digest-key 1 md5 DEPI B1-NGFW(config-if)#ip ospf message-digest-key 1 md5 DEPI B1-NGFW(config-if)#ip address 10.1.0.5 255.255.255.252 B1-NGFW(config-if)#ip address 10.1.0.5 255.255.255.252 B1-NGFW(config-if)#ip address 10.1.0.5 255.255.255.252 B1-NGFW(config-if)#ip ospf message-digest B1-NGFW(config-if)#ip ospf message-digest-key 1 md5 DEPI B1-NGFW(config-if)#ip ospf message-digest-key 1 md5 DEPI B1-NGFW(config-if)#ip address 10.1.0.13 255.255.255.252 B1-NGFW(config-if)#ip ospf authentication message-digest B1-NGFW(config-if)#ip ospf authentication message-digest B1-NGFW(config-if)#ip ospf message-digest-key 1 md5 DEPI
	Configuration B1-NGFW(config)#router ospf 1 B1-NGFW(config-router)#router-id 1.2.1.1 B1-NGFW(config-router)#network 10.1.0.0 255.255.252 area 0 B1-NGFW(config-router)#network 10.1.0.4 255.255.252 area 0 B1-NGFW(config-router)#network 10.1.0.8 255.255.252 area 0 B1-NGFW(config-router)#network 10.1.0.12 255.255.252 area 0
3	Default Route
	Configuration B1-NGFW(config)#route OUTSIDE 0.0.0.0 0.0.0.0 10.1.0.2

4	Access Lists (ACLs) Configuration
	Configuration
	access-list DMZ-INSIDE extended permit udp host 10.10.0.2 any eq bootps access-list DMZ-INSIDE extended permit udp host 10.10.0.2 any eq bootpc access-group DMZ-INSIDE in interface DMZ access-list Inside extended permit udp any host 10.10.0.3 eq 514
	access-list Inside extended permit udp any host 10.10.0.2 eq bootps access-list Inside extended permit udp any host 10.10.0.2 eq bootpc
	access-group Inside in interface INSIDE1 access-group Inside in interface INSIDE2
5	NTP
	Configuration
	HQ-NGFW1(config)#ntp authentication-key 123 md5 cisco HQ-NGFW1(config)#ntp authenticate HQ-NGFW1(config)#ntp trusted-key 123 HQ-NGFW1(config)#ntp server 195.1.1.8

B1-DMZ-MLS

No	Description
1	Create Vlans

	Configuration
	B1-DMZ-MLS(config)#vlan 40 B1-DMZ-MLS(config-vlan)#name Servers
	B1-DMZ-MLS(config)#vlan 999 B1-DMZ-MLS(config-vlan)#name PARKING_VLAN
2	OSPF Routing
	Configuration
	B1-DMZ-MLS(config)#router ospf 1 B1-DMZ-MLS(config-router)#router-id 1.2.1.5 B1-DMZ-MLS(config-router)#network 10.1.0.12 0.0.0.3 area 0 B1-DMZ-MLS(config-router)#network 10.10.0.0 0.0.0.7 area 0 B1-DMZ-MLS(config-router)#area 0 authentication message-digest
3	Interfaces IP Addresses
	Configuration
	B1-DMZ-MLS(config)#ip routing
	B1-DMZ-MLS(config)#int loopback 1 B1-DMZ-MLS(config-if)#ip address 1.2.1.5 255.255.255
	B1-DMZ-MLS(config)#interface GigabitEthernet0/1 B1-DMZ-MLS(config-if)#no shutdown
	B1-DMZ-MLS(config-if)#no switchport
	B1-DMZ-MLS(config-if)#ip address 10.1.0.14 255.255.252 B1-DMZ-MLS(config-if)#ip ospf authentication message-digest
	B1-DMZ-MLS(config-if)#ip ospf message-digest-key 1 md5 DEPI
	B1-DMZ-MLS(config)#int vlan 40
	B1-DMZ-MLS(config-if)#ip address 10.10.0.1 255.255.255.248 B1-DMZ-MLS(config-if)#no shutdown
	B1-DMZ-MLS(config-if)#no switchport
	B1-DMZ-MLS(config-if)#ip address 10.1.0.14 255.255.252
	B1-DMZ-MLS(config-if)#ip ospf authentication message-digest B1-DMZ-MLS(config-if)#ip ospf message-digest-key 1 md5 DEPI
	B1-DMZ-MLS(config)#int vlan 40

	B1-DMZ-MLS(config-if)#ip address 10.10.0.1 255.255.258
4	STP
	Configuration B1-DMZ-MLS(config)#no spanning-tree vlan 1,40,999 B1-DMZ-MLS(config)#spanning-tree portfast default
5	B1-DMZ-MLS(config)#spanning-tree portfast bpduguard default OSPF Routing
	OSI I Routing
	Configuration B1-DMZ-MLS(config)#router ospf 1 B1-DMZ-MLS(config-router)#router-id 1.2.1.5 B1-DMZ-MLS(config-router)#network 10.1.0.12 0.0.0.3 area 0 B1-DMZ-MLS(config-router)#network 10.10.0.0 0.0.0.7 area 0 B1-DMZ-MLS(config-router)#area 0 authentication message-digest
6	Default Route
	Configuration B1-DMZ-MLS(config)#ip route 0.0.0.0 0.0.0.0 10.1.0.13
7	Disabled Interfaces
	Configuration B1-DMZ-MLS(config)#int range fa0/4-24,g0/2 B1-DMZ-MLS(config-if-range)#switchport mode access B1-DMZ-MLS(config-if-range)#switchport access vlan 999
8	NTP

Configuration

HQ-DMZ-MLS(config)#ntp authentication-key 123 md5 cisco

HQ-DMZ-MLS(config)#ntp authenticate

HQ-DMZ-MLS(config)#ntp trusted-key 123

HQ-DMZ-MLS(config)#ntp server 195.1.1.8

B1-CORE-MLS1

No	Description
1	Create Vlans
	Configuration
	B1-CORE-MLS1(config)#vlan 15 B1-CORE-MLS1(config-vlan)#name CCTV B1-CORE-MLS1(config)#vlan 20
	B1-CORE-MLS1(config-vlan)#name ATM
	B1-CORE-MLS1(config)#vlan 30 B1-CORE-MLS1(config-vlan)#name Management
	B1-CORE-MLS1(config)#vlan 40 B1-CORE-MLS1(config-vlan)#name Voice
	B1-CORE-MLS1(config)#vlan 50

B1-CORE-MLS1(config-vlan)#name Guest B1-CORE-MLS1(config)#vlan 60 B1-CORE-MLS1(config-vlan)#name Retail Banking B1-CORE-MLS1(config)#vlan 70 B1-CORE-MLS1(config-vlan)#name Credits and Loans B1-CORE-MLS1(config)#vlan 80 B1-CORE-MLS1(config-vlan)#name Customer Service B1-CORE-MLS1(config)#vlan 90 B1-CORE-MLS1(config-vlan)#name IT B1-CORE-MLS1(config)#vlan 99 B1-CORE-MLS1(config-vlan)#name Native B1-CORE-MLS1(config)#vlan 200 B1-CORE-MLS1(config-vlan)#name Manage B1-CORE-MLS1(config)#vlan 999 B1-CORE-MLS1(config-vlan)#name PARKING_VLAN 2 Interfaces IP Addresses & HSRB Configuration B1-CORE-MLS1(config)#ip routing B1-CORE-MLS1(config)#interface loopback 1 B1-CORE-MLS1(config-if)#ip address 1.2.1.4 255.255.255.255 B1-CORE-MLS1(config)#interface GigabitEthernet1/0/1 B1-CORE-MLS1(config-if)#no shutdown B1-CORE-MLS1(config-if)#no switchport B1-CORE-MLS1(config-if)#ip address 10.1.0.10 255.255.255.252 B1-CORE-MLS1(config-if)#ip ospf authentication message-digest B1-CORE-MLS1(config-if)#ip ospf message-digest-key 1 md5 DEPI B1-CORE-MLS1(config)#int vlan 15 B1-CORE-MLS1(config-if)#ip address 192.168.151.2 255.255.255.240 B1-CORE-MLS1(config-if)#standby version 2 B1-CORE-MLS1(config-if)#standby 15 ip B1-CORE-MLS1(config)#int vlan 20 B1-CORE-MLS1(config-if)#ip address 192.168.21.2 255.255.255.240 B1-CORE-MLS1(config-if)#ip helper-address 10.10.0.2

```
B1-CORE-MLS1(config-if)#standby version 2
B1-CORE-MLS1(config-if)#standby 2 ip 192.168.21.1
B1-CORE-MLS1(config-if)#standby 2 priority 150
B1-CORE-MLS1(config-if)#standby 2 preempt
B1-CORE-MLS1(config)#int vlan 30
B1-CORE-MLS1(config-if)#ip address 192.168.31.2 255.255.255.240
B1-CORE-MLS1(config-if)#ip helper-address 10.10.0.2
B1-CORE-MLS1(config-if)#standby version 2
B1-CORE-MLS1(config-if)#standby 3 ip 192.168.31.1
B1-CORE-MLS1(config-if)#standby 3 priority 150
B1-CORE-MLS1(config-if)#standby 3 preempt
B1-CORE-MLS1(config)#int vlan 40
B1-CORE-MLS1(config-if)#ip address 192.168.41.2 255.255.255.0
B1-CORE-MLS1(config-if)#ip helper-address 10.10.0.2
B1-CORE-MLS1(config-if)#standby version 2
B1-CORE-MLS1(config-if)#standby 4 ip 192.168.41.1
B1-CORE-MLS1(config-if)#standby 4 priority 150
B1-CORE-MLS1(config-if)#standby 4 preempt
B1-CORE-MLS1(config)#int vlan 50
B1-CORE-MLS1(config-if)#ip address 192.168.51.2 255.255.255.0
B1-CORE-MLS1(config-if)#ip helper-address 10.10.0.2
B1-CORE-MLS1(config-if)#standby version 2
B1-CORE-MLS1(config-if)#standby 5 ip 192.168.51.1
B1-CORE-MLS1(config-if)#standby 5 priority 150
B1-CORE-MLS1(config-if)#standby 5 preempt
B1-CORE-MLS1(config)#int vlan 60
B1-CORE-MLS1(config-if)#ip address 192.168.61.2 255.255.255.240
B1-CORE-MLS1(config-if)#standby version 2
B1-CORE-MLS1(config-if)#standby 6 ip
B1-CORE-MLS1(config)#int vlan 70
B1-CORE-MLS1(config-if)#ip address 192.168.71.2 255.255.255.240
B1-CORE-MLS1(config-if)#standby version 2
B1-CORE-MLS1(config-if)#standby 7 ip
B1-CORE-MLS1(config)#int vlan 80
B1-CORE-MLS1(config-if)#ip address 192.168.81.2 255.255.255.240
B1-CORE-MLS1(config-if)#standby version 2
B1-CORE-MLS1(config-if)#standby 8 ip
B1-CORE-MLS1(config)#int vlan 90
B1-CORE-MLS1(config-if)#ip address 192.168.91.2 255.255.255.240
```

	B1-CORE-MLS1(config-if)#standby version 2 B1-CORE-MLS1(config-if)#standby 9 ip
	B1-CORE-MLS1(config)#int vlan 200 B1-CORE-MLS1(config-if)#ip address 192.168.200.2 255.255.255.248 B1-CORE-MLS1(config-if)#standby version 2 B1-CORE-MLS1(config-if)#standby 200 ip 192.168.200.1 B1-CORE-MLS1(config-if)#standby 200 priority 150 B1-CORE-MLS1(config-if)#standby 200 preempt
3	VTP
	Configuration
	B1-CORE-MLS1(config)#vtp version 2 B1-CORE-MLS1(config)#vtp domain DEPI B1-CORE-MLS1(config)#vtp password 123 B1-CORE-MLS1(config)#vtp mode server
4	STP
	Configuration
	B1-CORE-MLS1(config)#spanning-tree mode rapid-pvst B1-CORE-MLS1(config)#spanning-tree vlan 1,15,20,30,40,50,60,70,80,90,99,200, 999 root primary
5	Trunking
	Configuration
	B1-CORE-MLS1(config)#interface range g1/0/2,g1/0/3,g1/0/4 B1-CORE-MLS1(config-if-range)#switchport mode trunk B1-CORE-MLS1(config-if-range)#switchport trunk native vlan 99
6	OSPF Routing
	Configuration
	B1-CORE-MLS1(config)#router ospf 1 B1-CORE-MLS1(config-router)#router-id 1.2.1.4

## B1-CORE-MLS1(config-router)#no passive-interface g1/0/1 ## B1-CORE-MLS1(config-router)#network 10.1.0.8 0.0.0.3 area 0 ## B1-CORE-MLS1(config-router)#network 192.168.151.0 0.0.0.15 area 0 ## B1-CORE-MLS1(config-router)#network 192.168.21.0 0.0.0.15 area 0 ## B1-CORE-MLS1(config-router)#network 192.168.21.0 0.0.0.15 area 0 ## B1-CORE-MLS1(config-router)#network 192.168.31.0 0.0.0.15 area 0 ## B1-CORE-MLS1(config-router)#network 192.168.41.0 0.0.0.255 area 0 ## B1-CORE-MLS1(config-router)#network 192.168.51.0 0.0.0.255 area 0 ## B1-CORE-MLS1(config-router)#network 192.168.51.0 0.0.0.15 area 0 ## B1-CORE-MLS1(config-router)#network 192.168.51.0 0.0.0.15 area 0 ## B1-CORE-MLS1(config-router)#network 192.168.81.0 0.0.0.15 area 0 ## B1-CORE-MLS1(config-router)#network 192.168.81.0 0.0.0.15 area 0 ## B1-CORE-MLS1(config-router)#network 192.168.91.0 0.0.0.15 area 0 ## B1-CORE-MLS1(config-router)#network 192.168.200.0 0.0.0.7 area 0 ## B1-CORE-MLS1(config-router)#network 192.168.200.0 0.0.0.7 area 0 ## B1-CORE-MLS1(config-in-router)#network 192.168.200.0 0.0.0.7 area 0 ## B1-CORE-MLS1(config-in-router)#network 192.168.200.0 0.0.0.7 area 0 ## B1-CORE-MLS1(config-in-router)#network 192.168.200.0 0.0.0.0.7 area 0 ## B1-CORE-MLS1(config-in-router)#network 192.168.200.0 0.0.0.0.7 area 0 ## B1-CORE-MLS1(config-in-router)#network 192.168.200.0 0.0.0.0.0 10.1.0.9 ## B1-CORE-MLS1(config-in-router)#network 192.168.200.0 0.0.0.0 10.1.0.9 ## B1-CORE-MLS1(config-in-router)#network 192.168.200.0 10.1.0.9		B1-CORE-MLS1(config-router)#area 0 authentication message-digest B1-CORE-MLS1(config-router)#passive-interface Default
B1-CORE-MLS1(config-router)#network 192.168.151.0 0.0.0.15 area 0 B1-CORE-MLS1(config-router)#network 192.168.21.0 0.0.0.15 area 0 B1-CORE-MLS1(config-router)#network 192.168.31.0 0.0.0.15 area 0 B1-CORE-MLS1(config-router)#network 192.168.41.0 0.0.0.255 area 0 B1-CORE-MLS1(config-router)#network 192.168.51.0 0.0.0.255 area 0 B1-CORE-MLS1(config-router)#network 192.168.51.0 0.0.0.255 area 0 B1-CORE-MLS1(config-router)#network 192.168.61.0 0.0.0.15 area 0 B1-CORE-MLS1(config-router)#network 192.168.71.0 0.0.0.15 area 0 B1-CORE-MLS1(config-router)#network 192.168.81.0 0.0.0.15 area 0 B1-CORE-MLS1(config-router)#network 192.168.91.0 0.0.0.15 area 0 B1-CORE-MLS1(config-router)#network 192.168.200.0 0.0.0.7 area 0 B1-CORE-MLS1(config-router)#network 192.168.200.0 0.0.0.7 area 0 B1-CORE-MLS1(config)#ip route 0.0.0.0 0.0.0.0 10.1.0.9 Disabled Interfaces		B1-CORE-MLS1(config-router)#no passive-interface g1/0/1
B1-CORE-MLS1(config-router)#network 192.168.21.0 0.0.0.15 area 0 B1-CORE-MLS1(config-router)#network 192.168.31.0 0.0.0.15 area 0 B1-CORE-MLS1(config-router)#network 192.168.31.0 0.0.0.255 area 0 B1-CORE-MLS1(config-router)#network 192.168.51.0 0.0.0.255 area 0 B1-CORE-MLS1(config-router)#network 192.168.51.0 0.0.0.255 area 0 B1-CORE-MLS1(config-router)#network 192.168.61.0 0.0.0.15 area 0 B1-CORE-MLS1(config-router)#network 192.168.71.0 0.0.0.15 area 0 B1-CORE-MLS1(config-router)#network 192.168.81.0 0.0.0.15 area 0 B1-CORE-MLS1(config-router)#network 192.168.91.0 0.0.0.15 area 0 B1-CORE-MLS1(config-router)#network 192.168.200.0 0.0.0.7 area 0 B1-CORE-MLS1(config)#ip route 0.0.0.0 0.0.0 10.1.0.9 Toliabled Interfaces Configuration B1-CORE-MLS1(config)#ip route 0.0.0.0 0.0.0 10.1.0.9 B1-CORE-MLS1(config)#ip route 0.0.0.0 0.0.0 10.1.0.9		
B1-CORE-MLS1(config-router)#network 192.168.41.0 0.0.0.255 area 0 B1-CORE-MLS1(config-router)#network 192.168.51.0 0.0.0.255 area 0 B1-CORE-MLS1(config-router)#network 192.168.61.0 0.0.0.15 area 0 B1-CORE-MLS1(config-router)#network 192.168.71.0 0.0.0.15 area 0 B1-CORE-MLS1(config-router)#network 192.168.81.0 0.0.0.15 area 0 B1-CORE-MLS1(config-router)#network 192.168.91.0 0.0.0.15 area 0 B1-CORE-MLS1(config-router)#network 192.168.91.0 0.0.0.15 area 0 B1-CORE-MLS1(config-router)#network 192.168.200.0 0.0.0.7 area 0 7		B1-CORE-MLS1(config-router)#network 192.168.21.0 0.0.0.15 area 0
B1-CORE-MLS1(config-router)#network 192.168.51.0 0.0.0.255 area 0 B1-CORE-MLS1(config-router)#network 192.168.61.0 0.0.0.15 area 0 B1-CORE-MLS1(config-router)#network 192.168.71.0 0.0.0.15 area 0 B1-CORE-MLS1(config-router)#network 192.168.81.0 0.0.0.15 area 0 B1-CORE-MLS1(config-router)#network 192.168.91.0 0.0.0.15 area 0 B1-CORE-MLS1(config-router)#network 192.168.91.0 0.0.0.15 area 0 B1-CORE-MLS1(config-router)#network 192.168.200.0 0.0.0.7 area 0 7		
B1-CORE-MLS1(config-router)#network 192.168.71.0 0.0.0.15 area 0 B1-CORE-MLS1(config-router)#network 192.168.81.0 0.0.0.15 area 0 B1-CORE-MLS1(config-router)#network 192.168.91.0 0.0.0.15 area 0 B1-CORE-MLS1(config-router)#network 192.168.200.0 0.0.0.7 area 0 7		B1-CORE-MLS1(config-router)#network 192.168.51.0 0.0.0.255 area 0
B1-CORE-MLS1(config-router)#network 192.168.81.0 0.0.0.15 area 0 B1-CORE-MLS1(config-router)#network 192.168.91.0 0.0.0.15 area 0 B1-CORE-MLS1(config-router)#network 192.168.200.0 0.0.0.7 area 0 7		
7 Default Route Configuration B1-CORE-MLS1(config)#ip route 0.0.0.0 0.0.0.0 10.1.0.9 Disabled Interfaces Configuration B1-CORE-MLS1(config)#int range g1/0/5-24,g1/1/1-4 B1-CORE-MLS1(config)#int range g1/0/5-24,g1/1/1-4 B1-CORE-MLS1(config)-if-range)#shutdown B1-CORE-MLS1(config-if-range)#switchport access vlan 999		B1-CORE-MLS1(config-router)#network 192.168.81.0 0.0.0.15 area 0
Configuration B1-CORE-MLS1(config)#ip route 0.0.0.0 0.0.0 10.1.0.9 Disabled Interfaces Configuration B1-CORE-MLS1(config)#int range g1/0/5-24,g1/1/1-4 B1-CORE-MLS1(config-if-range)#shutdown B1-CORE-MLS1(config-if-range)#switchport access vlan 999		
Configuration B1-CORE-MLS1(config)#ip route 0.0.0.0 0.0.0 10.1.0.9 Disabled Interfaces Configuration B1-CORE-MLS1(config)#int range g1/0/5-24,g1/1/1-4 B1-CORE-MLS1(config-if-range)#shutdown B1-CORE-MLS1(config-if-range)#switchport access vlan 999		, , , , , , , , , , , , , , , , , , , ,
B1-CORE-MLS1(config)#ip route 0.0.0.0 0.0.0 10.1.0.9 Disabled Interfaces Configuration B1-CORE-MLS1(config)#int range g1/0/5-24,g1/1/1-4 B1-CORE-MLS1(config-if-range)#shutdown B1-CORE-MLS1(config-if-range)#switchport access vlan 999	7	Default Route
B1-CORE-MLS1(config)#ip route 0.0.0.0 0.0.0 10.1.0.9 Disabled Interfaces Configuration B1-CORE-MLS1(config)#int range g1/0/5-24,g1/1/1-4 B1-CORE-MLS1(config-if-range)#shutdown B1-CORE-MLS1(config-if-range)#switchport access vlan 999		Configuration
Disabled Interfaces Configuration B1-CORE-MLS1(config)#int range g1/0/5-24,g1/1/1-4 B1-CORE-MLS1(config-if-range)#shutdown B1-CORE-MLS1(config-if-range)#switchport access vlan 999		
Configuration B1-CORE-MLS1(config)#int range g1/0/5-24,g1/1/1-4 B1-CORE-MLS1(config-if-range)#shutdown B1-CORE-MLS1(config-if-range)#switchport access vlan 999		B1-CORE-MLS1(config)#Ip route 0.0.0.0 0.0.0.0 10.1.0.9
B1-CORE-MLS1(config)#int range g1/0/5-24,g1/1/1-4 B1-CORE-MLS1(config-if-range)#shutdown B1-CORE-MLS1(config-if-range)#switchport access vlan 999	8	Disabled Interfaces
B1-CORE-MLS1(config-if-range)#shutdown B1-CORE-MLS1(config-if-range)#switchport access vlan 999		Configuration
B1-CORE-MLS1(config-if-range)#shutdown B1-CORE-MLS1(config-if-range)#switchport access vlan 999		B1-CORF-MLS1(config)#int range g1/0/5-24 g1/1/1-4
		(0,
9 Sys-logs		
		B1-CORE-MLS1(config-if-range)#switchport access vlan 999
Configuration	9	
B1-CORE-MLS2(config)#service timestamps log datetime msec	9	Sys-logs Sys-logs
	9	Sys-logs Configuration
B1-CORE-MLS2(config)#logging 10.10.0.3	9	Sys-logs Configuration
10 DHCP Snooping & Dynamic Arp		Sys-logs Configuration B1-CORE-MLS2(config)#service timestamps log datetime msec B1-CORE-MLS2(config)#logging 10.10.0.3
		Sys-logs Configuration B1-CORE-MLS2(config)#service timestamps log datetime msec B1-CORE-MLS2(config)#logging 10.10.0.3 DHCP Snooping & Dynamic Arp
B1-CORE-MLS2(config)#logging 10.10.0.3	9	Sys-logs Configuration B1-CORE-MLS2(config)#service timestamps log datetime msec

	Configuration
	B1-CORE-MLS1(config)#ip dhcp snooping B1-CORE-MLS1(config)#ip dhcp snooping vlan 15,20,30,40,50,60,70,80,90
	B1-CORE-MLS1(config)#interface range g1/0/2-4 B1-CORE-MLS1(config-if)#ip dhcp snooping trus
11	AAA
	Configuration
	B1-CORE-MLS1(config)#username DEPI privilege 15 algorithm-type scrypt secret 123 B1-CORE-MLS1(config)#enable algorithm-type scrypt secret depi
	B1-CORE-MLS1(config)#aaa new-model B1-CORE-MLS1(config)#tacacs-server host 10.10.0.4 key DEPI B1-CORE-MLS1(config)#aaa authentication login default group tacacs+ local
	B1-CORE-MLS1(config)#aaa authorization exec default group tacacs+ local B1-CORE-MLS1(config)#aaa accounting exec default start-stop group tacacs+
	B1-CORE-MLS1(config)#ip domain-name B1-CORE-MLS1.depi B1-CORE-MLS1(config)#crypto key generate rsa general-keys modulus 1024 B1-CORE-MLS1(config)#ip ssh version 2
	B1-CORE-MLS1(config)#line vty 0 2 B1-CORE-MLS1(config-line)#login authentication default B1-CORE-MLS1(config-line)#transport input ssh

B1-CORE-MLS2

No	Description
1	Interfaces IP Addresses & HSRB
	Configuration
	B1-CORE-MLS2(config)#ip routing

```
B1-CORE-MLS2(config)#interface loopback 1
B1-CORE-MLS2(config-if)#ip address 1.2.1.3 255.255.255.255
B1-CORE-MLS2(config)#interface GigabitEthernet1/0/1
B1-CORE-MLS2(config-if)#no shutdown
B1-CORE-MLS2(config-if)#no switchport
B1-CORE-MLS2(config-if)#ip address 10.1.0.6 255.255.255.252
B1-CORE-MLS2(config-if)#ip ospf authentication message-digest
B1-CORE-MLS2(config-if)#ip ospf message-digest-key 1 md5 DEPI
B1-CORE-MLS2(config)#int vlan 15
B1-CORE-MLS2(config-if)#ip address 192.168.151.3 255.255.255.240
B1-CORE-MLS2(config-if)#ip helper-address 10.10.0.2
B1-CORE-MLS2(config-if)#standby version 2
B1-CORE-MLS2(config-if)#standby 15 ip 192.168.151.1
B1-CORE-MLS2(config-if)#standby 15 priority 150
B1-CORE-MLS2(config-if)#standby 15 preempt
B1-CORE-MLS2(config)#int vlan 20
B1-CORE-MLS2(config-if)#ip address 192.168.21.3 255.255.255.240
B1-CORE-MLS2(config-if)#standby version 2
B1-CORE-MLS2(config-if)#standby 2 ip
B1-CORE-MLS2(config)#int vlan 30
B1-CORE-MLS2(config-if)#ip address 192.168.31.3 255.255.255.240
B1-CORE-MLS2(config-if)#standby version 2
B1-CORE-MLS2(config-if)#standby 3 ip
B1-CORE-MLS2(config)#int vlan 40
B1-CORE-MLS2(config-if)#ip address 192.168.41.3 255.255.255.0
B1-CORE-MLS2(config-if)#standby version 2
B1-CORE-MLS2(config-if)#standby 4 ip
B1-CORE-MLS2(config)#int vlan 50
B1-CORE-MLS2(config-if)#ip address 192.168.51.3 255.255.255.0
B1-CORE-MLS2(config-if)#standby version 2
B1-CORE-MLS2(config-if)#standby 5 ip
B1-CORE-MLS2(config)#int vlan 60
B1-CORE-MLS2(config-if)#ip address 192.168.61.3 255.255.255.240
B1-CORE-MLS2(config-if)#ip helper-address 10.10.0.2
B1-CORE-MLS2(config-if)#standby version 2
B1-CORE-MLS2(config-if)#standby 6 ip 192.168.61.1
B1-CORE-MLS2(config-if)#standby 6 priority 150
```

	B1-CORE-MLS2(config-if)#standby 6 preempt
	B1-CORE-MLS2(config-if)#standby 6 preempt B1-CORE-MLS2(config-if)#ip address 192.168.71.3 255.255.255.240 B1-CORE-MLS2(config-if)#ip helper-address 10.10.0.2 B1-CORE-MLS2(config-if)#standby version 2 B1-CORE-MLS2(config-if)#standby 7 ip 192.168.71.1 B1-CORE-MLS2(config-if)#standby 7 priority 150 B1-CORE-MLS2(config-if)#standby 7 preempt B1-CORE-MLS2(config-if)#ip address 192.168.81.3 255.255.255.240 B1-CORE-MLS2(config-if)#ip helper-address 10.10.0.2 B1-CORE-MLS2(config-if)#standby version 2 B1-CORE-MLS2(config-if)#standby 8 ip 192.168.81.1 B1-CORE-MLS2(config-if)#standby 8 priority 150 B1-CORE-MLS2(config-if)#standby 8 preempt B1-CORE-MLS2(config-if)#standby 8 preempt B1-CORE-MLS2(config-if)#standby 9 ip 192.168.90.3 255.255.255.240 B1-CORE-MLS2(config-if)#standby 9 ip 192.168.90.1 B1-CORE-MLS2(config-if)#standby 9 ip 192.168.90.1 B1-CORE-MLS2(config-if)#standby 9 priority 150 B1-CORE-MLS2(config-if)#standby 9 priority 150 B1-CORE-MLS2(config-if)#standby 9 ip 192.168.90.1 B1-CORE-MLS2(config-if)#standby 9 ip 192.168.90.1 B1-CORE-MLS2(config-if)#standby 9 priority 150 B1-CORE-MLS2(config-if)#standby 9 preempt B1-CORE-MLS2(config-if)#standby 9 preempt B1-CORE-MLS2(config-if)#standby 9 preempt B1-CORE-MLS2(config-if)#standby 9 preempt
	B1-CORE-MLS2(config-if)#standby 200 ip
2	Trunking
	Configuration
	B1-CORE-MLS2(config)#interface range g1/0/2,g1/0/3,g1/0/4 B1-CORE-MLS2(config-if-range)#switchport mode trunk B1-CORE-MLS2(config-if-range)#switchport trunk native vlan 99
3	VTP

	Configuration
	B1-CORE-MLS2(config)#vtp version 2 B1-CORE-MLS2(config)#vtp domain DEPI B1-CORE-MLS2(config)#vtp password 123 B1-CORE-MLS2(config)#vtp mode client
4	STP
	Configuration
	B1-CORE-MLS2(config)#spanning-tree mode rapid-pvst B1-CORE-MLS2(config)#spanning-tree vlan 1,15,20,30,40,50,60,70,80,90,99,200, 999 root secondary
5	OSPF Routing
	Configuration B1-CORE-MLS2(config)#router ospf 1
	B1-CORE-MLS2(config-router)#router-id 1.2.1.3 B1-CORE-MLS2(config-router)#area 0 authentication message-digest B1-CORE-MLS2(config-router)#passive-interface Default B1-CORE-MLS2(config-router)#no passive-interface g1/0/1 B1-CORE-MLS2(config-router)#network 10.1.0.4 0.0.0.3 area 0 B1-CORE-MLS2(config-router)#network 192.168.151.0 0.0.0.15 area 0 B1-CORE-MLS2(config-router)#network 192.168.21.0 0.0.0.15 area 0 B1-CORE-MLS2(config-router)#network 192.168.31.0 0.0.0.15 area 0 B1-CORE-MLS2(config-router)#network 192.168.41.0 0.0.0.255 area 0 B1-CORE-MLS2(config-router)#network 192.168.51.0 0.0.0.255 area 0 B1-CORE-MLS2(config-router)#network 192.168.61.0 0.0.0.15 area 0 B1-CORE-MLS2(config-router)#network 192.168.71.0 0.0.0.15 area 0 B1-CORE-MLS2(config-router)#network 192.168.81.0 0.0.0.15 area 0 B1-CORE-MLS2(config-router)#network 192.168.81.0 0.0.0.15 area 0 B1-CORE-MLS2(config-router)#network 192.168.91.0 0.0.0.15 area 0 B1-CORE-MLS2(config-router)#network 192.168.91.0 0.0.0.15 area 0 B1-CORE-MLS2(config-router)#network 192.168.91.0 0.0.0.15 area 0
6	Default Route
	Configuration
	B1-CORE-MLS2(config)#ip route 0.0.0.0 0.0.0.0 10.1.0.5

7	Disabled Interfaces
	Configuration
	B1-CORE-MLS2(config)#int range g1/0/5-24,g1/1/1-4 B1-CORE-MLS2(config-if-range)#shutdown B1-CORE-MLS2(config-if-range)#switchport access vlan 999
8	Sys-logs
	Configuration
	B1-CORE-MLS2(config)#service timestamps log datetime msec B1-CORE-MLS2(config)#logging 10.10.0.3
9	DHCP Snooping & Dynamic Arp Inspection
	Configuration B1-CORE-MLS1(config)#ip dhcp snooping B1-CORE-MLS1(config)#ip dhcp snooping vlan 15,20,30,40,50,60,70,80,90 B1-CORE-MLS1(config)#interface range g1/0/2-4 B1-CORE-MLS1(config-if)#ip dhcp snooping trust
10	AAA
	Configuration
	B1-CORE-MLS2(config)#username DEPI privilege 15 algorithm-type scrypt secret 123 B1-CORE-MLS2(config)#enable algorithm-type scrypt secret depi
	B1-CORE-MLS2(config)#aaa new-model B1-CORE-MLS2(config)#tacacs-server host 10.10.0.4 key DEPI B1-CORE-MLS2(config)#aaa authentication login default group tacacs+ local

B1-CORE-MLS2(config)#aaa authorization exec default group tacacs+ local B1-CORE-MLS2(config)#aaa accounting exec default start-stop group tacacs+
B1-CORE-MLS2(config)#ip domain-name B1-CORE-MLS2.depi B1-CORE-MLS2(config)#crypto key generate rsa general-keys modulus 1024 B1-CORE-MLS2(config)#ip ssh version 2
B1-CORE-MLS2(config)#line vty 0 2
B1-CORE-MLS2(config-line)#login authentication default B1-CORE-MLS2(config-line)#transport input ssh

B1-ACC-SW1

No	Description
1	Trunking & Access Interfaces
	Configuration B1-ACC-SW1(config)#interface range GigabitEthernet0/1,GigabitEthernet0/2 B1-ACC-SW1(config-if-range)#switchport mode trunk B1-ACC-SW1(config-if-range)#switchport trunk native vlan 99 B1-ACC-SW1(config)#interface FastEthernet0/24 B1-ACC-SW1(config-if)#switchport mode B1-ACC-SW1(config-if)#switchport access vlan 50
2	VTP
	Configuration
	B1-ACC-SW1(config)#vtp version 2 B1-ACC-SW1(config)#vtp domain DEPI B1-ACC-SW1(config)#vtp password 123 B1-ACC-SW1(config)#vtp mode client

3	STP & Portfast
	Configuration
	B1-ACC-SW1(config)#spanning-tree mode rapid-pvst B1-ACC-SW1(config)#spanning-tree portfast default
	B1-ACC-SW1(config)#spanning-tree portfast bpduguard default
4	Port Security & Assign Vlan & Voice Vlan
	Configuration
	B1-ACC-SW1(config)#int range fastEthernet 0/1-5
	B1-ACC-SW1(config-if-range)#switchport mode access
	B1-ACC-SW1(config-if-range)#switchport access vlan 80
	B1-ACC-SW1(config-if-range)#switchport voice vlan 40
	B1-ACC-SW1(config-if-range)#ip dhcp snooping limit rate 10
	B1-ACC-SW1(config-if-range)#switchport port-security B1-ACC-SW1(config-if-range)#switchport port-security maximum 2
	B1-ACC-SW1(config-if-range)#switchport port-security mac-address sticky
	B1-ACC-SW1(config-if-range)#switchport port-security violation restrict
	B1-ACC-SW1(config)#int range fastEthernet 0/6-10
	B1-ACC-SW1(config-if-range)#switchport mode access
	B1-ACC-SW1(config-if-range)#switchport access vlan 70
	B1-ACC-SW1(config-if-range)#switchport voice vlan 40
	B1-ACC-SW1(config-if-range)#ip dhcp snooping limit rate 10
	B1-ACC-SW1(config-if-range)#switchport port-security B1-ACC-SW1(config-if-range)#switchport port-security maximum 2
	B1-ACC-SW1(config-if-range)#switchport port-security maximum 2 B1-ACC-SW1(config-if-range)#switchport port-security mac-address sticky
	B1-ACC-SW1(config-if-range)#switchport port-security violation restrict
	B1-ACC-SW1(config)#int range fastEthernet 0/11-14
	B1-ACC-SW1(config-if-range)#switchport mode access
	B1-ACC-SW1(config-if-range)#switchport access vlan 20
	B1-ACC-SW1(config-if-range)#ip dhcp snooping limit rate 10
	B1-ACC-SW1(config-if-range)#switchport port-security
	B1-ACC-SW1(config-if-range)#switchport port-security maximum 1
	B1-ACC-SW1(config-if-range)#switchport port-security mac-address sticky
	B1-ACC-SW1(config-if-range)#switchport port-security violation restrict

	Configuration
	Configuration
8	Disable CDP
	B1-ACC-SW1(config)#ip dhcp snooping B1-ACC-SW1(config)#ip dhcp snooping vlan 15,20,30,40,50,60,70,80,90 B1-ACC-SW1(config)#ip arp inspection vlan 15,20,30,40,50,60,70,80,90 B1-ACC-SW1(config)#interface range g0/1,g0/2,f0/24 B1-ACC-SW1(config-if-range)#ip dhcp snooping trust B1-ACC-SW1(config-if-range)#ip arp inspection trust
7	DHCP Snooping & Dynamic Arp Inspection
	Configuration B1-ACC-SW1(config)#service timestamps log datetime msec B1-ACC-SW1(config)#logging 10.10.0.4
6	Sys-logs
	Configuration B1-ACC-SW1(config-if)#int vlan 200 B1-ACC-SW1(config)#ip default-gateway 192.168.200.1 B1-ACC-SW1(config-if)#ip address 192.168.200.3 255.255.255.248
5	Interfaces IP Addresses
	B1-ACC-SW1(config)#int range fastEthernet 0/15-23 B1-ACC-SW1(config-if-range)#shutdown B1-ACC-SW1(config-if-range)#switchport mode access B1-ACC-SW1(config-if-range)#switchport access vlan 999
	B1-ACC-SW1(config)#int range fa0/5,fa0/10 B1-ACC-SW1(config)#no switchport voice vlan B1-ACC-SW1(config-if-range)#switchport port-security maximum 1

	B1-ACC-SW1(config)#int range g0/1,g0/2 B1-ACC-SW1(config-if)#no cdp enable
9	AAA
	Configuration
	B1-ACC-SW1(config)#enable secret level 15 depi
	B1-ACC-SW1(config)#username DEPI privilege 15 secret 123
	B1-ACC-SW1(config)#aaa new-model
	B1-ACC-SW1(config)#tacacs-server host 10.10.0.4 key DEPI
	B1-ACC-SW1(config)#aaa authentication login default group tacacs+ local
	B1-ACC-SW1(config)#aaa authorization exec default group tacacs+ local
	B1-ACC-SW1(config)#aaa accounting exec default start-stop group tacacs+
	B1-ACC-SW1(config)#ip domain-name B1-ACC-SW1.depi
	B1-ACC-SW1(config)#crypto key generate rsa general-keys modulus 1024
	B1-ACC-SW1(config)#ip ssh version 2
	B1-ACC-SW1(config)#line vty 0 2
	B1-ACC-SW1(config-line)#login authentication default
	B1-ACC-SW1(config-line)#transport input ssh

B1-ACC-SW2

No	Description
1	Trunking & Access Interfaces

	Configuration
	B1-ACC-SW2(config)#interface range GigabitEthernet0/1,GigabitEthernet0/2 B1-ACC-SW2(config-if-range)#switchport mode trunk B1-ACC-SW2(config-if-range)#switchport trunk native vlan 99
	B1-ACC-SW2(config)#int fa0/24 B1-ACC-SW2(config-if)#switchport mode B1-ACC-SW2(config-if)#switchport access vlan 50
2	VTP
	Configuration
	B1-ACC-SW2(config)#vtp version 2 B1-ACC-SW2(config)#vtp domain DEPI B1-ACC-SW2(config)#vtp password 123 B1-ACC-SW2(config)#vtp mode client
3	STP & Portfast
	Configuration
	B1-ACC-SW2(config)#spanning-tree mode rapid-pvst B1-ACC-SW2(config)#spanning-tree portfast default B1-ACC-SW2(config)#spanning-tree portfast bpduguard default
4	Port Security & Assign Vlan & Voice Vlan
	Configuration
	B1-ACC-SW2(config)#int range fa0/1-5 B1-ACC-SW2(config-if-range)#switchport mode access B1-ACC-SW2(config-if-range)#switchport access vlan 60 B1-ACC-SW2(config-if-range)#switchport voice vlan 40 B1-ACC-SW2(config-if-range)#ip dhcp snooping limit rate 10 B1-ACC-SW2(config-if-range)#switchport port-security B1-ACC-SW2(config-if-range)#switchport port-security maximum 2 B1-ACC-SW2(config-if-range)#switchport port-security mac-address sticky B1-ACC-SW2(config-if-range)#switchport port-security violation restrict
	91

	B1-ACC-SW2(config)#interface range fa0/6-8
	B1-ACC-SW2(config-if-range)#switchport mode access
	B1-ACC-SW2(config-if-range)#switchport access vlan 30
	B1-ACC-SW2(config-if-range)#switchport voice vlan 40
	B1-ACC-SW1(config-if-range)#ip dhcp snooping limit rate 10
	B1-ACC-SW2(config-if-range)#switchport port-security
	B1-ACC-SW2(config-if-range)#switchport port-security maximum 2
	B1-ACC-SW2(config-if-range)#switchport port-security mac-address sticky
	B1-ACC-SW2(config-if-range)#switchport port-security violation restrict
	B1-ACC-SW2(config)#int range fa0/1,fa0/6
	B1-ACC-SW2(config-if-range)#switchport port-security maximum 1
	B1-ACC-SW2(config-if)#no switchport voice vlan
	DI //CC 3W2(coming il/imo switchport voice vidii
	B1-ACC-SW2(config)#int range fastEthernet 0/9-23
	B1-ACC-SW2(config-if-range)#shutdown
	B1-ACC-SW2(config-if-range)#switchport mode access
	B1-ACC-SW2(config-if-range)#switchport access vlan 999
5	Interfaces IP Addresses
	Configuration
	Configuration
	B1-ACC-SW2(config)#ip default-gateway 192.168.200.1
	B1-ACC-SW2(config-if)#int vlan 200
	B1-ACC-SW2(config-if)#ip address 192.168.200.5 255.255.258.248
	, , , ,
6	Sys-logs
	Configuration
	P1 ACC CM/2/config/Hoom in time estamana log detetime a mass
	B1-ACC-SW2(config)#service timestamps log datetime msec
	B1-ACC-SW2(config)#logging 10.10.0.3
7	DHCP Snooping & Dynamic Arp Inspection
_	
	Configuration
	B1-ACC-SW2(config)#ip dhcp snooping

	B1-ACC-SW2(config)#ip dhcp snooping vlan 15,20,30,40,50,60,70,80,90 B1-ACC-SW2(config)#ip arp inspection vlan 15,20,30,40,50,60,70,80,90 B1-ACC-SW2(config)#interface range g0/1,g0/2,f0/24 B1-ACC-SW2(config-if-range)#ip dhcp snooping trust B1-ACC-SW2(config-if-range)#ip arp inspection trust
8	Disable CDP
	Configuration
	B1-ACC-SW2(config)#int range g0/1,g0/2 B1-ACC-SW2(config-if)#no cdp enable
9	AAA
	Configuration
	B1-ACC-SW2(config)#enable secret level 15 depi B1-ACC-SW2(config)#username DEPI privilege 15 secret 123
	B1-ACC-SW2(config)#aaa new-model
	B1-ACC-SW2(config)#tacacs-server host 10.10.0.4 key DEPI B1-ACC-SW2(config)#aaa authentication login default group tacacs+ local
	B1-ACC-SW2(config)#aaa authorization exec default group tacacs+ local B1-ACC-SW2(config)#aaa accounting exec default start-stop group tacacs+
	B1-ACC-SW2(config)#ip domain-name B1-ACC-SW2.depi
	B1-ACC-SW2(config)#crypto key generate rsa general-keys modulus 1024 B1-ACC-SW2(config)#ip ssh version 2
	B1-ACC-SW2(config)#line vty 0 2 B1-ACC-SW2(config-line)#login authentication default

B1-ACC-SW3

No	Description

1	Trunking & Access Interfaces
	Configuration B B1-ACC-SW3(config)#interface GigabitEthernet0/1 B1-ACC-SW3(config-if)#switchport mode trunk B1-ACC-SW2(config-if)#switchport trunk native vlan 99 B1-ACC-SW3(config)#interface GigabitEthernet0/2 B1-ACC-SW3(config-if)#switchport mode trunk B1-ACC-SW3(config-if)#switchport trunk native vlan 99
2	VTP
	Configuration B1-ACC-SW3(config)#vtp version 2 B1-ACC-SW3(config)#vtp domain DEPI B1-ACC-SW3(config)#vtp password 123 B1-ACC-SW3(config)#vtp mode client
3	STP & Portfast
	Configuration B1-ACC-SW3(config)#spanning-tree mode rapid-pvst B1-ACC-SW3(config)#spanning-tree portfast default B1-ACC-SW3(config)#spanning-tree portfast bpduguard default
4	Port Security & Assign Vlan & Voice Vlan
	Configuration
	B1-ACC-SW3(config)#int range fastEthernet 0/1-2 B1-ACC-SW3(config-if-range)#switchport mode access B1-ACC-SW3(config-if-range)#switchport access vlan 90 B1-ACC-SW3(config-if-range)#switchport voice vlan 40 B1-ACC-SW3(config-if-range)#ip dhcp snooping limit rate 10 B1-ACC-SW3(config-if-range)#switchport port-security B1-ACC-SW3(config-if-range)#switchport port-security maximum 2

	Configuration
7	DHCP Snooping & Dynamic Arp Inspection
	Configuration B1-ACC-SW3(config)#service timestamps log datetime msec B1-ACC-SW3(config)#logging 10.10.0.3
6	Sys-logs
	Configuration B1-ACC-SW3(config)#ip default-gateway 192.168.200.1 B1-ACC-SW3(config-if)#int vlan 200 B1-ACC-SW3(config-if)#ip address 192.168.200.6 255.255.255.248
5	Interfaces IP Addresses
	B1-ACC-SW3(config-if-range)#switchport port-security mac-address sticky B1-ACC-SW3(config-if-range)#switchport port-security violation restrict B1-ACC-SW3(config)#int range fastEthernet 0/6-24 B1-ACC-SW3(config-if-range)#shutdown B1-ACC-SW3(config-if-range)#switchport mode access B1-ACC-SW3(config-if-range)#switchport access vlan 999
	B1-ACC-SW3(config)#int range fastEthernet 0/3-5 B1-ACC-SW3(config-if-range)#switchport mode access B1-ACC-SW3(config-if-range)#switchport access vlan 15 B1-ACC-SW3(config-if-range)#switchport voice vlan 40 B1-ACC-SW3(config-if-range)#ip dhcp snooping limit rate 10 B1-ACC-SW3(config-if-range)#switchport port-security B1-ACC-SW3(config-if-range)#switchport port-security maximum 2
	B1-ACC-SW3(config-if-range)#switchport port-security mac-address sticky B1-ACC-SW3(config-if-range)#switchport port-security violation restrict

	B1-ACC-SW3(config)#ip dhcp snooping B1-ACC-SW3(config)#ip dhcp snooping vlan 15,20,30,40,50,60,70,80,90 B1-ACC-SW3(config)#ip arp inspection vlan 15,20,30,40,50,60,70,80,90 B1-ACC-SW3(config)#interface range g0/1,g0/2 B1-ACC-SW3(config-if-range)#ip dhcp snooping trust B1-ACC-SW3(config-if-range)#ip arp inspection trust
8	Disable CDP
	Configuration
	B1-ACC-SW3(config)#int range g0/1,g0/2 B1-ACC-SW3(config-if)#no cdp enable
9	AAA
	Configuration
	B1-ACC-SW3(config)#enable secret level 15 depi B1-ACC-SW3(config)#username DEPI privilege 15 secret 123
	B1-ACC-SW3(config)#aaa new-model
	B1-ACC-SW3(config)#tacacs-server host 10.10.0.4 key DEPI B1-ACC-SW3(config)#aaa authentication login default group tacacs+ local
	B1-ACC-SW3(config)#aaa authorization exec default group tacacs+ local
	B1-ACC-SW3(config)#aaa accounting exec default start-stop group tacacs+
	B1-ACC-SW3(config)#ip domain-name B1-ACC-SW3.depi
	B1-ACC-SW3(config)#crypto key generate rsa general-keys modulus 1024 B1-ACC-SW3(config)#ip ssh version 2
	B1-ACC-SW3(config)#line vty 0 2
	B1-ACC-SW3(config-line)#login authentication default
	B1-ACC-SW3(config-line)#transport input ssh