Load Balancing with NGINX Cheat Sheet

On the back end web servers, run the following commands to install NGINX:

```
sudo apt-get install -y nginx
uname -n | sudo tee /usr/share/nginx/html/index.html
```

On the load balancer, run the follow commands:

```
sudo apt-get install -y nginx
```

Use the following as the contents of /etc/nginx/sites-available/default:

```
upstream web backend {
     # Uncomment for the IP Hashing load balancing method:
     # ip hash;
     # Uncomment for the Least Connected load balancing method:
     # least conn;
     # Replace the IP addresses with the IP addresses
     # (or host names) of your back end web servers.
     # Examples:
     # server www1.example.com:8080;
     # server 192.168.1.100;
     server 10.11.12.51;
     server 10.11.12.52;
}
server {
     listen 80;
     location / {
     proxy set header X-Forwarded-For $proxy add x forwarded for;
     proxy pass http://web backend;
}
```

Make NGINX read the new configuration by running the following command:

```
sudo service nginx reload
```