ICON Namelist Overview

September 18, 2018

Contents

1.	ICON Namelists	3
	1.1. Scripts, Namelist files and Programs	
	1.2. Namelist parameters	4
_		
2.	Namelist parameters defining the atmospheric model	4
	2.1. assimilation_nml	
	2.2. coupling_mode_nml	
	2.3. diffusion_nml	
	2.4. dynamics_nml	
	2.5. echam_cld_nml	
	2.6. echam_cnv_nml	
	2.7. echam_gwd_nml	
	2.8. echam_phy_nml	12
	2.9. echam_rad_nml	13
	2.10. echam_sso_nml	16
	2.11. echam_vdf_nml	17
	2.12. ensemble_pert_nml	17
	2.13. gribout_nml	18
	2.14. grid_nml	20
	2.15. gridref nml	22
	2.16. ha_dyn_nml	23
	2.17. initicon_nml	24
	2.18. interpol_nml	28
	2.19. io_nml	29
	2.19.1. Restart read/write mode:	31
	2.20. les nml (parameters for LES turbulence scheme; valid for inwp turb=5)	32
	2.21. limarea nml (Scope: 1 limited area=.TRUE. in grid nml)	33
	2.22. lnd nml	
	2.23. ls forcing nml (parameters for large-scale forcing; valid for torus geometry)	
	2.24. master nml	
	2.25. master model nml (repeated for each model)	38

В.	. Changes incompatible with former versions of the model code	85
Α.	Arithmetic expression evaluation A.1. Examples for arithmetic expressions A.2. Expression syntax A.2.1. List of functions A.2.2. List of operators A.2.3. List of available constants A.3. Usage with Fortran A.3.1. Fortran examples A.3.2. Error handling A.4. Remarks	83 83 84 84 84 84
	Compile flag for mixed precision Arithmetic expression evaluation	82
	Information on vertical level distribution	82
6	External packages	82
5.	External data 5.1. extpar nml (Scope: itopo=1 in run nml)	81 81
4.	Namelist parameters for testcases (NAMELIST_ICON) 4.1. ha_testcase_nml (Scope: ltestcase=.TRUE. and iequations=[0,1,2] in run_nml)	
3.	Ocean-specific namelist parameters 3.1. ocean_physics_nml 3.2. sea_ice_nml (relevant if run_nml/iforcing=2 (ECHAM))	
	2.26. master_time_control_nml 2.27. meteogram_output_nml 2.28. nonhydrostatic_nml (relevant if run_nml:iequations=3) 2.29. nwp_phy_nml 2.30. nwp_tuning_nml 2.31. output_nml (relevant if run_nml/output='nml') 2.32. parallel_nml 2.33. psrad_nml 2.34. radiation_nml 2.35. run_nml 2.35. run_nml 2.36. sleve_nml (relevant if nonhydrostatic_nml:ivctype=2) 2.37. synsat_nml 2.38. time_nml 2.39. transport_nml (used if run_nml/ltransport=.TRUE.) 2.40. turbdiff_nml	39 40 43 45 47 55 57 61 64 64 65

1. ICON Namelists

1.1. Scripts, Namelist files and Programs

Run scripts starting the programs for the models are stored in run/. These scripts write namelist files containing the specified Fortran namelists. Programs are stored in < icon home>/build/<architecture>/bin/.

Table 1: Namelist files

Namelist file	Purpose	Made by script	Used by program
NAMELIST_GRAPH	Generate graphs	create_global_grids.run	grid_command
NAMELIST_GRID	Generate grids	create_global_grids.run	grid _command
NAMELIST_GRIDREF	Gen. nested domains	create_global_grids.run	$grid_command$
NAMELIST_ICON	Run ICON models	exp. <name>.run</name>	$control_model$

1.2. Namelist parameters

The following subsections tabulate all available Fortran namelist parameters by name, type, default value, unit, description, and scope:

- Type refers to the type of the Fortran variable, in which the value is stored: I=INTEGER, L=LOGICAL, R=REAL, C=character string
- Default is the preset value, if defined, that is assigned to this parameter within the programs.
- *Unit* shows the unit of the control parameter, where applicable.
- Description explains in a few words the purpose of the parameter.
- Scope explains under which conditions the namelist parameter has any effect, if its scope is restricted to specific settings of other namelist parameters.

Information on the file, where the namelist is defined and used, is given at the end of each table.

2. Namelist parameters defining the atmospheric model

Namelist parameters for the ICON models are organized in several thematic Fortran namelists controling the experiment, and the properties of dynamics, transport, physics etc.

2.1. assimilation nml

The main switch for the Latent heat nudging scheme is called ldass_lhn and has to be set in run_nml.

Type	Default	Unit	Description	Scope
I	-9999	s	time in seconds when LHN is applied for the	$run_nml:ldass_lhn = .true.$
			first time	
I	-9999	S	time in seconds when LHN is applied for the last	$run_nml:ldass_lhn = .true.$
			time	
R	1.0		Nudging coefficient of adding the increments	
R	2.0		Upper limit of the scaling factor of the	
			temperature profile.	
R	0.5		Lower limit of the scaling factor of the	
			temperature profile.	
L	.TRUE.		Apply all scaling factors as logarithmic values	fac_lhn_down, fac_lhn_up,
				fac_lhn_artif
R	0.1/3600.	$\mathrm{mm/s}$	Minimal value of precipitation rate, either of	
			model or radar. LHN will be applied first for	
			precipitation above it.	
R	1.0		Value to determine, at which model time step a	
L	.TRUE.			
			<u> </u>	
			to displacement of model surface precipitation.	
			rate is used as reference.	
	I R R R R L R	I -9999 I -9999 R 1.0 R 2.0 R 0.5 L .TRUE. R 0.1/3600.	I -9999 s I -9999 s R 1.0 R 2.0 R 0.5 L .TRUE. R 0.1/3600. mm/s R 1.0	I -9999 s time in seconds when LHN is applied for the first time I -9999 s time in seconds when LHN is applied for the last time R 1.0 Nudging coefficient of adding the increments Upper limit of the scaling factor of the temperature profile. Lower limit of the scaling factor of the temperature profile. Lower limit of the scaling factor of the temperature profile. Apply all scaling factors as logarithmic values R 0.1/3600. mm/s Minimal value of precipitation rate, either of model or radar. LHN will be applied first for precipitation above it. Value to determine, at which model time step a fading out of the increments might start. Use a vertical average of precipitation fluxes as reference to compare with radar observed precipitation, to avoid severe overestimation due to displacement of model surface precipitation. If set .FALSE. the model surface precipitation

Parameter	Type	Default	Unit	Description	Scope
rqrsgmax	R	1.0		This value determines the height of the vertical averaging, to obtain the reference precipitation	$lhn_qrs = .TRUE.$
				rate	
				It is the model layer where the quotion of the	
				maximal precipitation flux occurred for the first	
11 1 12	т	(DDIII)		time.	
lhn_hum_adj	L	.TRUE.		Apply an increment of specific humidity with	
				respect to the estimated temperature increment to maintain the relative humidty	
lhn no ttend	L	.FALSE.		Only apply moisture increments. Temperature	lhn hum adj=.TRUE.
		iiiibob.		increments will only be used for calculation of	min_nam_aaj=.11t02.
				moisture increments	
lhn incloud	ho L	.TRUE.		Apply increments only in model layers where the	lhn artif only=.FALSE.
_				underlying latent heat release of the model is	,
				positive.	
lhn_limit	L	.TRUE.		Limitation of temperature increments	abs_lhn_lim
abs_lhn_lim	R	50./3600.	K/s	Lower and upper limit for temperature	$lhn_limit = .TRUE.$
	_			increments to be added.	
lhn_filt	L	.TRUE.		Vertical smoothing of the profile of temperature	
111	т	.FALSE.		increments	11 1
lhn_relax	L	.FALSE.		Horizontal smoothing of radar data but also of incorporated model fields	nlhn_relax
nlhn relax	Т	2	grid	Number of horizontal grid point, where	ln relax = .TRUE.
mm_relax			points	smoothing is applied.	IIII_Telax = .TROE.
lhn artif	L	.TRUE.	pomes	Apply an artificial temperature profile to	fac lhn artif, tt artif max,
		11102		estimate increments at model grid points	zlev artif max, std artif ma
				without significant precipitation (determined by	/
				fac_lhn_artif).	
fac_lhn_artif	R	5.0		Value of the ratio of radar to model precipitation	lhn_artif=.TRUE.
				rate, from which an artificial temperature profile	
				is applied	
lhn_artif_only	$\mid L$.FALSE.		Scaling the artificial temperature profile instead	tt_artif_max,
				of local model profile of latent heat release for	zlev_artif_max,
				calculation the increments at any model grid	std_artif_max
				point. The scaling factor is still be determined by the	
				ratio of observed to modelled precipitation rate.	
tt artif max	\mathbb{R}	0.0015	K	Maximal temperature of Gaussian shaped	lhn artif, lhn artif only
		0.0010		function used a artificial temperature profile.	
zlev_artif_max	R	1000.0	m	Height of maximum of Gaussian shaped function	lhn_artif, lhn_artif_only
				used a artificial temperature profile.	
std_artif_max	R	4.0	m	Parameter defining width of Gaussian shaped	lhn_artif, lhn_artif_only
				function used a artificial temperature profile.	
$nlhnverif_start$	I	-9999	s	time in seconds when online verification within	$run_nml:ldass_lhn = .true.$
				LHN is active for the first time	

Parameter	Type	Default	Unit	Description	Scope
nlhnverif_end	I	-9999	S	time in seconds when online verification within	$run_nml:ldass_lhn = .true.$
				LHN is active for the last time	
lhn_diag	L	.FALSE.		Enable a extensive diagnostic output, writing	
				into file lhn.log.	
				lhn_diag is set .TRUE. automatically, when	
				online verification is active.	
lhn_dt_obs	R	300.0	s	Frequency of the radar observations	
radar_in	C	·./'		Path where the radar data file is expected.	
radardata_file(:)	C			Name of the radar data file. This might be	
	(n_dom)			either in GRIB2 or in NetCDF (recommended).	
lhn_black	L	.FALSE.		Apply a blacklist information in the radar data	
				obtained by comparison against satelite clound	
				information	
blacklist_file(:)	C			Name of blacklist file, containing a mask	lhn_black=.TRUE.
	(n_dom)			concerning the quality of the radar data.	
				Value 1: good quality	
				Value 0: bad quality	
				This might be either in GRIB2 or in NetCDF	
				(recommended).	
lhn_bright	L	.FALSE.		Apply a model intern bright band detection to	
				avoid strong overestimation due to uncertain	
				radar observations.	
height_file(:)	C			Name of file containing the height of the lowest	lhn_bright=.TRUE.
	(n_dom)			scan for each possible radar station within the	
				given radar composite.	
				This file is required, when applying bright band	
				detection.	
				This might be either in GRIB2 or in NetCDF	
	_			(recommended).	
nradar		200		Maximal number of radar station contained	lhn_bright=.TRUE.
	(n_dom)			within height_file	

Defined and used in: src/namelists/mo_assimilation_nml.f90

2.2. coupling_mode_nml

Parameter	Type	Default	Unit	Description	Scope
coupled_mode	L	.FALSE.		.TRUE.: if yac coupling routines have to be	
				called	

Defined and used in: src/namelists/mo_coupling_nml.f90

2.3. diffusion_nml

Parameter	Type	Default	Unit	Description	Scope
lhdiff_temp	L	.TRUE.		Diffusion on the temperature field	
lhdiff_vn	L	.TRUE.		Diffusion on the horizontal wind field	
lhdiff w	L	.TRUE.		Diffusion on the vertical wind field	
hdiff_order	I	4 (hydro)		Order of ∇ operator for diffusion:	Options 2, 24 and 42 are
_		5 (NH)		-1: no diffusion	allowed only in the hydrostatic
				2: ∇^2 diffusion	atm model (iequations = 1 or 2
				3: Smagorinsky ∇^2 diffusion	in dynamics nml).
				4: ∇^4 diffusion	_ /
				5: Smagorinsky ∇^2 diffusion combined with ∇^4	
				background diffusion as specified via	
				hdiff efdt ratio	
				$24 \text{ or } 42: \nabla 2 \text{ diffusion from model top to a}$	
				certain level (cf. k2 pres max and	
				k2 klev max below); ∇^4 for the lower levels.	
lsmag 3d	L	.FALSE.		.TRUE.: Use 3D Smagorinsky formulation for	hdiff order=3 or 5;
				computing the horizontal diffusion coefficient	itype_vn_diffu=1
				(recommended at mesh sizes finer than 1 km if	
				the LES turbulence scheme is not used)	
itype vn diffu	I	1		Reconstruction method used for Smagorinsky	iequations=3, hdiff order=3
				diffusion:	or 5
				1: u/v reconstruction at vertices only	
				2: u/v reconstruction at cells and vertices	
itype t diffu	I	2		Discretization of temperature diffusion:	iequations=3, hdiff order=3
				1: $K_h \nabla^2 T$	or 5
				$2: \nabla \cdot (K_h \nabla T)$	
k2 pres max	R	-99.	Pa	Pressure level above which ∇^2 diffusion is	hdiff order $= 24$ or 42 , and
				applied.	$\frac{-}{\text{dynamics nml:iequations}} = 1$
					or 2.
k2 klev max	I	0		Index of the vertical level till which (from the	$hdiff_order = 24 \text{ or } 42, \text{ and}$
				model top) ∇^2 diffusion is applied. If a positive	$\frac{-}{\text{dynamics}_\text{nml:iequations}} = 1$
				value is specified for k2 pres max,	or 2.
				k2 klev max is reset accordingly during the	
				initialization of a model run.	
hdiff efdt ratio	R	1.0 (hydro)		ratio of e-folding time to time step (or 2* time	
		36.0 (NH)		step when using a 3 time level time stepping	
				scheme) (for triangular NH model, values above	
				30 are recommended when using hdiff_order=5)	
hdiff w efdt ratio	R	15.0		ratio of e-folding time to time step for diffusion	iequations=3
				on vertical wind speed	
hdiff min efdt ratio	R	1.0		minimum value of hdiff efdt ratio near model	iequations=3 .AND.
				top	hdiff order=4

Parameter	Type	Default	Unit	Description	Scope
hdiff_tv_ratio	R	1.0		Ratio of diffusion coefficients for temperature	
				and normal wind: $T:v_n$	
hdiff_multfac	R	1.0		Multiplication factor of normalized diffusion	n_dom>1
				coefficient for nested domains	
hdiff_smag_fac	R	0.15 (hydro)		Scaling factor for Smagorinsky diffusion	iequations=3
		0.015 (NH)			

Defined and used in: src/namelists/mo_diffusion_nml.f90

2.4. dynamics nml

This namelist is relevant if run nml:ldynamics=.TRUE.

Parameter	Type	Default	Unit	Description	Scope
iequations	I	3		Equations and prognostic variables. Use positive	
				indices for the atmosphere and negative indices	
				for the ocean.	
				0: shallow water model	
				1: hydrostatic atmosphere, T	
				2: hydrostatic atm., θ -dp	
				3: non-hydrostatic atmosphere	
				-1: hydrostatic ocean	
idiv_method	I	1		Method for divergence computation:	
				1: Standard Gaussian integral.	
				Hydrostatic atm. model: for unaveraged normal	
				components	
				Non-hydrostatic atm. model: for averaged	
				normal components	
				2: bilinear averaging of divergence	
divavg_cntrwgt	R	0.5		Weight of central cell for divergence averaging	$idiv_method=2$
lcoriolis	L	.TRUE.		Coriolis force	
sw_ref_height	R	$0.9*\ 2.94e4/g$	m	Reference height of shallow water model used for	
				linearization in the semi-implicit time stepping	
				scheme	

Defined and used in: $src/namelists/mo_dynamics_nml.f90$

2.5. echam cld nml

The parameterization of cloud microphysics for the ECHAM physics is configured by a data structure $echam_cld_config(jg=1:ndom)\% < param>$, which is a 1-dimensional array extending over all domains. The structure contains parameters providing control over the parametrized effects:

Parameter	Type	Default	Unit	Description	Scope
$echam_cld_config(jg)\%$	R	1.0e-7	kg/kg	cloud water and ice minimum mass mixing ratio	echam_phy_config(jg)%
ccwmin				for cover>0	dt _cld $> 0.000\mathrm{s}$

Parameter	Type	Default	Unit	Description	Scope
$echam_cld_config(jg)\%$	R	1.0e-12	kg/kg	cloud water/ice minimum for microphysical	echam_phy_config(jg)%
cqtmin				processes	$ m dt_cld > 0.000s$
echam_cld_config(jg)%	R	Tmelt-35 =	K	maximum temperature for homogeneous freezing	echam_phy_config(jg)%
cthomi		238.15			dt cld > 0.000s
echam_cld_config(jg)%	R	5.0e-6	kg/kg	minimum in-cloud water mass mixing ratio in	echam_phy_config(jg)%
csecfrl			3/0	mixed phase clouds	$\frac{\text{dt cld} > 0.000s}{\text{dt cld} > 0.000s}$
echam_cld_config(jg)%	R	15.		coefficient of autoconversion of cloud droplets to	echam_phy_config(jg)%
ccraut		10.		rain	$\begin{array}{cccccccccccccccccccccccccccccccccccc$
echam cld config(jg)%	R	6.		coefficient of accretion of cloud droplets by	echam_phy_config(jg)%
	11	0.			
ccracl	D	10		falling rain	$dt_{cld} > 0.000s$
echam_cld_config(jg)%	R	10.		coefficient of local rainwater production by	echam_phy_config(jg)%
cauloc	_			autoconversion	$dt_{cld} > 0.000s$
$echam_cld_config(jg)\%$	R	0.0		minimum for cauloc* $dz/5000$	echam_phy_config(jg)%
clmin					$ m dt_cld > 0.000s$
$echam_cld_config(jg)\%$	R	0.5		maximum for cauloc* $dz/5000$	echam_phy_config(jg)%
clmax					$ m dt_cld > 0.000s$
echam cld config(jg)%	R	2.5		coefficient of sedimentation velocity of cloud ice	echam phy config(jg)%
cvtfall				·	dt cld > 0.000s
echam cld config(jg)%	R	10.	1.e-6 m	min effective radius for ice cloud	echam_phy_config(jg)%
ceffmin					$\frac{\text{dt cld} > 0.000s}{\text{dt cld} > 0.000s}$
echam cld config(jg)%	R	150.	1.e-6 m	max effective radius for ice cloud	echam phy config(jg)%
ceffmax	16	100.	1.0-0 III	max encoure radius for fee cloud	$\begin{array}{c} \text{dechain_phy_colling(jg)} \\ \text{dt. cld} > 0.000 \text{s} \end{array}$
echam cld config(jg)%	R	500.	kg/m2	density of cloud ice	_
crhoi	l n	500.	m kg/m3	density of cloud ice	echam_phy_config(jg)%
	D	100	l-m / 2	hulls density of anom	$dt_cld > 0.000s$
echam_cld_config(jg)%	R	100.	m kg/m3	bulk density of snow	echam_phy_config(jg)%
crhosno					$dt_{-}cld > 0.000s$
$echam_cld_config(jg)\%$	R	95.0		coefficient of autoconversion of cloud ice to snow	echam_phy_config(jg)%
ccsaut					$ m dt_cld > 0.000s$
$echam_cld_config(jg)\%$	R	0.1		coefficient of accretion of cloud droplets by	echam_phy_config(jg) $\%$
ccsacl				falling snow	$ m dt_cld > 0.000s$
$echam_cld_config(jg)\%$	R	defval	1e6/m3	cloud droplet number concentration over land, p	echam_phy_config(jg)%
cn1lnd				<= 100 hPa	dt cld > 0.000s
echam cld config(jg)%	R	defval	1e6/m3	cloud droplet number concentration over land, p	echam_phy_config(jg)%
cn2lnd			-/	>= 800 hPa	$dt \ cld > 0.000s$
echam_cld_config(jg)%	R	defval	$1\mathrm{e}6/\mathrm{m}3$	cloud droplet number concentration over sea, p	echam phy config(jg)%
cn1sea		401.01	100/1110	<= 100 hPa	$\frac{\text{centur_priy_coming(jg)}}{\text{dt cld}} > 0.000\text{s}$
echam cld config(jg)%	R	defval	$1\mathrm{e}6/\mathrm{m}3$	cloud droplet number concentration over sea, p	echam_phy_config(jg)%
cn2sea	16	ucivai	100/1119	>= 800 hPa	$\frac{\text{echan} \cdot \text{phy} \cdot \text{comg(jg)}}{\text{dt} \cdot \text{cld}} > 0.000 \text{s}$
	D	0.0		>= 800 nra ice cloud inhomogeneity factor	_
echam_cld_config(jg)%	R	0.8		ice cloud innomogeneity factor	echam_phy_config(jg)%
cinhomi					$dt_{-}cld > 0.000s$
echam_cld_config(jg)%	R	0.8		liquid cloud inhomogeneity factor, ktype = 0 =	echam_phy_config(jg)%
cinhoml1				stratiform clouds	$dt_{cld} > 0.000s$
$\operatorname{echam_cld_config(jg)}\%$	R	0.4		liquid cloud inhomogeneity factor, ktype $=4=$	echam_phy_config(jg)%
cinhoml2				shallow conv. (cf. clwprat)	dt cld > 0.000s

Parameter	Type	Default	Unit	Description	Scope
echam_cld_config(jg)%	R	0.8		liquid cloud inhomogeneity factor, ktype $= 1 =$	echam_phy_config(jg)%
cinhoml3				deep convection and $ktype = 2 = shallow conv.$	$ m dt_cld > 0.000s$
				(cf. clwprat) and ktype $= 3 = \text{mid-level conv.}$	
echam_cld_config(jg)%	R	4.0		critical ratio of cloud liq.+ice paths below and	echam_phy_config(jg)%
clwprat				above the top of shallow convection; for ratio >	$ m dt_cld > 0.000s$
				clwprat -> change ktype from 2 to 4	
$echam_cld_config(jg)\%$	R	0.968		critical relative humidity at surface	echam_phy_config(jg)%
crs					$ m dt_cld > 0.000s$
$echam_cld_config(jg)\%$	R	0.8		critical relative humidity aloft	echam_phy_config(jg)%
crt					$ m dt_cld > 0.000s$
$echam_cld_config(jg)\%$	I	2		transition parameter for critical relative	echam_phy_config(jg)%
nex				humidity profile	$ m dt_cld > 0.000s$
$echam_cld_config(jg)\%$	I	40		index of highest level for search of top level of	echam_phy_config(jg)%
jbmin				inversion layer over sea (ca. 2 km)	$ m dt_cld > 0.000s$
echam_cld_config(jg)%	I	45		index of bottom level of inversion layer over sea	echam_phy_config(jg)%
jbmax					$ m dt_cld > 0.000s$
$echam_cld_config(jg)\%$	R	0.25		fraction of dry adiabatic lapse rate for search of	echam_phy_config(jg)%
cinv				top level of inversion layer over sea	$ m dt_cld > 0.000s$
echam_cld_config(jg)%	R	0.7		minimum effective saturation for cloud cover	echam_phy_config(jg)%
csatsc				below an invesion layer over sea	$ m dt_cld > 0.000s$
echam_cld_config(jg)%	I	13		index of highest level for tropopause calculation	echam_phy_config(jg)%
ncctop					$ m dt_cld > 0.000s$
echam_cld_config(jg)%	I	35		index of lowest level for tropopause calculation	echam_phy_config(jg)%
nccbot					$ m dt_cld > 0.000s$

2.6. echam_cnv_nml

The parameterization of convection for the ECHAM physics is configured by a data structure $echam_cnv_config(jg=1:ndom)\% < param>$, which is a 1-dimensional array extending over all domains. The structure contains parameters providing control over the parametrized effects:

Parameter	Type	Default	Unit	Description	Scope
$echam_cnv_config(jg)\%$	L	.TRUE.		Switch on penetrative convection.	$echam_phy_config(jg)\%$
lmfpen					$\mathrm{dt_cnv} > 0.000\mathrm{s}$
$echam_cnv_config(jg)\%$	L	.TRUE.		Switch on midlevel convection.	$echam_phy_config(jg)\%$
lmfmid					$\mathrm{dt_cnv} > 0.000\mathrm{s}$
$echam_cnv_config(jg)\%$	L	.TRUE.		Switch on cumulus downdraft.	$echam_phy_config(jg)\%$
lmfdd					$\mathrm{dt_cnv} > 0.000\mathrm{s}$
$echam_cnv_config(jg)\%$	L	.TRUE.		Switch on cumulus friction.	$echam_phy_config(jg)\%$
lmfdudv					$\mathrm{dt_cnv} > 0.000\mathrm{s}$
$echam_cnv_config(jg)\%$	R	2.0e-4		Entrainment rate for midlevel convection.	$echam_phy_config(jg)\%$
entrmid					$\mathrm{dt_cnv} > 0.000\mathrm{s}$
$echam_cnv_config(jg)\%$	R	3.0e-3		Entrainment rate for shallow convection.	$echam_phy_config(jg)\%$
entrscv					$\mathrm{dt_cnv} > 0.000\mathrm{s}$
$echam_cnv_config(jg)\%$	R	2.0e-4		Entrainment rate for penetrative convection.	$echam_phy_config(jg)\%$
entrpen					$\mathrm{dt_cnv} > 0.000\mathrm{s}$

Parameter	Type	Default	Unit	Description	Scope
echam_cnv_config(jg)%	R	4.0e-4		Entrainment rate for cumulus downdrafts.	echam_phy_config(jg)%
entrdd					$dt_{cnv} > 0.000s$
echam_cnv_config(jg)%	R	2.5e-4		Coefficient for determining conversion from	echam_phy_config(jg)%
cprcon				cloud water to rain.	$dt_{cnv} > 0.000s$
echam_cnv_config(jg)%	R	0.2		Fractional convective mass flux across the top of	echam_phy_config(jg)%
cmfctop				cloud.	$dt_{cnv} > 0.000s$
echam_cnv_config(jg)%	R	0.3		Fractional convective mass flux for downdrafts	echam_phy_config(jg)%
cmfdeps				at lfs.	$dt_{cnv} > 0.000s$
echam_cnv_config(jg)%	R	0.02		Minimum excess buoyancy.	echam_phy_config(jg)%
cminbuoy					$dt_{cnv} > 0.000s$
echam_cnv_config(jg)%	R	1.0		Maximum excess buoyancy.	echam_phy_config(jg)%
cmaxbuoy					$dt_{cnv} > 0.000s$
echam_cnv_config(jg)%	R	1.0		Factor for std dev of virtual pot temp.	echam_phy_config(jg)%
cbfac					$dt_{cnv} > 0.000s$
echam_cnv_config(jg)%	R	3.0e-4		Maximum entrainment/detrainment rate.	echam_phy_config(jg)%
centrmax					$dt_{cnv} > 0.000s$
echam_cnv_config(jg)%	R	0	Pa	Minimum pressure thickness of clouds for	echam_phy_config(jg)%
dlev_land				precipitation over land.	$dt_{cnv} > 0.000s$
echam_cnv_config(jg)%	R	0	Pa	Minimum pressure thickness of clouds for	echam_phy_config(jg)%
dlev_ocean				precipitation over ocean.	$ m dt_cnv > 0.000s$
echam_cnv_config(jg)%	R	3600.		Characteristic convective adjustment time scale.	echam_phy_config(jg)%
cmftau					$dt_{cnv} > 0.000s$
echam_cnv_config(jg)%	R	1.0e-10		Minimum massflux value (for safety).	echam_phy_config(jg)%
cmfcmin					$ m dt_cnv > 0.000s$
echam_cnv_config(jg)%	R	1.0		Maximum massflux value for updrafts.	echam_phy_config(jg)%
cmfcmax					$ m dt_cnv > 0.000s$

2.7. echam_gwd_nml

The parameterization of atmospheric gravity waves for the ECHAM physics is configured by a data structure $echam_gwd_config(jg=1:ndom)\% < param>$, which is a 1-dimensional array extending over all domains. The structure contains parameters providing control over the parametrized effects:

Parameter	Type	Default	Unit	Description	Scope
lheatcal	L	.FALSE.		.TRUE.: compute drag, heating rate and	echam_phy_config(jg)%
				diffusion coefficient from the dissipation of	$ m dt_gwd > 0.000s$
				gravity waves	
				.FALSE.: compute drag only	
emiss_lev	I	10		Index of model level, counted from the surface,	echam_phy_config(jg) $\%$
				from which the gravity wave spectra are emitted	$ m dt_gwd > 0.000s$
rmscon	R	0.87	$\mathrm{m/s}$	Root mean square gravity wave wind at the	echam_phy_config(jg) $\%$
				emission level	$ m dt_gwd > 0.000s$
kstar	R	5.0e-5	$1/\mathrm{m}$	Typical gravity wave horizontal wavenumber	$echam_phy_config(jg)\%$
					$ m dt_gwd > 0.000s$
m_min	R	0.0	$1/\mathrm{m}$	Minimum bound in vertical wavenumber	echam_phy_config(jg) $\%$
					$ m dt_gwd > 0.000s$

2.8. echam phy nml

The ECHAM physics is configured by a data structure $echam_phy_config(jg=1:ndom)\%<param>$, which is a 1-dimensional array extending over all domains. The structure contains several parameters providing time control for the atmospheric forcing by the different parameterizations and additional logical switches for controlling the coupling between the parameterizations of the physics and between the dynamics and the physics. Further logical switches control how the atmospheric boundary conditions for the ECHAM physics are determined. Time control parameters are available for the following atmospheric processes:

prc	parameterized process
rad	LW and SW radiation
vdf	vertical diffusion
cnv	cumulus convection
cld	cloud microphysics
gwd	atmospheric gravity wave drag
sso	sub grid scale orographic effects
mox	methane oxidation and water vapor photolysis
car	Cariolle's linearized ozone chemistry
art	ART chemistry

The time control for an atmospheric forcing by a process prc consists of three components, the time interval dt_prc for re-computing the forcing, and the start and end dates and times defining the interval $[sd_prc, ed_prc]$, in which the forcing is either computed, if the date/time coincides with the interval dt_prc , or recycled. Recycling means that the forcing stored from the last computation is used again. Outside of the interval the forcing is set to zero.

If dt_prc is not specified, or an empty string or a string of blanks or an interval of length 0s, e.g. "PT0S" is given, then the forcing is switched off for the entire experiment and the start and end dates and times are irrelevant.

If sd_prc or ed_prc are not specified, or an empty string or a string of blanks are given, then the experiment start date and the experiment stop date are used, respectively. Further the forcing control switch fc_prc can be used to decide if an active process (dt_prc > 0) is used for the integration (fc_prc = 1) or only computed for diagnostic purposes (fc_prc = 0).

Parameter	Type	Default	Unit	Description	Scope
echam_phy_config(jg)%	С	""		This is the time interval in ISO 8601-2004	$run_nml/iforcing = 2$
dt_prc				format at which the forcing by the process <i>prc</i> is computed.	
$echam_phy_config(jg)\%$	C	""		Defines the start date/time in ISO 8601-2004	$run_nml/iforcing = 2$ and
sd_prc				format of the interval [sd_prc,ed_prc], in which	$dt_prc > 0.000s$
				the forcing by the process <i>prc</i> is computed in	
				intervals $dt_prc.$	
echam_phy_config(jg)%	C	""		Defines the end date/time in ISO 8601-2004	$run_nml/iforcing = 2$ and
ed_prc				format of the interval [sd_prc,ed_prc], in which	$dt_prc > 0.000 \mathrm{s}$
				the forcing by the process <i>prc</i> is computed in	
	_			intervals $dt_prc.$	1/10
echam_phy_config(jg)%	1	1		Forcing control for process prc.	$rac{ ext{run_nml/iforcing} = 2 ext{ and}}{ ext{run_nml/iforcing}}$
fc_prc				fc_prc = 0: the forcing of the process is not	$dt_prc > 0.000 \mathrm{s}$
				used in the integration.	
				fc_prc = 1: the forcing of the process is used in	
		DAT OF		the integration.	1/16
echam_phy_config(jg)%	L	.FALSE.		.TRUE. for sea-ice temperature calculation	$run_nml/iforcing = 2$
lice					

Parameter	Type	Default	Unit	Description	Scope
echam_phy_config(jg)%	L	.FALSE.		.TRUE. for mixed layer ocean	$run_nml/iforcing = 2$
lmlo					
echam_phy_config(jg)%	L	.FALSE.		.TRUE. for using the JSBACH land surface	$run_nml/iforcing = 2$
ljsb				model	
echam_phy_config(jg)%	L	.FALSE.		.TRUE. for AMIP boundary conditions	$\operatorname{run_nml/iforcing} = 2$
lamip					

2.9. echam_rad_nml

The input from ECHAM physics to the PSrad scheme is configured by a data structure $echam_rad_config(jg=1:ndom)\% < param>$, which is a 1-dimensional array extending over all domains. The structure contains parameters providing control over the Earth orbit, the computation of the SW incoming flux at the top of the atmosphere and the atmospheric composition:

Parameter	Type	Default	Unit	Description	Scope
echam_rad_config(jg)%	I	0		Selects the spectral solar irradiation (SSI) at 1	echam_phy_config(jg)%
isolrad				AU distance from the sun	$ m dt_rad > 0.000s$
				0: SSI of the SRTM scheme, $TSI = 1368.222$	
				Wm2.	
				1: SSI from an external file containing monthly	
				mean time series	
				2: Average 1844–1856 of the SSI time series	
				provided for CMIP5, $TSI = 1360.875 \text{ W/m2}$	
				3: Average 1979–1988 of the SSI time series	
				provided for CMIP5, $TSI = 1361.371 \text{ W/m2}$	
				4: SSI for RCE-type simulation with diurnal	
				cycle, $TSI = 1069.315 \text{ W/m2}$	
				5: SSI for RCE-type simulation without diurnal	
				cycle, $TSI = 433.3371 \text{ W/m2}$	
				6: Average 1850-1873 of the SSI time series	
				provided for CMIP6, $TSI = 1360.744 \text{ W/m2}$	
echam rad config(jg)%	R	1		Scaling factor for the SSI	echam phy config(jg)%
fsolrad	10	1		Scaling ractor for the SSI	$\begin{array}{c} \text{dt } \text{rad} > 0.000s \end{array}$
echam rad config(jg)%	L	.TRUE.		.TRUE. for the realistic VSOP87 Earth orbit	echam phy config(jg)%
1 orbvsop87				.FALSE. for the Kepler orbit	dt rad > 0.000s
echam_rad_config(jg)%	$ _{\mathrm{R}}$	0.016715		eccentricity of the Kepler orbit	echam phy config(jg)%
cecc				, I	dt rad > 0.000s and
					1 orbvsop87 = .FALSE.
echam rad config(jg)%	R	23.44100	deg	obliquity of the Earth rotation axis on the	echam phy config(jg)%
cobld				Kepler orbit	dt rad > 0.000s and
					$l_{\text{orbvsop}87} = .\text{FALSE}.$
echam_rad_config(jg)%	R	282.7000	deg	longitude of perihelion with respect to vernal	echam_phy_config(jg)%
clonp				equinox on the Kepler orbit	$\mathrm{dt_rad} > 0.000\mathrm{s} \; \mathrm{and}$
					$l_{orbvsop87} = .FALSE.$
		-	•	•	· '

Parameter	Type	Default	Unit	Description	Scope
$echam_rad_config(jg)\%$	L	.FALSE.		.FALSE. for transient VSOP87 Earth orbit	echam_phy_config(jg)%
lyr_perp				.TRUE.: VSOP87 Earth orbit of year yr_perp is	$\mathrm{dt_rad} > 0.000\mathrm{s} \; \mathrm{and}$
				perpertuated	$l_orbvsop87 = .TRUE.$
$echam_rad_config(jg)\%$	L	-99999		year to be used for $lyr_perp = .TRUE$.	$echam_phy_config(jg)\%$
yr_perp					$\mathrm{dt_rad} > 0.000\mathrm{s}$ and
					$l_orbvsop87 = .TRUE.$
$echam_rad_config(jg)\%$	I	0		0: Earth circles on orbit	$echam_phy_config(jg)\%$
nmonth				1-12: Earth orbit position fixed for specified	dt rad > 0.000s
				month	_
echam rad config(jg)%	L	.TRUE.		.TRUE. for diurnal cycle in solar irradiation	echam phy config(jg)%
ldiur				.FALSE. for zonally averaged solar irradiation	dt rad > 0.000s
echam rad config(jg)%	\mid L	.FALSE.		.TRUE. for a horizontally independent solar	_
l_sph_symm_irr				irradiation; .FALSE. for a horizontally resolved	
				solar irradiation	
echam rad config(jg)%	I	1		Selects source for concentration of water vapor,	echam phy config(jg)%
irad h2o				cloud water and cloud ice	dt rad > 0.000s
_				0: set to zero (or epsilon)	_
				1: from tracer	
echam_rad_config(jg)%	Ţ	2		Selects source for concentration of CO2	echam phy config(jg)%
irad_co2		-		0: set to zero (or epsilon)	$\frac{1}{2}$ dt rad > 0.000s and CO2
				1: from tracer	tracer is defined
				2: constant vol. mixing ration set by 'vmr co2'	ordeer is defined
				4: spatially constant, time dependent vol.	
				mixing ratio from file	
echam rad config(jg)%	I	3		Selects source for concentration of CH4	echam phy config(jg)%
irad_ch4				0: set to zero (or epsilon)	$\begin{array}{cccccccccccccccccccccccccccccccccccc$
				2: constant vol. mixing ration set by 'vmr ch4'	dt_1ad > 0.0005
				3: horizontally constant, vertically decaying,	
				with surface vol. mixing ratio set by 'vmr ch4'	
				4: horizontally constant, vertically decaying,	
				time dependent with surface vol. mixing ratio	
				from file	
echam rad config(jg)%	T	3		Selects source for concentration of N2O	echam phy config(jg)%
irad n2o	1	3		0: set to zero (or epsilon)	$\frac{\text{echan_phy_conng(jg)}}{\text{dt rad}} > 0.000s$
11 au_1120				2: constant vol. mixing ration set by 'vmr n2o'	dt_1ad / 0.0005
				3: horizontally constant, vertically decaying,	
				with surface vol. mixing ratio set by 'vmr n2o'	
				4: horizontally constant, vertically decaying,	
				time dependent with surface vol. mixing ratio	
				from file	

Parameter	Type	Default	Unit	Description	Scope
$echam_rad_config(jg)\%$	I	0		Selects source for concentration of O3	echam_phy_config(jg)%
irad_o3				0: set to zero (or epsilon)	$ m dt_rad > 0.000s$
				1: from tracer	
				2: 3-dim concentration, climatological annual	
				cycle, monthly means from an annual file	
				4: 3-dim concentration, constant in time, 1st	
				time slice file	
				8: 3-dim concentration, time dependent,	
				monthly means from yearly files	
echam rad config(jg)%	I	2		Selects source for concentration of O2	echam phy config(jg)%
irad_o2	1			0: set to zero (or epsilon)	$\begin{array}{c} \text{dt rad} > 0.000 \text{s} \end{array}$
11 au _ 02				2: constant vol. mixing ration set by 'vmr _o2'	10_100 / 0.0005
ocham rad config(ig)%	I	2		Selects source for concentration of CFC11	ocham phy config(ig)0%
echam_rad_config(jg)%	1	4			echam_phy_config(jg)%
irad_cfc11				0: set to zero (or epsilon)	$ m dt_rad > 0.000s$
				2: constant vol. mixing ration set by 'vmr	
				_cfc11'	
				4: spatially constant, time dependent vol.	
1 2 4 18	_			mixing ratio from file	1 1 2 4 184
echam_rad_config(jg)%	I	2		Selects source for concentration of CFC12	echam_phy_config(jg)%
irad_cfc12				0: set to zero (or epsilon)	$ m dt_rad > 0.000s$
				2: constant vol. mixing ration set by 'vmr	
				_cfc12'	
				4: spatially constant, time dependent vol.	
				mixing ratio from file	
$echam_rad_config(jg)\%$	I	2		Selects source for concentration of XYZ	echam_phy_config(jg)%
irad_aero				13: tropospheric 'Kinne' aerosols, time	$ m dt_rad > 0.000s$
				dependent from file	
				14: stratospheric 'Stenchikov' aerosols, time	
				dependent from file	
				15: tropospheric 'Kinne' aerosols + stratospheric	
				'Stenchikov' aerosols, time dependent, both from	
				file	
				18: tropospheric natural 'Kinne' aerosols for	
				1850 + time dep. stratospheric 'Stenchikov'	
				aerosols, both from file + param. time dep.	
				antropogenic 'simple plumes'	
				any other: set to zero	
echam rad config(jg)%	R	348.0e-06	m3/m3	Volume mixing ratio of CO2	echam phy config(jg)%
	l n	940.0e-00	шэ/шэ	volume mixing ratio of CO2	
vmr_co2	D	1650.000	m 9 / 9	Volume mining notic of CIIA	$dt_rad > 0.000s$
echam_rad_config(jg)%	R	1650.0e-09	m3/m3	Volume mixing ratio of CH4	echam_phy_config(jg)%
vmr_ch4		200.0	0/ 0	77.1	$dt_{rad} > 0.000s$
echam_rad_config(jg)%	R	306.0e-09	m3/m3	Volume mixing ratio of N2O	echam_phy_config(jg)%
vmr_n2o		0.00010			$dt_rad > 0.000s$
echam_rad_config(jg)%	R	0.20946	m3/m3	Volume mixing ratio of O2	echam_phy_config(jg)%
vmr o2					dt rad > 0.000s

Parameter	Type	Default	Unit	Description	Scope
echam_rad_config(jg)%	R	214.5e-12	m3/m3	Volume mixing ratio of CFC11	echam_phy_config(jg)%
vmr_cfc11					$ m dt_rad > 0.000s$
echam_rad_config(jg)%	R	371.1e-12	$\mathrm{m}3/\mathrm{m}3$	Volume mixing ratio of CFC11	echam_phy_config(jg)%
vmr_cfc12					$\mathrm{dt_rad} > 0.000\mathrm{s}$
$echam_rad_config(jg)\%$	R	1.0		Scaling factor for concentration of water vapor,	echam_phy_config(jg) $\%$
frad_h2o				cloud water and cloud ice	$ m dt_rad > 0.000s$
$echam_rad_config(jg)\%$	R	1.0		Scaling factor for concentration of CO2	$echam_phy_config(jg)\%$
frad_co2					$ m dt_rad > 0.000s$
$echam_rad_config(jg)\%$	R	1.0		Scaling factor for concentration of CH4	$echam_phy_config(jg)\%$
frad_ch4					$ m dt_rad > 0.000s$
echam_rad_config(jg)%	R	1.0		Scaling factor for concentration of N2O	$echam_phy_config(jg)\%$
frad_n2o					$ m dt_rad > 0.000s$
echam_rad_config(jg)%	R	1.0		Scaling factor for concentration of O3	echam_phy_config(jg)%
frad_o3					$ m dt_rad > 0.000s$
echam_rad_config(jg)%	R	1.0		Scaling factor for concentration of O2	echam_phy_config(jg)%
frad_o2					$ m dt_rad > 0.000s$
echam_rad_config(jg)%	R	1.0		Scaling factor for concentration of CFC11 and	echam_phy_config(jg)%
frad_cfc				CFC12	$dt_rad > 0.000s$

$2.10.\ echam_sso_nml$

The parameterization of subgrid scale orographic (SSO) effects for the ECHAM physics is configured by a data structure $echam_sso_config(jg=1:ndom)\% < param>$, which is a 1-dimensional array extending over all domains. The structure contains parameters providing control over the parametrized effects:

Parameter	Type	Default	Unit	Description	Scope
echam_sso_config(jg)%	R	40.	m	Minimum height difference of peak height and	echam_phy_config(jg)%
gpicmea				mean height to activate the SSO	$dt_sso > 0.000s$
				parameterization.	
echam_sso_config(jg) $\%$	R	10.	m	Minimum standard deviation of the SSO height	echam_phy_config(jg)%
gstd				to activate the SSO parameterization.	$dt_sso > 0.000s$
echam_sso_config(jg) $\%$	R	0.05		Coefficient for orographic gravity wave drag.	echam_phy_config(jg)%
gkdrag					$dt_sso > 0.000s$
echam_sso_config(jg) $\%$	R	0.		Coefficient for low level blocking.	echam_phy_config(jg)%
gkwake					$dt_sso > 0.000s$
$echam_sso_config(jg)\%$	R	0.		Coefficient for low level lift.	echam_phy_config(jg)%
gklift					$dt_sso > 0.000s$
echam_sso_config(jg) $\%$	L	.TRUE.		.FALSE.: SSO effects are directly applied, for	echam_phy_config(jg)%
lsftlf				the case that SSO parameters are valid for the	$ m dt_vdf > 0.000s$
				full cell area.	
				.TRUE.: SSO effects are scaled with the cell	
				area fraction of land including lakes (field sftlf),	
				for the case that SSO parameters are valid only	
				for this part of the cell area.	

$2.11. \ echam_vdf_nml$

The parameterization of vertical diffusion (VDF) for the ECHAM physics is configured by a data structure $echam_vdf_config(jg=1:ndom)\% < param>$, which is a 1-dimensional array extending over all domains. The structure contains parameters providing control over some of the parametrized effects:

Parameter	Type	Default	Unit	Description	Scope
echam_vdf_config(jg)%	L	.TRUE.		switch on/off surface momentum flux	echam_phy_config(jg)%
lsfc_mom_flux					$\mathrm{dt_vdf} > 0.000\mathrm{s}$
$echam_vdf_config(jg)\%$	\mathbf{L}	.TRUE.		switch on/off surface heat flux	$echam_phy_config(jg)\%$
lsfc_heat_flux					$ m dt_vdf > 0.000s$
$echam_vdf_config(jg)\%$	R	1.0		neutral limit Prandtl number, can be varied	$echam_phy_config(jg)\%$
pr0				from about 0.6 to 1.0	$ m dt_vdf > 0.000s$
$echam_vdf_config(jg)\%$	R	0.17		neutral non-dimensional stress factor	$echam_phy_config(jg)\%$
f_tau0					$ m dt_vdf > 0.000s$
$echam_vdf_config(jg)\%$	R	0.185		mixing length: coriolis term tuning parameter	$echam_phy_config(jg)\%$
c_f					$ m dt_vdf > 0.000s$
$echam_vdf_config(jg)\%$	R	2.0		mixing length: stability term tuning parameter	$echam_phy_config(jg)\%$
c_n					$ m dt_vdf > 0.000s$
$echam_vdf_config(jg)\%$	R	0.5		ratio of typical horizontal velocity to wstar at	$echam_phy_config(jg)\%$
wmc				free convection	$ m dt_vdf > 0.000s$
$echam_vdf_config(jg)\%$	R	0.4		fraction of first-level height at which surface	$echam_phy_config(jg)\%$
fsl				fluxes are nominally evaluated, tuning param for	$ m dt_vdf > 0.000s$
				sfc stress	
$echam_vdf_config(jg)\%$	R	3.0		1/fbl: fraction of BL height at which lmix hat its	$echam_phy_config(jg)\%$
fbl				max	$ m dt_vdf > 0.000s$

2.12. ensemble_pert_nml

Parameter	Type	Default	Unit	Description	Scope
use_ensemble_pert	L	.FALSE.		Main switch to activate physics parameter	$run_nml:iforcing = inwp$
				perturbations for ensemble forecasts / ensemble	
				data assimilation; the perturbations are applied	
				via random numbers depending on the	
				perturbationNumber (ensemble member ID)	
				specified in gribout_nml	
range_gkwake	R	0.5		Variability range for low level wake drag	
				constant	
range_gkdrag	R	0.04		Variability range for orographic gravity wave	
				drag constant	
range_gfrcrit	R	0.1		Variability range for critical Froude number in	
				SSO scheme	
range_gfluxlaun	R	0.75e-3		Variability range for non-orographic gravity	
				wave launch momentum flux	
range_zvz0i	R	0.2	m/s	Variability range for terminal fall velocity of ice	$inwp_gscp = 1 \text{ or } 2$

Parameter	Type	Default	Unit	Description	Scope
range_entrorg	R	0.2e-3	1/m	Variability range for entrainment parameter in convection scheme	$inwp_convection = 1$
range_capdcfac_et	R	0.75		Maximum fraction of CAPE diurnal cycle correction applied in the extratropics	icapdcycl = 3
range_rhebc	R	0.05		Variability range for RH threshold for the onset of evaporation below cloud base	$inwp_convection = 1$
range_texc	R	0.05	K	Variability range for temperature excess value in test parcel ascent	$inwp_convection = 1$
range_box_liq	R	0.01		Variability range for box width scale of liquid clouds in cloud cover scheme	inwp_cldcover = 1
range_tkhmin	R	0.2		Variability range for minimum vertical diffusion for heat/moisture	$inwp_turb = 1$
range_tkmmin	R	0.2		Variability range for minimum vertical diffusion for momentum	$inwp_turb = 1$
range_tkred_sfc	R	4.0		Range for multiplicative change of reduction of minimum diffusion coefficients near the surface	$inwp_turb = 1$
range_rlam_heat	R	3.0		Variability range (multiplicative!) of laminar transport resistance parameter	$inwp_turb = 1$
range_charnock	R	1.5		Variability range (multiplicative!) of upper and lower bound of wind-speed dependent Charnock parameter	$inwp_turb = 1$
range_minsnowfrac	R	0.05		Variability range for minimum value to which snow cover fraction is artificially reduced in case of melting snow	$idiag_snowfrac = 20/30/40$
range_c_soil	R	0.25		Variability range for evaporating fraction of soil	
range_cwimax_ml	R	2.0		Variability range for capacity of interception storage (multiplicative)	
range_z0_lcc	R	0.25		Variability range (relative change) of roughness length attributed to each landuse class	
range_rootdp	R	0.2		Variability range (relative change) of root depth attributed to each landuse class	
range_rsmin	R	0.2		Variability range (relative change) of minimum stomata resistance attributed to each landuse class	
range_laimax	R	0.15		Variability range (relative change) of leaf area index (maximum of annual cycle) attributed to each landuse class	

Defined and used in: src/namelists/mo_ensemble_pert_nml.f90

2.13. gribout_nml

Parameter	Type	Default	Unit	Description	Scope
preset	C	"determ"		Setting this different to "none" enables a couple	filetype=2
				of defaults for the other gribout_nml namelist	
				parameters. If, additionally, the user tries to set	
				any of these other parameters to a conflicting	
				value, an error message is thrown. Possible	
				values are "none", "deterministic", "ensemble".	
tablesVersion	Т	15		Main switch for Table version	filetype=2
	<u>1</u>				
backgroundProcess	1	0		Background process	filetype=2
	_			- GRIB2 code table backgroundProcess.table	
generatingCenter	1	-1		Output generating center. If this key is not set,	filetype=2
				center information is taken from the grid file	
				DWD: 78	
				MPIMET: 98	
				ECMWF: 98	
generatingSubcenter	I	-1		Output generating Subcenter. If this key is not	filetype=2
				set, subcenter information is taken from the grid	
				file	
				DWD: 255	
				MPIMET: 232	
				ECMWF: 0	
	T(1)	1			61-4 9
generatingProcess	I(n_dom)	1		generating Process Identifier	filetype=2
Identifier				- GRIB2 code table	
	_			generatingProcessIdentifier.table	
${\bf number Of Forecasts In\text{-} Ensemble}$	1	-1		Local definition for ensemble products, (only set	filetype=2
				if value changed from default)	
perturbationNumber	I	-1		Local definition for ensemble products, (only set	filetype=2
				if value changed from default)	
productionStatusOfPro-	I	1		Production status of data	filetype=2
cessedData				- GRIB2 code table 1.3	
significanceOfReference- Time	I	1		Significance of reference time	filetype=2
				- GRIB2 code table 1.2	
typeOfEnsembleForecast	1	-1		Local definition for ensemble products (only set if	filetype=2
V F	-			value changed from default)	- · · · · · · -
typeOfGeneratingPro- cess	T	-1		Type of generating process	filetype=2
typeoraciiciatiiigi io coss	•	1		- GRIB2 code table 4.3	med pe 2
typeOfProcessedData	T	-1		Type of data	filetype=2
typeOII 10cesseuData	1	-1		- GRIB2 code table 1.4	metype-2
1ID-C:4:N1	Т	1			C1-4 9
local Definition Number	1	-1		local Definition Number	filetype=2
				- GRIB2 code table	
				grib2LocalSectionNumber.78.table	
localNumberOfExperi- ment	I	1		local Number of Experiment	filetype=2
localTypeOfEnsemble-	I	-1		Local definition for ensemble products (only set if	filetype=2
Forecast				value changed from default)	

Parameter	Type	Default	Unit	Description	Scope
lspecialdate_invar	L	.FALSE.		Special reference date for invariant and	filetype = 2
				climatological fields	
				.TRUE.: set special reference date 0001-01-01,	
				00:00	
				.FASLE.: no special reference date	
ldate_grib_act	L	.TRUE.		GRIB creation date	filetype=2
				.TRUE.: add creation date	
				.FALSE.: add dummy date	
lgribout_24bit	L	.FALSE.		If TRUE, write thermodynamic fields ρ , θ_v , T , p	filetype=2
				with 24bit precision instead of 16bit	

Defined and used in: src/namelists/mo_gribout_nml.f90

2.14. grid_nml

Parameter	Type	Default	Unit	Description	Scope
cell_type	I	3		Cell type: not used	
lplane	L	.FALSE.		planar option	
is_plane_torus	L	.FALSE.		f-plane approximation on triangular grid	
corio_lat	R	0.0	deg	Center of the f-plane is located at this	lplane=.TRUE. and
				geographical latitude	is_plane_torus=.TRUE.
grid_angular _velocity	R	Earth's	$\mathrm{rad/s}$	The angular velocity in rad per sec.	
l limited area	L	.FALSE.			
grid_rescale_factor	R	1.0		Defined as the inverse of the reduced-size earth	
				reduction factor X . Choose	
				<pre>grid_rescale_factor < 1 for a reduced-size</pre>	
				earth.	
				The geometry and the timestep will be	
				multiplied by this factor.	
				The angular velocity will be divided by this	
				factor.	
lfeedback	L(n_dom)	.TRUE.		Specifies if feedback to parent grid is performed.	n_dom>1
				Setting lfeedback(1)=.false. turns off feedback	
				for all nested domains; to turn off feedback for	
				selected nested domains, set lfeedback(1)=.true.	
				and set ".false." for the desired model domains	
ifeedback_type	I	2		1: incremental feedback	n_dom>1
				2: relaxation-based feedback	
				Note: vertical nesting requires option 2 to run	
				numerically stable over longer time periods	

Parameter	Type	Default	Unit	Description	Scope
start_time	R(n_dom)	0.	S	Time when a nested domain starts to be active. Relative time w.r.t. experiment start date (ini_datetime_string / experimentStratDate).	n_dom>1
end_time	R(n_dom)	1.E30	s	(namelist entry is ignored for the global domain) Time when a nested domain terminates. Relative time w.r.t. experiment start date (ini_datetime_string /	n_dom>1
patch_weight	R(n_dom)	0.		experimentStratDate). (namelist entry is ignored for the global domain) If patch_weight is set to a value > 0 for any of the first level child patches, processor splitting will be performed, i.e. every of the first level	n_dom>1
				child patches gets a subset of the total number or processors corresponding to its patch_weight. A value of 0. corresponds to exactly 1 processor for this patch, regardless of the total number of processors. For the root patch and higher level childs, patch_weight is not used. However, patch_weight must be set to 0 for these patches to avoid confusion.	
lredgrid_phys	L	.FALSE.		If set to .true. radiation is calculated on a reduced grid (= one grid level higher)	
dynamics_grid_ filename	C			Array of the grid filenames to be used by the dycore. May contain the keyword <path> which will be substituted by model_base_dir.</path>	
dynamics_parent_ grid_id	I(n_dom)	i-1		Array of the indexes of the parent grid filenames, as described by the dynamics_grid_filename array. Indexes start at 1, an index of 0 indicates no parent.	
radiation_grid_ filename	С			Array of the grid filenames to be used for the radiation model. Filled only if the radiation grid is different from the dycore grid. May contain the keyword <path> which will be substituted by model_base_dir.</path>	lredgrid_phys=.TRUE.
dynamics_radiation_g rid_link	I(n_dom)	1 for i=1		Array of the indexes linking the dycore grids, as described by the dynamics_grid_filename array, and the radiation_grid_filename array. It provides the link index of the radiation_grid_filename, for each entry of the dynamics_grid_filename array. Indexes start at 1, an index of 0 indicates that the radiation grid is the same as the dycore grid. Only needs to be filled when the radiation_grid_filename is defined.	

Parameter	Type	Default	Unit	Description	Scope
create_vgrid	L	.FALSE.		.TRUE.: Write vertical grid files containing	
				(vct_a, vct_b, z_ifc, and z_ifv.	
vertical_grid_filename	C(n_dom)			Array of filenames. These files contain the	
				vertical grid definition (vct_a, vct_b, z_ifc). If	
				empty, the vertical grid is created within ICON	
				during the setup phase.	
use_duplicated_	L	.TRUE.		if .TRUE., the zero connectivity is replaced by	
connectivity				the last non-zero value	
use_dummy_cell_closure	L	.FALSE.		if .TRUE. then create a dummy cell and connect	
				it to cells and edges with no neighbor	

Defined and used in: src/namelists/mo_grid_nml.f90

2.15. gridref_nml

Parameter	Type	Default	Unit	Description	Scope
$grf_intmethod_c$	I	2		Interpolation method for grid refinement	n_dom>1
				(cell-based dynamical variables):	
				1: parent-to-child copying	
	_			2: gradient-based interpolation	
grf_intmethod_ct		2		Interpolation method for grid refinement	n_dom>1
				(cell-based tracer variables):	
				1: parent-to-child copying	
				2: gradient-based interpolation	
grf_intmethod_e	1	6		Interpolation method for grid refinement	n_dom>1
				(edge-based variables):	
				1: inverse-distance weighting (IDW)	
				2: RBF interpolation	
				3: combination gradient-based / IDW	
				4: combination gradient-based / RBF	
				5/6: same as 3/4, respectively, but direct	
				interpolation of mass fluxes along nest interface	
				edges	
grf_velfbk	1	1		Method of velocity feedback:	n_dom>1
				1: average of child edges 1 and 2	
				2: 2nd-order method using RBF interpolation	
grf_scalfbk	I	2		Feedback method for dynamical scalar variables	n_dom>1
				(T, p_{sfc}) :	
				1: area-weighted averaging	
				2: bilinear interpolation	
grf_tracfbk	1	2		Feedback method for tracer variables:	n_dom>1
				1: area-weighted averaging	
				2: bilinear interpolation	

Parameter	Type	Default	Unit	Description	Scope
grf_idw_exp_e12	R	1.2		exponent of generalized IDW function for child	n_dom>1
				edges $1/2$	
grf_idw_exp_e34	R	1.7		exponent of generalized IDW function for child	n_dom>1
				edges $3/4$	
rbf_vec_kern_grf_e	I	1		RBF kernel for grid refinement (edges):	n_dom>1
				1: Gaussian	
				$2: 1/(1+r^2)$	
				3: inverse multiquadric	
rbf_scale_grf_e	R(n_dom)	0.5		RBF scale factor for grid refinement (lateral	$n_{dom}>1$
				boundary interpolation to edges). Refers to the	
				respective parent domain and thus does not need	
				to be specified for the innermost nest. Lower	
				values than the default of 0.5 are needed for	
				child mesh sizes less than about 500 m.	
denom_diffu_t	R	135		Deniminator for lateral boundary diffusion of	n_dom>1
				temperature	
denom_diffu_v	R	200		Deniminator for lateral boundary diffusion of	n_dom>1
				velocity	
l_mass_consvcorr	L	.FALSE.		.TRUE.: Apply mass conservation correction in	n_dom>1
				feedback routine	
l_density_nudging	L	.FALSE.		.TRUE.: Apply density nudging near lateral nest	$n_{dom} > 1$.AND. lfeedback =
				boundary if grf_intmethod_e ≤ 4	.TRUE.
fbk_relax_timescale	R	10800		Relaxation time scale for feedback	$n_{dom}>1$.AND. lfeedback =
					.TRUEAND. ifeedback_type
					=2

Defined and used in: src/namelists/mo_gridref_nml.f90

$2.16.\ ha_dyn_nml$

 $This \ namelist \ is \ relevant \ if \ run_nml: ldynamics=. TRUE. \ and \ dynamics_nml: iequations=IHS_ATM_TEMP \ or \ IHS_ATM_THETA.$

Parameter	Type	Default	Unit	Description	Scope
itime_scheme	I	14		Time integration scheme:	
				11: pure advection (no dynamics)	
				12: 2 time level semi implicit (not yet	
				implemented)	
				13: 3 time level explicit	
				14: 3 time level with semi implicit correction	
				15: standard 4th-order Runge-Kutta method	
				(4-stage)	
				16: SSPRK(5,4) scheme (5-stage)	
ileapfrog_startup	I	1		How to integrate the first time step when the	$itime_scheme = 13 \text{ or } 14$
				leapfrog scheme is chosen. $1 = \text{Euler forward}$; 2	
				= a series of sub-steps.	

Parameter	Type	Default	Unit	Description	Scope
asselin_coeff	R	0.1		Asselin filter coefficient	itime_scheme= 13 or 14
si_2tls	R	0.6		weight of time step $n+1$. Valid range: $[0,1]$	itime_scheme=12
si_expl_scheme	I	2		scheme for the explicit part used in the 2 time	itime_scheme=12
				level semi-implicit time stepping scheme. 1 =	
				Euler forward; $2 = Adams$ -Bashforth 2nd order	
si_cmin	R	30.0	m/s	semi implicit correction is done for eigenmodes	itime_scheme=14 and
				with speeds larger than si_cmin	lsi_3d=.FALSE.
si_coeff	R	1.0		weight of the semi implicit correction	itime_scheme=14
si_offctr	R	0.7			itime_scheme=14
si_rtol	R	1.0e-3		relative tolerance for GMRES solver	itime_scheme=14
lsi_3d	L	.FALSE.		3D GMRES solver or decomposistion into 2D	lshallow_water=.FALSE. and
				problems	itime_scheme=14
ldry_dycore	L	.TRUE.		Assume dry atmosphere	iequations $\in \{1,2\}$
lref_temp	L	.FALSE.		Set a background temperature profile as base	iequations $\in \{1,2\}$
_				state when computing the pressure gradient force	

2.17. initicon_nml

Parameter	Type	Default	Unit	Description	Scope
init_mode	I	2		1: MODE_DWDANA	
_				start from DWD analysis or FG	
				2: MODE_IFSANA	
				start from IFS analysis	
				3: MODE_COMBINED	
				${ m IFS~atm} + { m ICON/GME~soil}$	
				4: MODE_COSMO	
				start from prognostic set of variables as used	
				by COSMO	
				5: MODE_IAU	
				start from DWD analysis with incremental	
				analysis update. Extension of	
				MODE_IAU_OLD including snow increments	
				6: MODE_IAU_OLD	
				start from DWD analysis with incremental	
				analysis update. NOTE: Extension of mode	
				MODE_DWDANA_INC including W_SO	
				increments.	
				7: MODE_ICONVREMAP	
				start from DWD first guess with subsequent	
				vertical remapping (work in progress; so far,	
				changing the number of model levels does not	
				yet work)	

Parameter	Type	Default	Unit	Description	Scope
dt_iau	R	10800	S	Duration of incremental analysis update (IAU) procedure. Start time for IAU is the actual model start time (see below).	$init_mode=5,6$
${ m lt_shift}$	R	0	S	Time by which the actual model start time is shifted ahead of the nominal date. The latter is given by either ini_datetime_string or experimentStartDate. dt_shift must be NEGATIVE, usually -0.5 dt iau.	$init_mode=5,6$
terate_iau	L	.FALSE.		If .TRUE., the IAU phase is calculated twice with halved dt_shift in first cycle (allows writing a fully initialized analysis at the nominal initialization date while using a centered IAU window for the forecast).	init_mode=5,6 and dt_shift < 0
tart_time_avg_fg	R	0	S	Start time for calculating temporally averaged first guess output for data assimilation.	
and_time_avg_fg	R	0	S	End time for calculating temporally averaged first guess output for data assimilation. Setting end_time_avg_fg > start_time_avg_fg activates the averaging	
nterval_avg_fg	R	0	s	Corresponding averaging interval. Note that end_time_avg_fg - start_time_avg_fg must not be smaller than the averaging interval	
ho_incr_filter_wgt	R	0		Vertical filtering weight on density increments	$init_mode=5,6$
iter_diffu	I	10		Number of diffusion iterations applied on wind increments	init_mode=5,6
iter_divdamp	I	25		Number of divergence damping iterations applied on wind increments	init_mode=5,6
ype_iau_wgt	I	1		Weighting function for performing IAU 1: Top-Hat 2: SIN2	$init_mode=5,6$
nlevsoil_in pbl1	I R	4 500.0	m	number of soil levels of input data bottom height (AGL) of layer used for gradient computation	init_mode=2
pbl2	R	1000.0	m	top height (AGL) of layer used for gradient computation	
read_ana	L	.TRUE.		If .FALSE., ICON is started from first guess only. Analysis field is not required, and skipped if provided.	$init_mode=1,3$
ise_lakeiceana	L	.FALSE.		If .TRUE., analysis data for sea ice fraction are also used for freshwater lakes (for the time being restricted to the Great Lakes; extension to other lakes needs to be tested)	init_mode=5,6

Parameter	Type	Default	Unit	Description	Scope
lconsistency_checks	L	.TRUE.		If .FALSE., consistency checks for Analysis and First Guess fields are skipped. On default, checks are performed for <i>uuidOfHGrid</i> and <i>validity time</i> .	init_mode=1,3,4,5,6
l_coarse2fine_mode	L(n_dom)	.FALSE.		If true, apply corrections for coarse-to-fine mesh interpolation to wind and temperature	
lp2cintp_incr	L(n_dom)	.FALSE.		If true, interpolate atmospheric data assimilation increments from parent domain. Can be specified separately for each nested domain; setting the first (global) entry to true activates the interpolation for all nested domains.	$init_mode = 5,6$
lp2cintp_sfcana	L(n_dom)	.FALSE.		If true, interpolate atmospheric surface analysis data from parent domain. Can be specified separately for each nested domain; setting the first (global) entry to true activates the interpolation for all nested domains.	$init_mode=5,6$
$ltile_init$	L	.FALSE.		True: initialize tiled surface fields from a first guess coming from a run without tiles. Along coastlines and lake shores, a neighbor search is executed to fill the variables on previously non-existing land or water points with reasonable values. Should be combined with ltile coldstart = .TRUE.	$init_mode=1,5,6$
ltile_coldstart	L	.FALSE.		If true, tiled surface fields are initialized with tile-averaged fields from a previous run with tiles. A neighbor search is applied to subgrid-scale ocean points for SST and sea-ice fraction.	$init_mode{=}1,\!5,\!6$
lvert_remap_fg	L	.FALSE.		If true, vertical remapping is applied to the atmospheric first-guess fields, whereas the analysis increments remain unchanged. The number of model levels must be the same for input and output fields, and the z_ifc (alias HHL) field pertaining to the input fields must be appended to the first-guess file.	$init_mode=5,6$
ifs2icon_filename	C			Filename of IFS2ICON input file, default " <path>ifs2icon_R<nroot>B<jlev>_DOM <idom>.nc". May contain the keywords <path> which will be substituted by model_base_dir, as well as nroot, nroot0, jlev, and idom defining the current patch.</path></idom></jlev></nroot></path>	init_mode=2

Parameter	Type	Default	Unit	Description	Scope
dwdfg_filename	C			Filename of DWD first-guess input file, default	$init_mode=1,3,5,6$
				" <path>dwdFG_R<nroot>B<jlev>_DOM</jlev></nroot></path>	
				<idom>.nc". May contain the keywords <path></path></idom>	
				which will be substituted by model_base_dir,	
				as well as nroot, nroot0, jlev, and idom	
				defining the current patch.	
dwdana_filename	ightharpoons C			Filename of DWD analysis input file, default	$init_mode=1,3,5,6$
				" <path>dwdana_R<nroot>B<jlev>_DOM</jlev></nroot></path>	
				<pre><idom>.nc". May contain the keywords <path></path></idom></pre>	
				which will be substituted by model_base_dir,	
				as well as nroot, nroot0, jlev, and idom	
				defining the current patch.	
filetype	I	-1 (undef.)		One of CDI's FILETYPE_XXX constants.	
				Possible values: 2 (=FILETYPE_GRB2), 4	
				(=FILETYPE_NC2). If this parameter has not	
				been set, we try to determine the file type by its	
				extension "*.grb*" or ".nc".	
$check_fg(jg)\%$ list	C(:)			In ICON a small subset of first guess input fields	$init_mode=1,5,6$
				is declared 'optional', meaning that they are	
				read in if present, but they are not mandatory to	
				start the model. By adding optional fields to	
				this list, they become mandatory for domain jg,	
				such that the model aborts if any of them is	
				missing. This list may include a subset of the	
				optional first guess fields, or even the entire set	
				of first guess fields. On default this list is empty,	
				such that optional fields experience a cold-start	
				initialization if they are missing and the model	
4. \@4.	(A)			does not abort.	
check_ana(jg)%list	C(:)			List of mandatory analysis fields for domain jg	$init_mode=1,5,6$
				that must be present in the analysis file. If these	
				fields are not found, the model aborts. For all	
				other analysis fields, the FG-fields will serve as	
				fallback position.	
ana_varnames_map_ file	C			Dictionary file which maps internal variable	
				names onto GRIB2 shortnames or NetCDF var	
				names. This is a text file with two columns	
				separated by whitespace, where left column:	
				ICON variable name, right column: GRIB2	
				short name or NetCDF var name.	

Defined and used in: src/namelists/mo_initicon_nml.f90

2.18. interpol_nml

Parameter	Type	Default	Unit	Description	Scope
l_intp_c2l	L	.TRUE.		DEPRECATED	
l_mono_c2l	L	.TRUE.		Monotonicity can be enforced by demanding	
				that the interpolated value is not higher or lower	
				than the stencil point values.	
llsq high consv	L	.TRUE.		conservative (T) or non-conservative (F)	
				least-squares reconstruction for high order	
				transport	
lsq high ord	I	3		polynomial order for high order reconstruction	
<u>-</u>				1: linear	ihadv tracer=4
				2: quadratic	_
				30: cubic (no 3^{rd} order cross deriv.)	
				3: cubic	
llsq lin consv	L	.FALSE.		conservative (T) or non-conservative (F)	
······································				least-squares reconstruction for 2nd order	
				(linear) transport	
nudge efold width	\mathbb{R}	2.0		e-folding width (in units of cell rows) for lateral	
nadge_cloid_width	10	2.0		boundary nudging coefficient	
nudge max coeff	R	0.02		Maximum relaxation coefficient for lateral	
nudge_max_cocn	10	0.02		boundary nudging	
nudge zone width	I	8		Total width (in units of cell rows) for lateral	
nuage_zone_wiain	1			boundary nudging zone. If < 0 the patch	
				boundary depth index is used.	
rbf dim c2l	I	10		stencil size for direct lon-lat interpolation: 4 =	
101_01111_021	1	10		nearest neighbor, 13 = vertex stencil, 10 = edge	
				stencil.	
rbf scale mode ll	I	2		Specifies, how the RBF shape parameter is	
Ibi_scale_mode_n	1	2		determined for lon-lat interpolation.	
				1: lookup table based on grid level	
				2: determine automatically.	
				So far, this routine only estimates the smallest	
				value for the shape parameter for which the	
				Cholesky is likely to succeed in floating point	
				· · · · · · · · · · · · · · · · · · ·	
				arithmetic. 3: explicitly set shape parameter in	
				each output namelist (namelist parameter	
who was been s	т	1		output_nml::rbf_scale, p. 51).	
rbf_vec_kern_c	1	1		Kernel type for reconstruction at cell centres: 1: Gaussian	
-1. f 1	т			3: inverse multiquadric	
rbf_vec_kern_e	1	3		Kernel type for reconstruction at edges:	
				1: Gaussian	
1.6		1		3: inverse multiquadric	
rbf_vec_kern_ll	I	1		Kernel type for reconstruction at lon-lat-points:	

Parameter	Type	Default	Unit	Description	Scope
				1: Gaussian	
				3: inverse multiquadric	
rbf_vec_kern_v	I	1		Kernel type for reconstruction at vertices:	
				1: Gaussian	
				3: inverse multiquadric	
rbf_vec_scale_c	R(n_dom)	resolution-		Scale factor for RBF reconstruction at cell	
		dependent		centres	
rbf_vec_scale_e	R(n_dom)	resolution-		Scale factor for RBF reconstruction at edges	
		dependent			
rbf_vec_scale_v	R(n_dom)	resolution-		Scale factor for RBF reconstruction at vertices	
		dependent			
support_baryctr_intp	L	.FALSE.		Flag. If .FALSE. barycentric interpolation is	
				replaced by a fallback interpolation.	
lreduced_nestbdry_stencil	L	.FALSE.		Flag. If .TRUE. then the nest boundary points	
				are taken out from the lat-lon interpolation	
				stencil.	

Defined and used in: src/namelists/mo_interpol_nml.f90

2.19. io_nml

Parameter	Type	Default	Unit	Description	Scope
lkeep_in_sync	L	.FALSE.		Sync output stream with file on disk after each	
				timestep	
dt_{diag}	R	86400.	s	diagnostic integral output interval	run_nml:output = "totint"
${ m dt_checkpoint}$	R	2592000	s	Time interval for writing restart files. Note that	output /= "none" (run_nml)
				if the value of dt_checkpoint resulting from	
				model default or user's specification is longer	
				than time_nml:dt_restart, it will be reset (by	
				the model) to dt_restart so that at least one	
				restart file is generated during the restart cycle.	
inextra_2d	I	0		Number of extra 2D Fields for	$dynamics_nml:iequations = 3$
				diagnostic/debugging output.	(to be done for 1, 2)
inextra_3d	I	0		Number of extra 3D Fields for	$dynamics_nml:iequations = 3$
				diagnostic/debugging output.	(to be done for 1, 2)
lflux_avg	L	.TRUE.		if .FALSE. the output fluxes are accumulated	iequations=3
				from the beginning of the run	iforcing=3
				if .TRUE. the output fluxes are average values	
				from the beginning of the run, except of	
				TOT_PREC that would be accumulated	

Parameter	Type	Default	Unit	Description	Scope
itype_pres_msl	I	1		Specifies method for computation of mean sea	
				level pressure (and geopotential at pressure	
				levels below the surface).	
				1: GME-type extrapolation,	
				2: stepwise analytical integration,	
				3: current IFS method,	
				4: IFS method with consistency correction	
				5: New DWD method constituting a mixture	
				between IFS and old GME method (departure	
				level for downward extrapolation between 10 m	
				and 150 m AGL depending on elevation)	
$itype_rh$	I	1		Specifies method for computation of relative	
				humidity	
				1: WMO-type: water only (e_s=e_s_water),	
				2: IFS-type: mixed phase (water and ice),	
				3: IFS-type with clipping (rh ≤ 100)	
gust_interval	R	3600.	S	Interval over which wind gusts are maximized	iforcing=3
$\operatorname{output_nml_dict}$	C	, ,		File containing the mapping of variable names to	output_nml namelists
				the internal ICON names. May contain the	
				keyword <path> which will be substituted by</path>	
				model_base_dir.	
				The format of this file:	
				One mapping per line, first the name as given in	
				the ml_varlist, hl_varlist, pl_varlist or	
				il_varlist of the output_nml namelists, then	
				the internal ICON name, separated by an	
				arbitrary number of blanks. The line may also	
				start and end with an arbitrary number of	
				blanks. Empty lines or lines starting with $\#$ are	
				treated as comments.	
				Names not covered by the mapping are used as	
				they are.	
linvert_dict	L	.FALSE.		If .TRUE., columns in dictionary file	
				output_nml_dict are evaluated in inverse order.	
				This allows using the same dictionary file as for	
				input (ana_varnames_map_file in	
				initicon_nml).	

Parameter	Type	Default	Unit	Description	Scope
netcdf_dict	С	, ,		File containing the mapping from internal names	output_nml namelists,
				to names written to NetCDF. May contain the	NetCDF output
				keyword <path> which will be substituted by</path>	
				model_base_dir.	
				The format of this file:	
				One mapping per line, first the name written to	
				NetCDF, then the internal name, separated by	
				an arbitrary number of blanks (inverse to the	
				definition of output_nml_dict). The line may	
				also start and end with an arbitrary number of	
				blanks. Empty lines or lines starting with $\#$ are	
				treated as comments.	
				Names not covered by the mapping are output	
				as they are.	
				Note that the specification of output variables,	
				e.g. in ml_varlist, is independent from this	
				renaming, see the namelist parameter	
				output_nml_dict for this.	
lnetcdf_flt64_output	L	.FALSE.		If .TRUE. floating point variable output in	
				NetCDF files is written in 64-bit instead of	
				32-bit accuracy.	
restart_file_type	I	4		Type of restart file. One of CDI's	
				FILETYPE_XXX. So far, only 4	
				(=FILETYPE_NC2) is allowed	
restart_write_mode	C	""		Restart read/write mode.	
				Allowed settings (character strings!) are listed	
				below.	
$nrestart_streams$	I	1		When using the restart write mode "dedicated	${ t restart_write_mode} =$
				procs multifile", it is possible to split the restart	"dedicated procs multifile"
				output into several files, as if	
				<pre>nrestart_streams * num_io_procs restart</pre>	
				processes were involved. This speeds up the	
				read-in process, since all the files may then be	
				read in parallel.	
lmask_boundary	L	F		Set to .TRUE., if interpolation zone should be	
				masked in triangular output.	

2.19.1. Restart read/write mode:

Allowed settings for restart_write_mode are:

'Old' synchronous mode. PE # 0 reads and writes restart files. All other PEs have to wait.

[&]quot;sync"

[&]quot;async"

Asynchronous restart writing: Dedicated PEs (num_restart_proc > 0) write restart files while the simulation continues. Restart PEs can only parallelize over different patches. — Read-in: PE # 0 reads while other PEs have to wait.

"joint procs multifile"

All worker PEs write restart files to a dedicated directory. Therefore, the directory itself is called the restart file. The information is stored in a way that it can be read back into the model independent from the processor count and the domain decomposition. — Read-in: All worker PEs read the data in parallel.

"dedicated procs multifile"

In this case, all the restart data is first transferred to memory buffers in dedicated restart writer PEs. After that, the work processes carry on with their work immediately, while the restart writers perform the actual restart writing asynchronously. Restart PEs can parallelize over patches and horizontal indices. — Read-in: All worker PEs read the data in parallel..

Fallback mode.

If num_restart_proc == 0 (parallel_nml), then this behaves like "sync", otherwise like "async".

Defined and used in: src/namelists/mo_io_nml.f90

2.20. les nml (parameters for LES turbulence scheme; valid for inwp turb=5)

Parameter	Type	Default	Unit	Description	Scope
sst	R	300	K	sea surface temperature for idealized LES	isrfc_type=5,4
				simulations	
shflx	R	0.1	${ m Km/s}$	Kinematic sensible heat flux at surface	$isrfc_type = 2$
lhflx	R	0	m/s	Kinematic latent heat flux at surface	$isrfc_type = 2$
isrfc_type	I	1		surface type	
				0 = No fluxes and zero shear stress	
				1 = TERRA land physics	
				2 = fixed surface fluxes	
				3 = fixed buoyancy fluxes	
				4 = RICO test case	
				5 = fixed SST	
				6 = time varying SST and qv_s case with	
				prescribed roughness length for semi-idealized	
				setups	
ufric	R	-999	m/s	friction velocity for idealized LES simulations; if	
				< 0 then it is automatically diagnosed	
psfc	R	-999	Pa	surface pressure for idealized LES simulations; if	
				< 0 then it uses the surface pressure from	
				dynamics	
min_sfc_wind	R	1.0	m/s	Minimum surface wind for surface layer useful in	
				the limit of free convection	
is_dry_cbl	L	.FALSE.		switch for dry convective boundary layer	
				simulations	
smag_constant	R	0.23		Smagorinsky constant	
km_min	R	0.0		Minimum turbulent viscosity	

Parameter	Type	Default	Unit	Description	Scope
max_turb_scale	R	300.0		Asymtotic maximum turblence length scale	
				(useful for coarse grid LES and when grid is	
				vertically stretched)	
turb_prandtl	R	0.333333		turbulent Prandtl number	
bflux	R	0.0007	$\mathrm{m^2/s^3}$	buoyancy flux for idealized LES simulations	isrfc_type=3
				(Stevens 2007)	
tran_coeff	R	0.02	m/s	transfer coefficient near surface for idealized LES	isrfc_type=3
				simulation (Stevens 2007)	
vert_scheme_type	I	2		type of time integration scheme in vertical	
				diffusion	
				1 = explicit	
				2 = fully implicit	
sampl freq sec	R	60	s	sampling frequency in seconds for statistical (1D	
				and 0D) output	
avg_interval_sec	R	900	S	(time) averaging interval in seconds for 1D	
				statistical output	
expname	C	ICOLES		expname to name the statistical output file	
ldiag_les_out	L	.FALSE.		Control for the statistical output in LES mode	
les_metric	L	.FALSE.		Switch to turn on Smagorinsky diffusion with 3D	
				metric terms to account for topography	

Defined and used in: src/namelists/mo_les_nml.f90

$2.21.\ limarea_nml\ (Scope:\ l_limited_area=.TRUE.\ in\ grid_nml)$

Parameter	Type	Default	Unit	Description	Scope
itype_latbc	I	0		Type of lateral boundary nudging.	
				0: constant lateral boundary conditions derived	
				from the initial conditions,	
				1: time-dependent lateral boundary conditions	
				provided by an external source (IFS, COSMO or	
				a coarser-resolution ICON run),	
				2: Test mode using time-dependent lateral	
				boundary conditions from a nested ICON run in	
				which the present limited-area domain was	
				operated as a nested grid with identical(!) model	
				level configuration.	
$dtime_latbc$	R	10800.0	s	Time difference between two consecutive	itype_latbc ≥ 1
				boundary data.	
init_latbc_from_fg	L	.FALSE.		If .TRUE., take lateral boundary conditions for	itype_latbc ≥ 1
				initial time from first guess (or analysis) field	

Parameter	Type	Default	Unit	Description	Scope
latbc_filename	С			Filename of boundary data input file, these files	itype_latbc ≥ 1
				must be located in the latbc_path directory.	
				Default:	
				"prepiconR <nroot>B<jlev>_<y><m><d><h>.nc".</h></d></m></y></jlev></nroot>	
				The filename may contain keyword tokens (day,	
				hour, etc.) which will be automatically replaced	
				during the run-time. See the table below for a	
				list of allowed keywords.	
latbc_path	C			Absolute path to boundary data.	itype_latbc ≥ 1
latbc_boundary_grid	C	""		Grid file defining the lateral boundary. Empty	itype_latbc ≥ 1
				string means: whole domain is read for the	
				lateral boundary. This NetCDF grid file must	
				contain two integer index arrays: int	
				<pre>global_cell_index(cell), int</pre>	
				global_edge_index(edge), both with	
				attributes nglobal which contains the global	
				size size of the non-sparse cells and edges.	
latbc_varnames_map_ file	C			Dictionary file which maps internal variable	$num_prefetch_proc=1$
				names onto GRIB2 shortnames or NetCDF var	
				names. This is a text file with two columns	
				separated by whitespace, where left column:	
				ICON variable name, right column: GRIB2	
				short name. This list contains variables that are	
				to be read asynchronously for boundary data	
				nudging in a HDCP2 simulation. All new	
				boundary variables that in the future, would be	
				read asynchronously. Need to be added to text	
				file dict.latbc in run folder.	

Defined and used in: src/namelists/mo_limarea_nml.f90

Keyword substitution in boundary data filename (latbc_filename):

```
substituted by year (four digits)
<y>
                                                                      substituted by month (two digits)
< m>
                                                                      substituted by day (two digits)
<d>>
<h>
                                                                      substituted by hour (two digits)
<min>
                                                                      substituted by minute (two digits)
                                                                      substituted by seconds (two digits)
<sec>
<ddhhmmss>
                                                                      substituted by a relative day-hour-minute-second string.
                                                                      substituted by a relative (three-digit) day-hour string.
<dddhh>
```

2.22. Ind nml

Parameter	Type	Default	Unit	Description	Scope
nlev_snow	I	2		number of snow layers	lmulti_snow=.true.
ntiles	I	1		number of tiles	
lsnowtile	L	.FALSE.		.TRUE.: consider snow-covered and snow-free	ntiles>1
				tiles separately	
frlnd thrhld	R	0.05		fraction threshold for creating a land grid point	ntiles>1
frlake thrhld	R	0.05		fraction threshold for creating a lake grid point	ntiles>1
frsea thrhld	R	0.05		fraction threshold for creating a sea grid point	ntiles>1
frlndtile thrhld	R	0.05		fraction threshold for retaining the respective	ntiles>1
minatine_timina		0.00		tile for a grid point	Heliosy I
lmelt	\mid L	.TRUE.		.TRUE. soil model with melting process	
lmelt var		.TRUE.		.TRUE. freezing temperature dependent on	
imeit_vai		.1102.		~ -	
lane who ener-	_T	.TRUE.		water content	init mada_1
lana_rho_snow	L			.TRUE. take rho_snow-values from analysis file	$_{ m init_mode=1}$
$lmulti_snow$	L	.FALSE.		TRUE. for use of multi-layer snow model	
101 1	_	DATOR		(default is single-sayer scheme)	1 10 DATOR
l2lay_rho_snow	$\mid L \mid$.FALSE.		.TRUE. predict additional snow density for	$lmulti_snow = .FALSE.$
				upper part of the snowpack, having a maximum	
				depth of max_toplaydepth	
$\max_toplaydepth$	R	0.25	m	maximum depth of uppermost snow layer	lmulti_snow=.TRUE. or
					l2lay_rho_snow=.TRUE.
$idiag_snowfrac$	I	1		Type of snow-fraction diagnosis:	
				1 = based on SWE only	
				2–4 = more advanced experimental methods	
				20, 30, 40 = same as 2, 3, 4, respectively, but	
				with artificial reduction of snow fraction in case	
				of melting snow	
itype snowevap	I	2		Tuning of snow evaporation in vegetated areas:	lsnowtile=.TRUE.
7 F 3	-	-		1: Tuning turned off	
				2: First level of tuning without additional	
				control variables	
				3: Second level of tuning with additional I/O	
				variables for snow age and maximum snow depth	
ituna ladthi	_T	9			
itype_lndtbl	I	3		Table values used for associating surface	
				parameters to land-cover classes:	
				1 = defaults from extpar (GLC2000 and	
				GLOBCOVER2009)	
				2 = Tuned version based on IFS values for	
				globcover classes (GLOBCOVER2009 only)	
				3 = even more tuned operational version	
				(GLOBCOVER2009 only)	
				4 = tuned version for new bare soil evaporation	
				scheme (itype_evsl=4)	
$itype_root$	I	2		root density distribution:	
				1 = constant	
				2 = exponential	
	I	I	I	1	

Parameter	Type	Default	Unit	Description	Scope
itype_evsl	I	2		type of bare soil evaporation parameterization	
				2 = Dickinson (1984)	
				3 = Noilhan and Planton (1989)	
				4 = Resistance-based scheme by Jan-Peter	
.,	Т Т			Schulz	
itype_trvg		2		type of plant transpiration parameterization	
				2 = BATS scheme, Dickinson (1984) 3 = Extended BATS scheme with additional	
				prognostic variable for integrated plant	
				transpiration since sunrise; should be used only	
				with an appropriate first guess for this variable	
				coming from the assimilation cycle	
ityma hastaand	_T	2		type of soil heat conductivity	
itype_heatcond	1			1 = constant soil heat conductivity	
				2 = moisture dependent soil heat conductivity	
				3 = variant of option 2 with reduced near-surface	
				heat conductivity in the presence of plant cover	
itype interception	I	1		type of plant interception	
ity pe_intercoption		1		1 = standard scheme, effectively switched off by	
				tiny value cwimax_ml	
				2 = Rain and snow interception (under	
				development)	
cwimax_ml	R	1.e-6	m	scaling parameter for maximum interception	$itype_interception = 1$
				storage (almost switched off);	
				use 5.e-4 to activate interception storage	
c_soil	R	1.		surface area density of the (evaporative) soil	
				surface	
				allowed range: $0-2$	
c_soil_urb	R	1.		surface area density of the (evaporative) soil	
				surface, urban areas	
	_			allowed range: 0 – 2	
itype_hydbound	I	1		type of hydraulic lower boundary condition	
				1 = none	
				3 = ground water as lower boundary of soil	
Istomata	Т т	.TRUE.		column If .TRUE., use map of minimum stomatal	
lstomata	L	.IRUE.		, -	
				resistance If .FALSE., use constant value of 150 s/m.	
l2tls	L	.TRUE.		If .TRUE., forecast with 2-Time-Level	
12013	11	.11001.		integration scheme	
lseaice	L	.TRUE.		.TRUE. for use of sea-ice model	
lprog albsi		.FALSE.		If .TRUE., sea-ice albedo is computed	lseaice=.TRUE.
iprog_arosi		.FALSE.		prognostically	Bearce—. 110012.
llake	L	.TRUE.		TRUE. for use of lake model	
114110	"	.11001.	I	.1100 2. for use of faite inoder	

Parameter	Type	Default	Unit	Description	Scope
sstice_mode	I	1		1: SST and sea ice fraction are read from the	iequations=3
				analysis. The SST is kept constant whereas the	iforcing=3
				sea ice fraction can be modified by the seaice	
				model.	
				2: SST and sea ice fraction are read from the	
				analysis. The SST is updated by climatological	
				increments on a daily basis. The sea ice fraction	
				can be modified by the seaice model.	
				3: SST and sea ice fraction are updated daily,	
				based on climatological monthly means	
				4: SST and sea ice fraction are updated daily,	
				based on actual monthly means	
				5: SST and sea ice fraction are updated daily,	
				based on actual daily means (not yet	
				implemented)	
sst_td_filename	C			Filename of SST input files for time dependent	$sstice_mode=3,4,5$
				SST. Default is	
				" <path>SST_<year>_<month>_<gridfile>".</gridfile></month></year></path>	
				May contain the keyword <path> which will be</path>	
				substituted by model_base_dir	
ci_td_filename	C			Filename of sea ice fraction input files for time	$sstice_mode=3,4,5$
				dependent sea ice fraction. Default is	
				" <path>CI_<year>_<month>_<gridfile>".</gridfile></month></year></path>	
				May contain the keyword <path> which will be</path>	
				substituted by model_base_dir	

Defined and used in: src/namelists/mo_lnd_nwp_nml.f90

2.23. ls_forcing_nml (parameters for large-scale forcing; valid for torus geometry)

Parameter	Type	Default	Unit	Description	Scope
is_subsidence_moment	L	.FALSE.		switch for enabling LS vertical advection due to	is_plane_torus=.TRUE.
				subsidence for momentum equations	
is_subsidence_heat	L	.FALSE.		switch for enabling LS vertical advection due to	is_plane_torus=.TRUE.
				subsidence for thermal equations	
is_advection	$\mid L \mid$.FALSE.		switch for enabling LS horizontal advection	$is_plane_torus=.TRUE.$
				(currently only for thermal equations)	
is_nudging	L	.FALSE.		switch for enabling LS Newtonian relaxation	is_plane_torus=.TRUE.
				(nudging) for horizontal winds, temperature and	
				specific humidity	
is_geowind	L	.FALSE.		switch for enabling geostrophic wind	is_plane_torus=.TRUE.
is_rad_forcing	L	.FALSE.		switch for enabling radiative forcing	is_plane_torus=.TRUE.
					$ \text{inwp_rad} = .FALSE. $

Parameter	Type	Default	Unit	Description	Scope
is_theta	L	.FALSE.		switch to indicate that the prescribed radiative	$is_plane_torus=.TRUE.$
				forcing is for potential temperature	is_rad_forcing=.TRUE.

Defined and used in: src/namelists/mo_ls_forcing_nml.f90

2.24. master_nml

Parameter	Type	Default	Unit	Description	Scope
institute	С	, ,		Acronym of the institute for which the full	
				institute name is printed in the log file. Options	
				are DWD, MPIM, KIT, or CSCS. Otherwise the	
				full names of MPIM and DWD are printed.	
lrestart	L	.FALSE.		If .TRUE.: Current experiment is started from a	
				restart.	
$read_restart_namelists$	L	.TRUE.		If .TRUE.: Namelists are read from the restart	
				file to override the default namelist settings,	
				before reading new namelists from the run	
				script. Otherwise the namelists stored in the	
				restart file are ignored.	
lrestart_write_last	L	.FALSE.		If .TRUE.: model run should create restart at	
				experiment end. This is independent from the	
				settings of the restart interval.	
$model_base_dir$	\mathbf{C}	, ,		General path which may be used in file names of	
				other name lists: If a file name contains the	
				keyword " <path>", then this model_base_dir</path>	
				will be substituted.	

${\bf 2.25.\ master_model_nml\ (repeated\ for\ each\ model)}$

Parameter	Type	Default	Unit	Description	Scope
model_name	С			Character string for naming this component.	
${f model_namelist_filename}$	C			File name containing the model namelists.	
$model_type$	I	-1		Identifies which component to run.	
_				1=atmosphere	
				2=ocean	
				3=radiation	
				99=dummy_model	
model_min_rank	I	0		Start MPI rank for this model.	
model_max_rank	I	-1		End MPI rank for this model.	
model_inc_rank	I	1		Stride of MPI ranks.	

$2.26.\ master_time_control_nml$

Parameter	Type	Default	Unit	Description	Scope
calendar	I	1		Selects the calendar type to use:	
				0 = calendar is not defined yet	
				1 = proleptic Gregorian calendar	
				2 = 365 day year without leap years	
				3 = 360 day year with 30 day months	
${\bf experiment Reference Date}$	C	experiment start		This specifies the reference date for the calendar	
		date		in use. It is an anchor date for cycling of events	
				on the time line. If this namelist parameter is	
				unspecified, then the reference date is set to the	
		TGG0001	1	experiment start date.	
experimentStartDate	ightharpoons C	ISO8601	date of	This is the start date of an experiment, which	
		formatted string	initial file	remains valid for the whole experiment. The	
				start date is also the reference date of the	
				experiment, which is the anchor point for cycling	
				events. In special cases the reference date might	
				be reset. Reasons might be debugging purposes or spinning off experiments from an existing	
				restart of an other experiment.	
experimentStopDate	C	ISO8601	n/a	This is the date an experiment is finished.	
experimentstopDate		formatted string	Π/ α	This is the date an experiment is infished.	
forecastLeadTime	\mathbf{C}	ISO8601	n/a	Specifies the time span for a numerical weather	
		formatted string	11/ 0	forecast. It is used to set the experiment stop	
		8		time with respect to the experiment start date.	
checkpointTimeIntVal	C	ISO8601	n/a	Time interval for writing checkpoints.	
_		formatted string	′		
restartTimeIntVal	C	ISO8601	n/a	Time interval for writing a restart file and	
		formatted string		interrupt the current running job.	

$2.27.\ meteogram_output_nml$

Nearest neighbour 'interpolation' is used for all variables.

Parameter	Type	Default	Unit	Description	Scope
lmeteogram_enabled	L(n_dom)	.FALSE.		Flag. True, if meteogram of output variables is	
				desired.	
zprefix	C(n_dom)	"METEO		string with file name prefix for output file	
		GRAM "			
ldistributed	L(n dom)	.TRUE.		Flag. Separate files for each PE.	
loutput tiles	L	.FALSE.		Write tile-specific output for some selected	
_				surface/soil fields	
n0_mtgrm	I(n dom)	0		initial time step for meteogram output.	
ninc_mtgrm	I(n_dom)	1		output interval (in time steps)	

Parameter	Type	Default	Unit	Description	Scope
stationlist_tot		53.633, 9.983,		list of meteogram stations (triples with lat, lon,	
		'Hamburg'		name string)	
silent_flush	L(n_dom)	1		do not warn about flushing to disk if .TRUE.	
max_time_stamps	I(n_dom)	1		number of output time steps to record in	
				memory before flushing to disk	
var_list	C(:)	" "		Positive-list of variables (optional). Only	
				variables contained in this list are included in	
				the meteogram. If the default list is not changed	
				by user input, then all available variables are	
				added to the meteogram	

Defined and used in: src/namelists/mo_mtgrm_nml.f90

2.28. nonhydrostatic_nml (relevant if run_nml:iequations=3)

Parameter	Type	Default	Unit	Description	Scope
itime_scheme	I	4		Options for predictor-corrector time-stepping scheme: 4: Contravariant vertical velocity is computed in the predictor step only, velocity tendencies are computed in the corrector step only (most efficient option) 5: Contravariant vertical velocity is computed in both substeps (beneficial for numerical stability in very-high resolution setups with extremely steep slops, otherwise no significant impact) 6: As 5, but velocity tendencies are also computed in both substeps (no apparent benefit, but more expensive)	iequations=3
rayleigh_type	I	2		Type of Rayleigh damping 1: CLASSICAL (requires velocity reference state!) 2: Klemp (2008) type	
rayleigh_coeff	R(n_dom)	0.05		Rayleigh damping coefficient $1/\tau_0$ (Klemp, Dudhia, Hassiotis: MWR136, pp.3987-4004); higher values are recommended for R2B6 or finer resolution	
damp_height	R(n_dom)	45000	m	Height at which Rayleigh damping of vertical wind starts (needs to be adjusted to model top height; the damping layer should have a depth of at least 20 km when the model top is above the stratopause)	

Parameter	Type	Default	Unit	Description	Scope
htop_moist_proc	R	22500.0	m	Height above which moist physics and advection	
				of cloud and precipitation variables are turned	
	D	22500.0		off	11 1 4 99 99 49 79
hbot_qvsubstep	R	22500.0	m	Height above which QV is advected with	ihadv_tracer=22, 32, 42 or 52
				substepping scheme (must be at least as large as	
vwind_offctr	R	0.15		htop_moist_proc) Off-centering in vertical wind solver. Higher	
vwind_oneti	110	0.15		values may be needed for R2B5 or coarser grids	
				when the model top is above 50 km.	
rhotheta offctr	R	-0.1		Off-centering of density and potential	
	10	0.1		temperature at interface level (may be set to 0.0	
				for R2B6 or finer grids)	
veladv offctr	R	0.25		Off-centering of velocity advection in corrector	
		0.20		step	
ivctype	I	2		Type of vertical coordinate:	
				1: Gal-Chen hybrid	
				2: SLEVE (uses sleve nml)	
ndyn_substeps	I	5		number of dynamics substeps per fast-physics /	
				transport step	
lhdiff_rcf	L	.TRUE.		.TRUE.: Compute diffusion only at advection	
				time steps (in this case, divergence damping is	
				applied in the dynamical core)	
lextra_diffu	L	.TRUE.		.TRUE.: Apply additional momentum diffusion	
				at grid points close to the stability limit for	
				vertical advection (becomes effective extremely	
				rarely in practice; this is mostly an emergency	
				fix for pathological cases with very large	
1:1 f	D	0.0005		orographic gravity waves)	11-4:00f TDIJE
divdamp_fac		0.0025		Scaling factor for divergence damping Order of divergence damping:	$lhdiff_rcf = .TRUE.$ $lhdiff_rcf = .TRUE.$
divdamp_order	1	4		Order of divergence damping: 2 = second-order divergence damping	$\begin{bmatrix} \text{Indin}_\text{rel} = .1 \text{ KUE}. \end{bmatrix}$
				4 = fourth-order divergence damping	
				24 = combined second-order and fourth-order	
				divergence damping and enhanced vertical wind	
				off-centering during the initial spinup phase	
				(does not allow checkpointing/restarting earlier	
				than 2.5 hours of integration)	
divdamp_type	I	3		Type of divergence damping:	lhdiff rcf = .TRUE.
				2 = divergence damping acting on 2D divergence	_
				3 = divergence damping acting on 3D divergence	
				32 = combination of 3D div. damping in the	
				troposphere with transition to 2D div. damping	
				in the stratosphere	
divdamp_trans_start	R	12500.		Lower bound of transition zone between 2D and	$\operatorname{divdamp_type} = 32$
				3D divergence damping	

Parameter	Type	Default	Unit	Description	Scope
divdamp_trans_end	R	17500.		Upper bound of transition zone between 2D and	$divdamp_type = 32$
				3D divergence damping	
nest_substeps	I	2		Number of dynamics substeps for the child	
				patches.	
				DO NOT CHANGE!!! The code will not work	
				correctly with other values	
l_masscorr_nest	L	.FALSE.		.TRUE.: Apply mass conservation correction	
				also in nested domain	
iadv_rhotheta	I	2		Advection method for rho and rhotheta:	
				1: simple second-order upwind-biased scheme	
				2: 2nd order Miura horizontal	
				3: 3rd order Miura horizontal (not	
				recommended)	
igradp_method	I	3		Discretization of horizontal pressure gradient:	
				1: conventional discretization with metric	
				correction term	
				2: Taylor-expansion-based reconstruction of	
				pressure (advantageous at very high resolution)	
				3: Similar discretization as option 2, but uses	
				hydrostatic approximation for downward	
				extrapolation over steep slopes	
				4: Cubic/quadratic polynomial interpolation for	
				pressure reconstruction 5: Same as 4, but hydrostatic approximation for	
				downward extrapolation over steep slopes	
l_zdiffu_t	ho L	.TRUE.		.TRUE.: Compute Smagorinsky temperature	hdiff order=3/5 .AND.
		.1102.		diffusion truly horizontally over steep slopes	lhdiff temp = .true.
thslp_zdiffu	R	0.025		Slope threshold above which truly horizontal	hdiff_order=3/5 .AND.
thsip_zdinu	16	0.025		temperature diffusion is activated	lhdiff temp=.trueAND.
				temperature diffusion is activated	l zdiffu t=.true.
thhgtd zdiffu	R	200	m	Threshold of height difference between	hdiff order=3/5 .AND.
umgua_zama	10	200	111	neighboring grid points above which truly	lhdiff temp=.trueAND.
				horizontal temperature diffusion is activated	l zdiffu t=.true.
				(alternative criterion to thslp zdiffu)	i_zama_v .vrao.
exner_expol	R	1./3.		Temporal extrapolation (fraction of dt) of Exner	
		, -		function for computation of horizontal pressure	
				gradient. This damps horizontally propagating	
				sound waves. For R2B5 or coarser grids, values	
				between $1/2$ and $2/3$ are recommended.	
l open ubc	L	.FALSE.		.TRUE.: Use open upper boundary condition	
				(rather than w=0) to allow vertical motions	
				related to diabatic heating to extend beyond the	
				model top	

2.29. nwp phy nml

The switches for the physics schemes and the time steps can be set for each model domain individually. If only one value is specified, it is copied to all child domains, implying that the same set of parameterizations and time steps is used in all domains. If the number of values given in the namelist is larger than 1 but less than the number of model domains, then the settings from the highest domain ID are used for the remaining model domains.

If the time steps are not an integer multiple of the advective time step (dtime), then the time step of the respective physics parameterization is automatically rounded to the next higher integer multiple of the advective time step. If the radiation time step is not an integer multiple of the cloud-cover time step it is automatically rounded to the next higher integer multiple of the cloud cover time step.

Parameter	Type	Default	Unit	Description	Scope
inwp_gscp	I (max_	1		cloud microphysics and precipitation	$run_nml:iforcing = inwp$
	dom)			0: none	
				1: hydci (COSMO-EU microphysics, 2-cat ice:	
				cloud ice, snow)	
				2: hydci_gr (COSMO-DE microphysics, 3-cat	
				ice: cloud ice, snow, graupel)	
				3: as 1, but with improved ice nucleation scheme	
				by C. Koehler	
				4: Two-moment microphysics by A. Seifert	
				9: Kessler scheme	
qi0	R	0.0	kg/kg	cloud ice threshold for autoconversion	inwp_gscp=1
qc0	R	0.0	kg/kg	cloud water threshold for autoconversion	inwp_gscp=1
mu_rain	R	0.0		shape parameter in gamma distribution for rain	inwp_gscp>0
rain_n0_factor	R	1.0		tuning factor for intercept parameter of raindrop	inwp_gscp>0
				size distribution	
mu_snow	R	0.0		shape parameter in gamma distribution for snow	inwp_gscp>0
icpl_aero_gscp	I	0		0: off	currently only for inwp_gscp
				1: simple coupling between autoconversion and	= 1
				Tegen aerosol climatology; requires irad_aero=6	
				More advanced options are in preparation	
inwp_convection	I (max_	1		convection	run_nml:iforcing = inwp
	dom)			0: none	
				1: Tiedtke/Bechtold convection	
lshallowconv_only	L (max_	.FALSE.		.TRUE.: use shallow convection only	$inwp_convection = 1$
	dom)				
ldetrain_conv_prec	L (max_	.FALSE.		.TRUE.: Activate detrainment of convective rain	$inwp_convection = 1$
	dom)			and snow	

Parameter	Type	Default	Unit	Description	Scope
icapdcycl	I	0		Type of CAPE correction to improve diurnal	$inwp_convection = 1$
				cycle for convection:	
				0 = none (IFS default prior to autumn 2013)	
				1 = intermediate testing option	
				2 = correctoins over land and water now operational at ECMWF	
				3 = correction over land as in 2 restricted to the	
				tropics, no correction over water (this choice	
				optimizes the NWP skill scores)	
icpl_aero_conv	I	0		0: off	
				1: simple coupling between autoconversion and	
				Tegen aerosol climatology; requires irad_aero=6	
iprog_aero	I	0		0: off	
				1: simple prognostic aerosol scheme, based on	
				2D aerosol optical depth fields of Tegen	
				climatology; requires irad_aero=6	_
icpl_o3_tp	I	1		0: off	$irad_o3 = 7 \text{ or } 9$
				1: simple coupling between the ozone mixing	
				ratio and the thermal tropopause, restricted to	
. ,,	T (the extratropics	1.6
inwp_cldcover	I (max_	1		cloud cover scheme for radiation	run_nml:iforcing = inwp
	dom)			0: no clouds (only QV)	
				1: diagnostic cloud cover (by Martin Koehler)	
				2: prognostic total water variance (not yet started)	
				3: clouds from COSMO SGS cloud scheme	
				4: clouds as in turbulence (turbdiff)	
				5: grid scale clouds	
inwp radiation	I (max	1		radiation	run nml:iforcing = inwp
mwp_radiation	dom)	1		0: none	Tun_mm.noremg = mwp
	(3011)			1: RRTM radiation	
				2: Ritter-Geleyn radiation	
				3: PSRAD radiation	
inwp_satad	I	1		saturation adjustment	run nml:iforcing = inwp
				0: none	
				1: saturation adjustment at constant density	
inwp_turb	I (max_	1		vertical diffusion and transfer	$\operatorname{run_nml}$: if $\operatorname{orcing} = \operatorname{inwp}$
	dom)			0: none	
				1: COSMO diffusion and transfer	
				2: GME turbulence scheme	
				3: EDMF-DUALM (work in progress)	
	- /			5: Classical Smagorinsky diffusion	
inwp_sso	I (max_	1		subgrid scale orographic drag	$run_nml:iforcing = inwp$
	dom)			0: none	
				1: Lott and Miller scheme (COSMO)	

Parameter	Type	Default	Unit	Description	Scope
inwp_gwd	I (max_	1		non-orographic gravity wave drag	$run_nml:iforcing = inwp$
	dom)			0: none	
				1: Orr-Ern-Bechtold-scheme (IFS)	
$inwp_surface$	I (max_	1		surface scheme	$run_nml:iforcing = inwp$
	dom)			0: none	
				1: TERRA	
$ustart_raylfric$	R	160.0	m/s	wind speed at which extra Rayleigh friction	$inwp_gwd > 0$
				starts	
efdt_min_raylfric	R	10800.	s	minimum e-folding time of Rayleigh friction	$inwp_gwd > 0$
				(effective for u > ustart_raylfric + 90 m/s)	
latm_above_top	L (max_	.FALSE.		.TRUE.: take into account atmosphere above	$inwp_radiation > 0$
	dom)			model top for radiation computation	
itype_z0	I	2		Type of roughness length data used for	inwp turb > 0
				turbulence scheme:	
				1 = land-cover-related roughness including	
				contribution from sub-scale orography (does not	
				account for tiles)	
				2 = land-cover-related roughness based on	
				tile-specific landuse class	
				3 = land-cover-related roughness based on	
				tile-specific landuse class including contribution	
				from sub-scale orography	
dt conv	R (max	600.	s	time interval of convection and cloud-cover call.	run nml:iforcing = inwp
_	dom)			If convection is switched off, dt conv controlls	
				the time interval of cloud-cover, only.	
				currently each subdomain has the same value	
${ m dt}$ rad	R (max	1800.	s	time interval of radiation call	$run_nml:iforcing = inwp$
_	dom)			currently each subdomain has the same value	_
dt sso	R (max	1200.	s	time interval of sso call	run nml:iforcing = inwp
_	dom)			currently each subdomain has the same value	
${ m dt}\ { m gwd}$	R (max	1200.	s	time interval of gwd call	run nml:iforcing = inwp
_ 	dom			currently each subdomain has the same value	
lrtm filename	C(:)	"rrtmg_ lw.nc"		NetCDF file containing longwave absorption	
_				coefficients and other data for RRTMG_LW	
				k-distribution model.	
${\it cldopt_filename}$	C(:)	"ECHAM		NetCDF file with RRTM Cloud Optical	
- —		6 CldOpt		Properties for ECHAM6.	
		Props.nc"		-	

Defined and used in: src/namelists/mo_nwp_phy_nml.f90

2.30. nwp_tuning_nml

Please note: These tuning parameters are NOT domain specific.

Parameter	Type	Default	Unit	Description	Scope
SSO (Lott and Miller)					
tune_gkwake	R (max_dom)	1.5		low level wake drag constant	$run_nml:iforcing = inwp$
tune_gkdrag	R (max_dom)	0.075		gravity wave drag constant	run_nml:iforcing = inwp
tune_gfrcrit	R (max_dom)	0.4		critical Froude number (controls depth of blocking layer)	run_nml:iforcing = inwp
tune_grcrit	R (max_dom)	0.25		critical Richardson number (controls onset of wave breaking)	run_nml:iforcing = inwp
GWD (Warner McIntyre)	·			·	
tune_gfluxlaun	R	2.50e-3		total launch momentum flux in each azimuth (rho_o x F_o)	run_nml:iforcing = inwp
Grid scale microphysics (one m	noment)				
tune_zceff_min	R	0.01		Minimum value for sticking efficiency	$run_nml:iforcing = inwp$
tune_v0snow	R	25.0		factor in the terminal velocity for snow	$run_nml:iforcing = inwp$
tune_zvz0i	R	1.25	m/s	Terminal fall velocity of ice	$run_nml:iforcing = inwp$
tune_icesedi_exp	R	0.33		Exponent for density correction of cloud ice sedimentation	run_nml:iforcing = inwp
Convection scheme					
tune_entrorg	R	1.85e-3	1/m	Entrainment parameter valid for dx=20 km (depends on model resolution)	run_nml:iforcing = inwp
tune_capdcfac_et	R	0.125		Fraction of CAPE diurnal cycle correction applied in the extratropics	icapdcycl = 3
tune_rhebc_land	R	0.75		RH threshold for onset of evaporation below cloud base over land	$run_nml:iforcing = inwp$
tune_rhebc_land_trop	R	0.75		RH threshold for onset of evaporation below cloud base over land in the tropics	run_nml:iforcing = inwp
tune_rhebc_ocean	R	0.85		RH threshold for onset of evaporation below cloud base over sea	$run_nml:iforcing = inwp$
tune_rhebc_ocean_trop	R	0.80		RH threshold for onset of evaporation below cloud base over sea in the tropics	$run_nml:iforcing = inwp$
tune_rcucov	R	0.05		Convective area fraction used for computing evaporation below cloud base	run_nml:iforcing = inwp
tune_rcucov_trop	R	0.05		Convective area fraction used for computing evaporation below cloud base in the tropics	$run_nml:iforcing = inwp$
tune_texc	R	0.125	K	Excess value for temperature used in test parcel ascent	run_nml:iforcing = inwp
tune_qexc	R	0.0125		Excess fraction of grid-scale QV used in test parcel ascent	run_nml:iforcing = inwp
tune_box_liq	R	0.05		Box width for liquid cloud diagnostic in cloud cover scheme	$run_nml:iforcing = inwp;$ $inwp_cldcover = 1$
tune_box_liq_asy	R	2.5		Asymmetry factor for liquid cloud cover diagnostic	$run_nml:iforcing = inwp;$ $inwp_cldcover = 1$

Parameter	Type	Default	Unit	Description	Scope
lcalib_clcov	L	.TRUE.		Apply calibration of layer-wise cloud cover	$run_nml:iforcing = inwp$
				diagnostics	
Misc					
itune_albedo	I	0		MODIS albedo tuning	$run_nml:iforcing = inwp$
				0: None	albedo_type=2
				1: dimmed sahara	
tune_minsnowfrac	R	0.125		Minimum value to which the snow cover fraction	$lnd_nml:idiag_snowfrac =$
				is artificially reduced in case of melting show	20/30/40
IAU					
max_freshsnow_inc	R	0.025		Maximum allowed freshsnow increment per	init_mode=5 (MODE_IAU)
				analysis cycle (positive or negative)	

Defined and used in: src/namelists/mo_nwp_tuning_nml.f90

2.31. output_nml (relevant if run_nml/output='nml')

Please note: There may be several instances of output_nml in the namelist file, every one defining a list of variables with separate attributes for output.

Parameter	Type	Default	Unit	Description	Scope
dom	I(:)	-1		Array of domains for which this name-list is	
				used. If not specified (or specified as -1 as the	
				first array member), this name-list will be used	
				for all domains.	
				Attention: Depending on the setting of the	
				parameter l_output_phys_patch these are	
				either logical or physical domain numbers!	
file_interval	C	5 5		Defines the length of a file in terms of an	
_				ISO-8601 duration string. An example for this	
				time stamp format is given below. This namelist	
				parameter can be set instead of	
				steps_per_file.	
$filename_format$	C	see description.		Output filename format. Includes keywords	
				path, output_filename, physdom, etc. (see	
				below). Default is	
				<pre><output_filename>_DOM<physdom>_<levtype>_</levtype></physdom></output_filename></pre>	
				<jfile></jfile>	
filename_extn	\mid C	"default"		User-specified filename extension (empty string	
				also possible). If this namelist parameter is	
				chosen as "default", then we have ".nc" for	
				NetCDF output files, and ".grb" for GRIB1/2.	
filetype	I	4		One of CDI's FILETYPE_XXX constants.	
				Possible values:	
				$2=$ FILETYPE $_$ GRB2 $,$	
				$4=FILETYPE_NC2,$	
				5=FILETYPE_NC4	

Parameter	Type	Default	Unit	Description	Scope
m_levels	C	None		Model level indices (optional). Allowed is a comma- (or semicolon-) separated list of integers, and of integer ranges like "1020". One may also use the keyword "nlev" to denote the maximum integer (or, equivalently, "n" or "N"). Furthermore, arithmetic expressions like "(nlev - 2)" are possible. Basic example: m_levels = "1,3,510,20(nlev-2)"	
h_levels	R(:)	None	m	height levels	
p_levels	R(:)	None	Pa	pressure levels	
i_levels	R(:)	None	K	isentropic levels	
ml_varlist hl_varlist pl_varlist il_varlist include_last mode	C(:) C(:) C(:) C(:) I	None None None None .TRUE. 2		Name of model level fields to be output. Name of height level fields to be output. Name of pressure level fields to be output. Name of isentropic level fields to be output. Flag whether to include the last time step 1 = forecast mode, 2 = climate mode In climate mode the time axis of the output file is set to TAXIS_ABSOLUTE. In forecast mode it is set to TAXIS_RELATIVE. Till now the forecast mode only works if the output is at multiples of 1 hour	
taxis_tunit	I	None		Time unit of the TAXIS_RELATIVE time axis. 1 = TUNIT_SECOND 2 = TUNIT_MINUTE 5 = TUNIT_HOUR 9 = TUNIT_DAY For a complete list of possible values see cdilib.c	mode=1
${ m output_bounds}$	R(k*3)	None		Post-processing times: start, end, increment. We choose the advection time step matching or following the requested output time, therefore we require output_bounds(3) > dtime. Multiple triples are possible in order to define multiple starts/ends/intervals. See namelist parameters output_start, output_end, output_interval for an alternative specification of output events.	

Parameter	Type	Default	Unit	Description Scope	
output_time_unit	I	1		Units of output bounds specification.	
				1 = second	
				2 = minute	
				3 = hour	
				4 = day	
				5 = month	
				6 = year	
${ m output_filename}$	ightharpoons C	None		Output filename prefix (which may include	
• –				path). Domain number, level type, file number	
				and extension will be added, according to the	
				format given in namelist parameter	
				"filename format".	
output grid	L	.FALSE.		Flag whether grid information is added to	
output_8114		1112021		output.	
$output_start$	C(:)	5 5		ISO8601 time stamp for begin of output. An	
output_start				example for this time stamp format is given	
				below. More than one value is possible in order	
				to define multiple start/end/interval triples. See	
				namelist parameter output_bounds for an	
				alternative specification of output events.	
output and	$C(\cdot)$, ,			
$\operatorname{output_end}$	C(:)			ISO8601 time stamp for end of output. An	
				example for this time stamp format is given	
				below. More than one value is possible in order	
				to define multiple start/end/interval triples. See	
				namelist parameter output_bounds for an	
	544	5 5		alternative specification of output events.	
$output_interval$	C(:)	, ,		ISO8601 time stamp for repeating output	
				intervals. We choose the advection time step	
				matching or following the requested output time,	
				therefore we require output_bounds(3) >	
				dtime. An example for this time stamp format	
				is given below. More than one value is possible	
				in order to define multiple start/end/interval	
				triples. See namelist parameter output_bounds	
				for an alternative specification of output events.	
operation	C	None		Choose "mean" for generating time averaged	
				output for the given list of variables or groups.	
				The corresponding interval is the	
				output_interval. Supported are 2D and 3D	
				fields on model levels of the atmosphere and	
				land model. Any other value than mean will be	
				ignored.	

Parameter	Type	Default Unit	Description	Scope
pe_placement_il	I(:)	-1	Advanced output option: Explicit assignment of	
			output MPI ranks to the isentropic level output	
			file. At most stream_partitions_il different	
			ranks can be specified. See namelist parameter	
			<pre>pe_placement_ml for further details.</pre>	
pe placement hl	I(:)	-1	Advanced output option: Explicit assignment of	
			output MPI ranks to the height level output file.	
			At most stream_partitions_hl different ranks	
			can be specified. See namelist parameter	
			pe_placement_ml for further details.	
pe placement ml	I(:)	-1	Advanced output option: Explicit assignment of	
			output MPI ranks to the model level output file.	
			At most stream_partitions_ml different ranks	
			can be specified, out of the following list: 0	
			(num_io_procs - 1). If this namelist parameters	
			is not provided, then the output ranks are	
			chosen in a Round-Robin fashion among those	
			ranks that are not occupied by explicitly placed	
			output files.	
pe placement pl	I(:)	-1	Advanced output option: Explicit assignment of	
pe_placement_pr	1(.)		output MPI ranks to the pressure level output	
			file. At most stream_partitions_pl different	
			ranks can be specified. See namelist parameter	
			pe_placement_ml for further details.	
ready file	C	'default'	A ready file is a technique for handling	
ready_ine		deraute	dependencies between the NWP processes. The	
			completion of the write process is signalled by	
			creating a small file with name ready_file.	
			Different output_nml's may be joined together	
			to form a single ready file event. The setting of	
			ready_file = "default" does not create a	
			ready file. The ready file name may contain	
			string tokens <path>, <datetime>, <ddhmmss>,</ddhmmss></datetime></path>	
			<pre><dddhhmmss> which are substituted as described</dddhhmmss></pre>	
			for the namelist parameter filename_format.	
reg def mode	I		Specify if the "delta" value prescribes an interval	remap=1
reg_der_mode	1		size or the total *number* of intervals: 0: switch	remap—r
			automatically between increment and no. of grid	
			points, 1: reg_lon/lat_def(2) specifies	
			increment, 2: reg_lon/lat_def(2) specifies no.	
noman			of grid points. interpolate horizontally	
remap	1	0	0: none	
			1: to regular lat-lon grid	

Parameter	Type	Default	Unit	Description	Scope
north_pole	R(2)	0,90		definition of north pole for rotated lon-lat grids	
				([longitude, latitude].	
$ m reg_lat_def$	R(3)	None		start, increment, end latitude in degrees.	remap=1
				Alternatively, the user may set the number of	
				grid points instead of an increment. Details for	
				the setting of regular grids is given below	
				together with an example.	
${ m reg_lon_def}$	R(3)	None		The regular grid points are specified by three	remap=1
				values: start, increment, end given in degrees.	
				Alternatively, the user may set the number of	
				grid points instead of an increment. Details for	
				the setting of regular grids is given below	
				together with an example.	
${ m steps_per_file}$	I	-1		Max number of output steps in one output file.	
				If this number is reached, a new output file will	
				be opened.	
steps_per_file_inclfirst	\mid L	see descr.		Defines if first step is counted wrt.	
				steps_per_file files count. The default is	
				.FALSE. for GRIB2 output, and .TRUE.	
				otherwise.	
stream partitions hl	I	1		Splits height level output of this namelist into	
_rr				several concurrent alternating files. See namelist	
				parameter stream_partitions_ml for details.	
stream partitions il	I	1		Splits isentropic level output of this namelist into	
				several concurrent alternating files. See namelist	
				parameter stream_partitions_ml for details.	
stream partitions ml	I	1		Splits model level output of this namelist into	
				several concurrent alternating files. The output	
				is split into N files, where the start date of part	
				i gets an offset of $(i-1)$ * output_interval.	
				The output interval is then replaced by	
				N * output_interval, the include_last flag is	
				set to .FALSE., the steps_per_file_inclfirst	
				flag is set to .FALSE., and the steps_per_file	
				counter is set to 1.	
stream partitions pl	I	1		Splits pressure level output of this namelist into	
_rr				several concurrent alternating files. See namelist	
				parameter stream_partitions_ml for details.	
rbf scale	R	-1.		Explicit setting of RBF shape parameter for	interpol nml:rbf scale mode 1 = 3
				interpolated lon-lat output. This namelist	
				parameter is only active in combination with	
				interpol nml:rbf scale mode ll=3.	

Interpolation onto regular grids: Horizontal interpolation onto regular grids is possible through the namelist setting remap=1, where the mesh is defined by the parameters

- reg_lon_def: mesh latitudes in degrees,
- reg_lat_def: mesh longitudes in degrees,
- north_pole: definition of north pole for rotated lon-lat grids.

The regular grid points in reg_lon_def, reg_lat_def are each specified by three values, given in degrees: start, increment, end. The mesh then contains all grid points start + k * increment <= end, where k is an integer. Instead of defining an increment it is also possible to prescribe the number of grid points.

- Setting the namelist parameter reg_def_mode=0: Switch automatically from increment specification to no. of grid points, when the reg_lon/lat_def(2) value is larger than 5.0.
- 1: reg_lon/lat_def(2) specifies increment
- 2: reg_lon/lat_def(2) specifies no. of grid points

For longitude values the last grid point is omitted if the end point matches the start point, e.g. for 0 and 360 degrees.

Examples

local grid with 0.5 degree increment:

global grid with 720x361 grid points:

reg_lon_def = -30.,0.5,30. reg_lat_def = 90.,-0.5, -90.

reg_lon_def = 0.,720,360. reg_lat_def = -90.,360,90.

Time stamp format: The namelist parameters output_start, output_end, output_interval allow the specification of time stamps according to ISO 8601. The general format for time stamps is YYYY-MM-DDThh:mm:ss where Y: year, M: month, D: day for dates, and hh: hour, mm: minute, ss: second for time strings. The general format for durations is PnYnMnDTnHnMnS. See, for example, http://en.wikipedia.org/wiki/ISO_8601 for details and further specifications.

NOTE: as the mtime library underlaying the output driver currently has some restrictions concerning the specification of durations:

- 1. Any number n in PnYnMnDTnHnMnS must have two digits. For instance use "PT06H" instead of "PT6H"
- 2. In a duration string PnyearYnmonMndayDTnhrHnminMnsecS the numbers nxyz must not pass the carry over number to the next larger time unit: 0<=nmon<=12, 0<=nhr<=23, 0<=nmin<=59, 0<=nsec<=59.999. For instance use "PO1D" instead of "PT24H", or "PT01M" instead of "PT60S".

Soon the formatting problem will be resolved and the valid number ranges will be enlarged. (2013-12-16).

Examples

date and time representation (output_start, output_end)
duration (output_interval)

2013-10-27T13:41:00Z POODTO6HOOMOOS

Variable Groups

Keyword "group:": Using the "group:" keyword for the namelist parameters ml_varlist, hl_varlist, pl_varlist, sets of common variables can be added to the output:

group:all output of all variables (caution: do not combine with mixed vertical interpolation) basic atmospheric variables on model levels group:atmo_ml_vars same set as atmo ml vars, but except pres group:atmo_pl_vars same set as atmo ml vars, but expect height group:atmo_zl_vars additional prognostic variables of the nonhydrostatic model group:nh_prog_vars derived atmospheric variables group:atmo_derived_vars group:rad_vars group:precip_vars group:cloud_diag group:pbl_vars group:phys_tendencies group:land_vars snow variables group:snow_vars group:multisnow_vars multi-layer snow variables group:additional_precip_vars DWD first guess fields (atmosphere) group:dwd_fg_atm_vars group:dwd_fg_sfc_vars DWD first guess fields (surface/soil) group: ART_AERO_VOLC ART volcanic ash fields ART radioactive tracer fields group: ART_AERO_RADIO ART mineral dust aerosol fields group:ART_AERO_DUST ART sea salt aerosol fields group:ART_AERO_SEAS group:prog_timemean time mean output: temp, u, v, rho time mean output: qv, qc, qi group:tracer_timemean time mean output: most echam surface variables group:echam_timemean time mean variables from prog_timemean,tracer_timemean, echam_timemean group:atmo_timemean

Keyword "tiles:": The "tiles:" keyword allows to add all tiles of a specific variable to the output, without the need to specify all tile fields separately. E.g. "tiles:t_g" (read: "tiles of t_g ") automatically adds all t_g_t fields to the output. Here, X is a placeholder for the tile number. Make sure to specify the name of the aggregated variable rather than the name of the corresponding tile container (i.e. in the given example it must be t_g , and not t_g_t !).

Note:

There exists a special syntax which allows to remove variables from the output list, e.g. if these undesired variables were contained in a previously selected group. Typing "-<varname>" (for example "-temp") removes the variable from the union set of group variables and other selected variables. Note that typos are not detected but that the corresponding variable is simply not removed!

Keyword substitution in output filename (filename_format):

substituted by model_base_dir
output_filename
substituted by output_filename
substituted by physical patch ID
substituted by level type "ML", "PL", "HL", "IL"
levtype_l
like levtype, but in lower case
jfile substituted by output file counter
datetime substituted by ISO-8601 date-time stamp in format YYYY-MM-DDThh:mm:ss.sssZ

datetime2
datetime3
ddhhmmss
dddhhmmss
hhhmmss
npartitions
ifile_partition
total_index

substituted by ISO-8601 date-time stamp in format YYYYMMDDThhmmssZ substituted by ISO-8601 date-time stamp in format YYYYMMDDThhmmss.sssZ substituted by relative day-hour-minute-second string substituted by relative three-digit day-hour-minute-second string substituted by relative hour-minute-second string If namelist is split into concurrent files: number of stream partitions. If namelist is split into concurrent files: stream partition index of this file. If namelist is split into concurrent files: substituted by the file counter (like in jfile), which an "unsplit" namelist would have produced

2.32. parallel_nml

Parameter	Type	Default	Unit	Description	Scope
nproma	I	1		chunk length	
n_ghost_rows	I	1		number of halo cell rows	
division_method	I	1		method of domain decomposition	
				0: read in from file	
				1: use built-in geometric subdivision	
division_file_name	C			Name of division file	$division_method = 0$
ldiv_phys_dom	L	.TRUE.		.TRUE.: split into physical domains before	$division_method = 1$
				computing domain decomposition (in case of	
				merged domains)	
				(This reduces load imbalance; turning off this	
				option is not recommended except for very small	
				processor numbers)	
p_test_run	L	.FALSE.		.TRUE. means verification run for MPI	
				parallelization (PE 0 processes full domain)	
num_test_pe	I	-1		If set to more than 1, use this many ranks for	$p_{test_run} = .TRUE.$
				testing and switch to different consistency test.	
				This enables tests for identity in setups which	
				are too big to run on a single rank but is limited	
				to comparing one MPI parallelization setup vs.	
				another, obviously.	
l_test_openmp	L	.FALSE.		if .TRUE. is combined with	$p_{test_run} = .TRUE.$
				p_test_run=.TRUE. and OpenMP	
				parallelization, the test PE gets only 1 thread in	
				order to verify the OpenMP parallelization	
l_log_checks	L	.FALSE.		if .TRUE. messages are generated during each	
				synchonization step (use for debugging only)	
l_fast_sum	L	.FALSE.		if .TRUE., use fast (not	
				processor-configuration-invariant) global	
				summation	
use_dycore_barrier	L	.FALSE.		if .TRUE., set an MPI barrier at the beginning	
				of the nonhydrostatic solver (do not use for	
				production runs!)	
itype_exch_barrier	I	0		1: set an MPI barrier at the beginning of each	
				MPI exchange call	
				2: set an MPI barrier after each MPI WAIT call	
				3: 1+2 (do not use for production runs!)	
iorder_sendrecv	I	1		Sequence of send/receive calls:	
				1 = irecv/send	
				2 = isend/recv	
				3 = isend/irecv	

$2.33.\ psrad_nml$

Parameter	Type	Default	Unit	Description	Scope
lradforcing	L(2)	.FALSE.		switch for diagnostics of aerosol forcing in the	
				solar spectral range (lradforcing (1)) and the	
				thermal spectral range (lradforcing (2)).	
lw_gpts_ts	I	1		number of g-points in Monte-Carlo spectral	
				integration for thermal radiation, see	
				lw_spec_samp	
lw_spec_samp	I	1		sampling of spectral bands in radiation	
				calculation for thermal radiation	
				$lw_spec_samp = 1$: standard broad band	
				sampling	
				lw_spec_samp = 2: Monte-Carlo spec- tral	
				integration (MSCI); lw_gpts_ts randomly	
				chosen g-points per column and radiation call	
				lw_spec_samp = 3: choose g-points not	
				completely randomly in order to reduce errors in	
				the surface radiative fluxes	
rad_perm	I	0		integer number that influences the perturba-	
				tion of the random seed from column to column	
sw_gpts_ts	I	1		number of g-points in Monte-Carlo spectral	
				integration for solar radiation, see	
				sw_spec_samp	
sw_spec_samp	1	1		sampling of spectral bands in radiation	
				calculation for solar radiation	
				$sw_spec_samp = 1$: standard broad band	
				sampling	
				sw_spec_samp = 2: Monte-Carlo spectral	
				integration (MSCI); lw_gpts_ts randomly	
				chosen g-points per column and radiation call	
				sw_spec_samp = 3: choose g-points not	
				completely randomly in order to reduce errors in	
				the surface radiative fluxes	

Defined and used in: src/echam_phy_psrad/mo_psrad_radiation.f90

2.34. radiation_nml

Parameter	Type	Default	Unit	Description	Scope
ldiur	L	.TRUE.		switch for solar irradiation:	
				.TRUE.:diurnal cycle,	
				.FALSE.:zonally averaged irradiation	

Parameter	Type	Default	Unit	Description	Scope
nmonth	I	0		0: Earth circles on orbit	
				1-12: Earth orbit position fixed for specified	
				month	
lyr_perp	L	.FALSE.		.FALSE.: transient Earth orbit following	
v <u>_</u> 1 1				VSOP87	
				.TRUE.: Earth orbit of year yr perp of the	
				VSOP87 orbit is perpertuated	
yr_perp	\mid L	-99999		year used for lyr perp = .TRUE.	
isolrad	I	0		Insolation scheme	
isonad	1			0: Use original SRTM insolation.	
				1: Use insolation from external file containing	
				the spectrally resolved insolation (monthly	
				means)	
				2: Use preindustrial insolation as in CMIP5	
				(average from 1844–1856)	1
				3: Use insolation for AMIP-type CMIP5	1
				simulation (average from 1979–1988)	
				4: Use insolation for RCE-type simulation with	
				$\cos(\text{zenith angle}) = \text{pi}/4 \text{ (with PSRAD: use "4")}$	
				if the diurnal cycle is switched on)	
				5: Use insolation for RCE-type simulation with	
				PSRAD if the diurnal cycle is switched off.	
izenith	I	4		Choice of zenith angle formula for the radiative	
				transfer computation.	
				0: Sun in zenith everywhere	
				1: Zenith angle depends only on latitude	
				2: Zenith angle depends only on latitude. Local	
				time of day fixed at 07:14:15 for radiative	
				transfer computation ($\sin(\text{time of day}) = 1/\text{pi}$	
				3: Zenith angle changing with latitude and time	
				of day	
				4: Zenith angle and irradiance changing with	
				season, latitude, and time of day (iforcing=inwp	
				only)	
islope_rad	I	0		Slope correction for surface radiation:	
				0: None	
				1: Slope correction for direct solar radiation	
				without shading effects	
$albedo_type$	I	1		Type of surface albedo	iforcing=inwp
				1: based on soil type specific tabulated values	
				(dry soil)	
				2: MODIS albedo	

Parameter	Type	Default	Unit	Description	Scope
direct_albedo	Iype I	4	Unit	Direct beam surface albedo. Options mainly differ in terms of their solar zenith angle (SZA) dependency) 1: SZA dependency following Ritter-Geleyn; applied to unconditionally all grid points 2: SZA dependency following Zaengl (pers. comm.). Same as 1 for water, but for 'rough surfaces' over land the direct albedo is not allowed to exceed the corresponding broadband diffuse albedo. 3: SZA dependency following Yang (2008) for snow-free land points. Same as 1 for water/ice	iforcing=inwp albedo_type=2
$icld_overlap$	I	2		and 2 for snow. 4: SZA dependency following Briegleb (1992) for snow-free land points. Same as 1 for water/ice and 2 for snow. Method for cloud overlap calculation in shortwave part of RRTM 1: maximum-random overlap 2: generalized overlap (Hogan, Illingworth, 2000) 3: maximum overlap 4: random overlap	iforcing=inwp inwp_radiation=1

Parameter	Type	Default	Unit	Description	Scope
irad_h2o	I	1		Switches for the concentration of radiative agents	
irad_co2		2		$irad_xyz = 0$: set to zero	
irad_ch4		3		irad_h2o = 1: vapor, cloud water and cloud ice	
irad n2o		3		from tracer variables	
irad o3		0		irad $co2 = 1$: CO_2 from tracer variable	
irad o2		2		irad co2/ch4/n2o/o2/cfc11/cfc12 = 2:	
irad cfc11		2		concentration given by	
irad_cfc12		2		vmr $co2/ch4/n2o/o2/cfc11/cfc12$	
_				$\frac{1}{1}$ irad $\frac{1}{1}$ ch4/n2o = 3: tanh-profile with surface	
				concentration given by vmr ch4/n2o	
				irad $co2/cfc11/cfc12 = 4$: time dependent	
				concentration from greenhouse gas file	
				irad $ch4/n2o = 4$: time dependent tanh-profile	
				with surface concentration from greenhouse gas	
				file irad $o3 = 2$: ozone climatology from MPI	
				irad o3 = 4: ozone clim for Aqua Planet Exp	
				$\frac{1}{1}$ irad $\frac{1}{1}$ of $\frac{1}{1}$ irad $\frac{1}$	
				geographical distribution and Fourier series for	
				seasonal cycle for run nml/iforcing = 3 (NWP)	
				irad o3 = 7: GEMS ozone climatology (from	
				IFS) for run nml/iforcing = 3 (NWP)	
				irad o3 = 8: ozone climatology for AMIP	
				$a_0 = 0$ ozone chimatology for AMII irad $a_0 = 0$: MACC ozone climatology (from	
				IFS) for run nml/iforcing = 3 (NWP)	
				irad_o3 = 79: Blending between GEMS and	
				MACC ozone climatologies (from IFS) for	
				$run_nml/iforcing = 3 (NWP); MACC is used$	
				over Antarctica	
				irad_o3 = 97: As 79, but MACC is also used	
				above 1 hPa with transition zone between 5 hPa	
				and 1 hPa	
				irad_o3 = 10: Linearized ozone chemistry (ART	
				extension necessary) for run_nml/iforcing = 3	
2		240.0		(NWP)	
vmr_co2	R	348.0e-6		Volume mixing ratio of the radiative agents	
vmr_ch4		1650.0e-9			
vmr_n2o		306.0e-9			
vmr_02		0.20946			
vmr_cfc11		214.5e-12			
vmr_cfc12		371.1e-12			

Parameter	Type	Default	Unit	Description	Scope
fh2o	R	1.		Scaling factors for concentrations used in	run_nml/iforcing=2
fco2		1.		radiation	(ECHAM)
fch4		1.			
fn2o		1.			
fo3		1.			
fo2		1.			
fcfc		1.			
irad_aero	I	2		Aerosols 1: prognostic variable	
				2: global constant	
				3: externally specified	
				5: Tanre aerosol climatology for	
				$run_nml/iforcing = 3 (NWP)$	
				6: Tegen aerosol climatology for	
				run $nml/iforcing = 3 (NWP)$. AND. itopo =1	
				9: ART online aerosol radiation interaction, uses	
				Tegen for aerosols not chosen to be represented	
				in ART for $run_nml/iforcing = 3$ (NWP) .AND.	
				itopo =1 .AND. lart=TRUE .AND. iart_ari=1	
lrad_aero_diag	L	.FALSE.		writes actual aerosol optical properties to output	
ighg	I	0		Select dynamic greenhouse gases scenario (read	$run_nml/iforcing=2$
				from file)	(ECHAM)
				0 : select default gas volume mixing ratios - 1990	
				values (CMIP5)	
				1: transient CMIP5 scenario from file	

Defined and used in: src/namelists/mo_radiation_nml.f90

2.35. run_nml

Parameter	Type	Default	Unit	Description	Scope
nsteps	I	-999		Number of time steps of this run. Allowed range	
				is ≥ 0 ; setting a value of 0 allows writing initial	
				output (including internal remapping) without	
				calculating time steps.	

Parameter	Type	Default	Unit	Description	Scope
dtime	R	600.0	S	time step.	
				For real case runs the maximum allowable time	
				step can be estimated as	
				$1.8 \cdot \text{ndyn substeps} \cdot \overline{\Delta x} \text{s km}^{-1}$,	
				where $\frac{\sqrt{x}}{\Delta x}$ is the average resolution in km and	
				ndyn substeps is the number of dynamics	
				substeps set in nonhydrostatic nml.	
				ndyn substeps should not be increased beyond	
				the default value 5.	
ltestcase	т	.TRUE.		Idealized testcase runs	
	L				
ldynamics	L	.TRUE.		Compute adiabatic dynamic tendencies	
iforcing	I	0		Forcing of dynamics and transport by	
				parameterized processes. Use positive indices for	
				the atmosphere and negative indices for the	
				ocean.	
				0: no forcing	
				1: Held-Suarez forcing	
				2: ECHAM forcing	
				3: NWP forcing	
				4: local diabatic forcing without physics	
				5: local diabatic forcing with physics	
				-1: MPIOM forcing (to be done)	
ltransport	L	.FALSE.		Compute large-scale tracer transport	
ntracer	I	0		Number of advected tracers handled by the	
	•			large-scale transport scheme	
lvert nest	\mid L	.FALSE.		If set to .true. vertical nesting is switched on	
1,01,0 _ 11000		.171101.		(i.e. variable number of vertical levels)	
num lev	I(max	31		Number of full levels (atm.) for each domain	lvert_nest=.TRUE.
num_iev	$egin{array}{c} I(\max_\\ \mathrm{dom}) \end{array}$	91		rumber of full levels (atm.) for each domain	Ivert_nest=.IRUE.
nshift	I(max_	0		vertical half level of parent domain which	lvert nest=.TRUE.
	dom			coincides with upper boundary of the current	_
	'			domain required for vertical refinement, which is	
				not yet implemented	
ltimer	L	.TRUE.		TRUE: Timer for monitoring the runtime of	
		12202		specific routines is on (FALSE = off)	
timers level	1	1		specific routines is on (Triboti — on)	
_		F		TRUE: Timer for monitoring runtime of	
activate_sync_timers	"	I I		communication routines (FALSE = off)	
man lavel	т	10			
msg_level	I	10		controls how much printout is written during	
				runtime.	
				For values less than 5, only the time step is	
				written.	
$msg_timestamp$	L	.FALSE.		If .TRUE., precede output messages by time	
		1		stamp.	

Parameter	Type	Default	Unit	Description	Scope
test_mode debug_check_level output	I C(:)	0 "nml", "totint"		Setting a value larger than 0 activates a dummy mode in which time stepping is changed into just doing iterations, and MPI communication is replaced by copying some value from the send buffer into the receive buffer (does not work with nesting and reduced radiation grid because the send buffer may then be empty on some PEs) Setting a value larger than 0 activates debug checks. Main switch for enabling/disabling components of the model output. One or more choices can be set (as an array of string constants). Possible choices are: • "none": switch off all output; • "nml": new output mode (cf. output_nml); • "totint": computation of total integrals. • "maxwinds": write max. winds to separate ASCII file "maxwinds.log". If the output namelist parameter is not set explicitly, the default setting "nml", "totint" is	iequations = 3
restart_filename	С			assumed. File name for restart/checkpoint files (containing keyword substitution patterns <gridfile>, <idom>, <rsttime>, <mtype>). default: "<gridfile>_restart_<mtype>_<rsttime>.nc".</rsttime></mtype></gridfile></mtype></rsttime></idom></gridfile>	
profiling_output	I	1		controls how profiling printout is written: TIMER_MODE_AGGREGATED=1, TIMER_MODE_DETAILED=2, TIMER_MODE_WRITE_FILES=3.	
lart	L	.FALSE.		Main switch which enables the treatment of atmospheric aerosol and trace gases (The ART package of KIT is needed for this purpose)	
ldass_lhn	L	.FALSE.		Main switch which enables the assimilation of radar derived precipitation rate via Latent Heat Nudging	
check_uuid_gracefully	L	.FALSE.		If this flag is set to .TRUE. we give only warnings for non-matching UUIDs.	

Defined and used in: src/namelists/mo_run_nml.f90

2.36. sleve_nml (relevant if nonhydrostatic_nml:ivctype=2)

Parameter	Type	Default	Unit	Description	Scope
min_lay_thckn	R	50	m	Layer thickness of lowermost layer; specifying	
				zero or a negative value leads to constant layer	
				thicknesses determined by top_height and nlev	
max_lay_thckn	R	25000	m	Maximum layer thickness below the height given	
				by htop_thcknlimit (NWP recommendation:	
				400 m)	
				Use with caution! Too ambitious settings may	
				result in numerically unstable layer	
				configurations.	
htop_thcknlimit	R	15000	m	Height below which the layer thickness does not	
				exceed max_lay_thckn	
itype_laydistr	I	1		Type of analytical function used to specify the	
				distribution of the vertical coordinate surfaces	
				1: transformed cosine, 2: third-order polynomial	
top_height	R	23500.0	m	Height of model top	
stretch_fac	R	1.0		Stretching factor to vary distribution of model	
				levels; values <1 increase the layer thickness	
				near the model top	
decay_scale_1	R	4000	m	Decay scale of large-scale topography component	
decay_scale_2	R	2500	m	Decay scale of small-scale topography component	
decay_exp	R	1.2		Exponent of decay function	
flat_height	R	16000	m	Height above which the coordinate surfaces are	
				flat	
lread_smt	L	.FALSE.		read smoothed topography from file (TRUE) or	
				compute internally (FALSE)	

Defined and used in: src/namelists/mo_sleve_nml.f90

2.37. synsat nml¹

This namelist enables the RTTOV library incorporated into ICON for simulating satellite radiance and brightness temperatures. RTTOV is a radiative transfer model for nadir-viewing passive visible, infrared and microwave satellite radiometers, spectrometers and interferometers, see

https://nwpsaf.eu/deliverables/rtm

for detailed information.

Parameter	Type	Default	Unit	Description	Scope
lsynsat	L	.FALSE.		Main switch: Enables/disables computation	on of
	(max_don	\mathbf{n}		synthetic satellite imagery for each model	
				domain.	
nlev_rttov	I	51		Number of RTTOV levels.	

¹Important note: This feature is currently active for configuration dwd+cray only.

Enabling the synsat module makes the following 32 two-dimensional output fields available:

SYNMSG_RAD_CL_IR3.9	SYNMSG_BT_CL_IR3.9	SYNMSG_RAD_CL_WV6.2	SYNMSG_BT_CL_WV6.2
SYNMSG_RAD_CL_WV7.3	SYNMSG_BT_CL_WV7.3	SYNMSG_RAD_CL_IR8.7	SYNMSG_BT_CL_IR8.7
SYNMSG_RAD_CL_IR9.7	SYNMSG_BT_CL_IR9.7	SYNMSG_RAD_CL_IR10.8	SYNMSG_BT_CL_IR10.8
SYNMSG_RAD_CL_IR12.1	SYNMSG_BT_CL_IR12.1	SYNMSG_RAD_CL_IR13.4	SYNMSG_BT_CL_IR13.4
SYNMSG_RAD_CS_IR3.9	SYNMSG_BT_CS_IR3.9	SYNMSG_RAD_CS_WV6.2	SYNMSG_BT_CS_WV6.2
SYNMSG_RAD_CS_WV7.3	SYNMSG_BT_CS_WV7.3	SYNMSG_RAD_CS_IR8.7	SYNMSG_BT_CS_IR8.7
SYNMSG_RAD_CS_IR9.7	SYNMSG_BT_CS_IR9.7	SYNMSG_RAD_CS_IR10.8	SYNMSG_BT_CS_IR10.8
SYNMSG_RAD_CS_IR12.1	SYNMSG_BT_CS_IR12.1	SYNMSG_RAD_CS_IR13.4	SYNMSG_BT_CS_IR13.4

Here, RAD denotes radiance, BT brightness temperature, CL cloudy, and CS clear sky, supplemented by the channel name. Defined and used in: $src/namelists/mo_synsat_nml.f90$

$2.38.\ time_nml$

Parameter	Type	Default	Unit	Description	Scope
calendar	I	1		Calendar type:	
				0=Julian/Gregorian	
				1=proleptic Gregorian	
				2=30day/month, 360 day/year	
dt_restart	R	86400.*30.	S	Length of restart cycle in seconds. This namelist	
				parameter specifies how long the model runs	
				until it saves its state to a file and stops. Later,	
				the model run can be resumed, s. t. a simulation	
				over a long period of time can be split into a	
				chain of restarted model runs.	
				Note that the frequency of writing restart files is	
				controlled by io_nml:dt_checkpoint. Only if	
				the value of dt_checkpoint resulting from	
				model default or user's specification is longer	
				than dt_restart, it will be reset (by the model)	
				to dt_restart so that at least one restart file is	
				generated during the restart cycle. If	
				dt_restart is larger than but not a multiple of	
				dt_checkpoint, restart file will not be	
		10000 00 01 5		generated at the end of the restart cycle.	
ini_datetime_string	C	'2008- 09-01T		Initial date and time of the simulation	
		00:00:00Z'			
end_datetime_string	C	'2008- 09-01T		End date and time of the simulation	
		01:40:00Z'			

Parameter	Type	Default	Unit	Description	Scope
is_relative_time	L	.FALSE.		.TRUE., if time loop shall start with step 0	
				regardless whether we are in a standard run or in	
				a restarted run (which means re-initialized run).	

Length of the run If "nsteps" in run_nml is positive, then nsteps*dtime is used to compute the end date and time of the run. Else the initial date and time, the end date and time, dt_restart, as well as the time step are used to compute "nsteps".

$2.39.\ transport_nml\ (used\ if\ run_nml/ltransport=.TRUE.)$

Parameter	Type	Default	Unit	Description	Scope
lvadv_tracer ihadv_tracer	L I(ntracer)	.TRUE.		TRUE: compute vertical tracer advection FALSE: do not compute vertical tracer advection Tracer specific method to compute horizontal advection: 0: no horiz. transport (note that the specific tracer quantity q is kept constant and not tracer	-
				 mass ρq) 1: upwind (1st order) 2: Miura (2nd order, linear reconstr.) 3: Miura3 (quadr. or cubic reconstr.) 4: FFSL (quadr. or cubic reconstr.) 5: hybrid Miura3/FFSL (quadr. or cubic reconstr.) 20: miura (2nd order, lin. reconstr.) with subcycling 	$\begin{aligned} & \operatorname{lsq_high_ord} \in [2,3] \\ & \operatorname{lsq_high_ord} \in [2,3] \\ & \operatorname{lsq_high_ord} \in [2,3] \end{aligned}$
				22: combination of miura and miura with subcycling 32: combination of miura3 and miura with subcycling 42: combination of FFSL and miura with subcycling 52: combination of hybrid FFSL/Miura3 with subcycling	
ivadv_tracer	I(ntracer)	3		Subcycling means that the integration from time step n to n+1 is splitted into substeps to meet the stability requirements. For NWP runs, substepping is generally applied above $z=22\mathrm{km}$ (see nonhydrostatic_nml/hbot_qvsubstep). Tracer specific method to compute vertical advection: 0: no vert. transport (note that tracer mass ρq instead of the specific tracer quantity q is kept	$lvadv_tracer{=}TRUE$
iadv_tke	I	0 .FALSE.		constant. This differs from the behaviour in horizontal direction!) 1: upwind (1st order) 3: ppm_cfl (3 rd order, handles CFL > 1) 30: ppm (3rd order, CFL<=1) Type of TKE advection 0: no TKE advection 1: vertical advection only 2: vertical and horizontal advection Time splitting method	$inwp_turb{=}1$

Parameter	Type	Default	Unit	Description	Scope
				TRUE: second order Strang splitting	
				FALSE: first order Godunov splitting	
tracer_names	C(:)	'Int2Str(i)'		Tracer-specific name suffixes. When running	iforcing≠ inwp, iecham'
				idealized cases or the hydrostatic ICON, this	
				variable is used to specify tracer names. If	
				nothing is specified, the tracer name is given as	
				PREFIX+Int2String(i), where i is the tracer	
				index. Note that this namelist variable has no	
				effect for nonhydrostatic real-case runs, if the	
				NWP- or ECHAM physics packages are switched	
				on.	
npassive_tracer	I	0		number of additional passive tracers which have	
				no sources and are transparent to any physical	
				process (no effect).	
				Passive tracers are named Qpassive ID, where	
				ID is a number between ntracer and	
				ntracer+npassive_tracer.	
				NOTE: By default, limiters are switched of for	
				passive tracers and the scheme 52 is selected for	
				horizontal advection.	
init formula	C	, ,		Comma-separated list of initialization formulas	npassive tracer > 0
				for additional passive tracers.	inpublic_tracer > 0
itype_hlimit	I(ntracer)	4		Type of limiter for horizontal transport:	
rtype_mmit	I(IIII acci)			0: no limiter	
				3: monotonous flux limiter	
				4: positive definite flux limiter	
itype_vlimit	I(ntracer)	1		Type of limiter for vertical transport:	
type_viiiit	I(IItiacei)	1		0: no limiter	
				1: semi-monotone slope limiter	
				2: monotonous slope limiter	
				4: positive definite flux limiter	
hote fat	D	1.005		4: positive definite flux finiter factor of allowed over-/undershooting in	itama hlimit - 2
beta_fct	R	1.005		monotonous limiter	$itype_hlimit = 3$
iord bagktrai	I	1		order of backward trajectory calculation:	
iord_backtraj		1		1: first order	
					ihady tracon- 'mi-ma'
				2: second order (iterative; currently 1 iteration	ihadv_tracer='miura'
:	т	1		hardcoded; experimental!)	
igrad_c_miura	I	1		Method for gradient reconstruction at cell center	
				for 2nd order miura scheme	.1 1 2
				1: Least-squares (linear, non-consv)	ihadv_tracer=2
				2: Green-Gauss	
ivcfl_max	I	5		determines stability range of vertical	ivadv_tracer=3
				PPM-scheme in terms of the maximum allowable	
				CFL-number	

Parameter	Type	Default	Unit	Description	Scope
llsq_svd	L	.TRUE.		use QR decomposition (FALSE) or SV	
				decomposition (TRUE) for least squares design	
				matrix A	
lclip_tracer	L	.FALSE.		Clipping of negative values	

Defined and used in: src/namelists/mo_advection_nml.f90

$2.40.\ turbdiff_nml$

Parameter	Type	Default	Unit	Description	Scope
imode_turb	I	1		Mode of solving the TKE equation for atmosph.	
				layers:	
				0: diagnostic equation	
				1: prognostic equation (current version)	
				2: prognostic equation (intrinsically positive	
				definite)	
imode_tran	I	0		Same as $imode_turb$ but only for the transfer	
				layer	
icldm_turb	I	2		Mode of water cloud representation in	
				turbulence for atmosph. layers:	
				-1: ignoring cloud water completely (pure dry	
				scheme)	
				0: no clouds considered (all cloud water is	
				evaporated)	
				1: only grid scale condensation possible	
				2: also sub grid (turbulent) condensation	
	_			considered	
icldm_tran	1	2		Same as $icldm_turb$ but only for the transfer	
.,	D.	1.0		layer	
q_crit	R	1.6		critical value for normalized super-saturation	
itype_wcld	1	2		type of water cloud diagnosis within the	icldm_turb=2 or
				turbulence scheme:	icldm_tran=2
				1: employing a scheme based on relative humitidy	
				ů.	
ityma shar	т			2: employing a statistical saturation adjustment Type of shear forcing used in turbulence:	
itype_sher	1	0		0: only vertical shear of horizontal wind	
				1: previous plus horizontal shear correction	
				2: previous plus shear from vertical velocity	
				3: same as option 1, but (when combined with	
				ltkeshs=.TRUE.) scaling of coarse-grid	
				horizontal shear production term with $\frac{1}{\sqrt{Ri}}$	
	I		I	\sqrt{Ri}	

Parameter	Type	Default	Unit	Description	Scope
ltkeshs	L	.FALSE.		Include correction term for coarse grids in horizontal shear production term (needed at non-convection-resolving model resolutions in	itype_sher ≥ 1
ltkesso	L	.TRUE.		order to get a non-negligible impact) Consider TKE-production by sub grid SSO wakes	$inwp_sso = 1$
$imode_tkesso$	I	1		mode of calculat. the SSO source term for TKE production: 1: original implementation 2: Ri-dependent reduction factor for Ri>1	
ltkecon	L	.FALSE.		Consider TKE-production by sub grid convective plumes (inactive)	$inwp_conv = 1$
ltkeshs	L	.FALSE.		Consider TKE-production by separated horizontal shear eddies (inactive)	
ltmpcor	L	.FALSE.		Consider thermal TKE sources in enthalpy equation	
lsflend	L	.TRUE.		Use lower flux condition for vertical diffusion calculation (TRUE) instead of a lower concentration condition (FALSE)	
lexpcor	L	.FALSE.		Explicit corrections of implicitly calculated vertical diffusion of non-conservative scalars that are involved in sub grid condensation processes	
tur _len	R	500.0	m	Asymptotic maximal turbulent distance $(\kappa * tur_len$ is the integral turbulent master length scale)	
pat_len	R	100.0	m	Effective length scale of thermal surface patterns controlling TKE-production by sub grid kata/ana-batic circulations. In case of pat $len = 0$, this production is switched off.	
c_{diff}	R	0.2	1	Length scale factor for vertical diffusion of TKE. In case of $c_diff = 0$, TKE is not diffused vertically.	
a_stab	R	0.0	1	Factor for stability correction of turbulent length scale. In case of $a_stab = 0$, the turbulent length scale is not reduced for stable stratification.	
a_hshr	R	0.20	1	Length scale factor for the separated horizontal shear mode. In case of $a_hshr = 0$, this shear mode has no effect.	ltkeshs=.TRUE.
alpha0	R	0.0123	1	Lower bound of velocity-dependent Charnock parameter	
alpha0_max	R	0.0335	1	Upper bound of velocity-dependent Charnock parameter. Setting this parameter to 0.0335 or higher values implies unconstrained velocity dependence	

Parameter	Type	Default	Unit	Description	Scope
alpha1	R	0.75	1	Scaling parameter for molecular roughness of	
tkhmin	R	0.75	m^2/s	ocean waves Scaling factor for minimum vertical diffusion coefficient (proportional to $Ri^{-2/3}$) for heat and	
tkmmin	R	0.75	m^2/s	moisture Scaling factor for minimum vertical diffusion coefficient (proportional to $Ri^{-2/3}$) for	
tkmmin_strat	R	4	m^2/s	momentum Scaling factor for stratospheric minimum vertical diffusion coefficient (proportional to $Ri^{-1/3}$) for momentum, valid above 17.5 km (tropics above	
tkhmin_strat	R	0.75	m^2/s	22.5 km) Scaling factor for stratospheric minimum vertical diffusion coefficient (proportional to $Ri^{-1/3}$) for heat and moisture, valid above 17.5 km (tropics above 22.5 km)	
itype_synd	I	2		Type of diagnostics of synoptic near surface variables:1: Considering the mean surface roughness of a grid box2: Considering a fictive surface roughness of a	
rlam_heat	R	1.0	1	SYNOP lawn Scaling factor of the laminar boundary layer for heat (scalars). The larger rlam_heat, the larger is the laminar resistance.	
rat_sea	R	10.0	1	Ratio of laminar resistance. Ratio of laminar scaling factors for scalars over sea and land. The larger rat_sea, the larger is the laminar resistance for a sea surface compared to a land surface.	
tkesmot	R	0.15	1	Time smoothing factor within $[0, 1]$ for TKE. In case of $tkesmot = 0$, no smoothing is active.	
fresmot	R	0.0	1	Vertical smoothing factor within $[0, 1]$ for TKE forcing terms. In case of $frcmot = 0$, no smoothing is active.	
$imode_frcsmot$	I			1 = apply vertical smoothing (if frcsmot>0) uniformly over the globe 2 = restrict vertical smoothing to the tropics (reduces the moist bias in the tropics while avoiding adverse effects on NWP skill scores in the extratropics)	
impl_s	R	1.20	1	Implicit weight near the surface (maximal value)	
impl_t	R	0.75	1	Implicit weight near top of the atmosphere (minimal value)	
lconst_z0	L	.FALSE.		TRUE: horizontally homogeneous roughness length z0	

Parameter	Type	Default	Unit	Description	Scope
const_z0	R	0.001	m	value for horizontally homogeneous roughness	lconst_z0=.TRUE.
				length z0	
ldiff_qi	L	.FALSE.		Turbulent diffusion of cloud ice, if .TRUE.	
itype_tran	I	2		type of surface-atmosphere transfer	
lprfcor	L	.FALSE.		using the profile values of the lowest main level	
				instead of the mean value of the lowest layer for	
				surface flux calculations	
lnonloc	L	.FALSE.		nonlocal calculation of vertical gradients used for	
				turbul. diff.	
lfreeslip	L	.FALSE.		.TRUE.: use a free-slip lower boundary	
				condition, i.e. neither momentum nor	
				heat/moisture fluxes (use for idealized runs	
				only!)	
lepflue	L	.FALSE.		consideration of fluctuations of the heat capacity	
				of air	

Defined and used in: src/namelists/mo_turbdiff_nml.f90

3. Ocean-specific namelist parameters

3.1. ocean_physics_nml

Parameter	Type	Default	Unit	Description	Scope
i_sea_ice	I	1		0: No sea ice, 1: Include sea ice	
				.FALSE.: compute drag only	
richardson_factor_tracer	I	0.5e-5	m/s		
richardson_factor_veloc	I	0.5e-5	m/s		
l_constant_mixing	L	.FALSE.			

3.2. sea_ice_nml (relevant if run_nml/iforcing=2 (ECHAM))

Parameter	Type	Default	Unit	Description	Scope
i_ice_therm	I	2		Switch for thermodynamic model:	In an ocean run i_sea_ice
				1: Zero-layer model	must be $\geq =1$. In an
				2: Two layer Winton (2000) model	atmospheric run the ice surface
				3: Zero-layer model with analytical forcing (for	type must be defined.
				diagnostics)	
				4: Zero-layer model for atmosphere-only runs	
				(for diagnostics)	
i_ice_dyn	I	0		Switch for sea-ice dynamics:	
				0: No dynamics	
				1: FEM dynamics (from AWI)	

Parameter	Type	Default	Unit	Description	Scope
i_ice_albedo	I	1		Switch for albedo model. Only one is	
				implemented so far.	
i_Qio_type	I	2		Switch for ice-ocean heat-flux calculation	Defaults to 1 when
				method:	i_ice_dyn=0 and 2 otherwise.
				1: Proportional to ocean cell thickness (like	
				MPI-OM)	
				2: Proportional to speed difference between ice	
				and ocean	
kice	I	1		Number of ice classes (must be one for now)	
hnull	R	0.5	m	Hibler's h_0 parameter for new-ice growth.	
hmin	R	0.05	m	Minimum sea-ice thickness allowed.	
ramp_wind	R	10	days	Number of days it takes the wind to reach	
				correct strength. Only used at the start of an	
				OMIP/NCEP simulation (not after restart).	

4. Namelist parameters for testcases (NAMELIST_ICON)

The ICON model code includes several experiments, so-called test cases, for the shallow water model as well as the 3-dimensional atmosphere. Depending on the specified experiment, initial conditions and boundary conditions are computed internally.

4.1. ha_testcase_nml (Scope: ltestcase=.TRUE. and iequations=[0,1,2] in run_nml)

Parameter	Type	Default	Unit	Description	Scope
ctest_name	С	'JWw'		Name of test case:	
				'SW_GW': gravity wave	$lshallow_water=.TRUE.$
				'USBR': unsteady solid body rotation	$lshallow_water=.TRUE.$
				'Will_2': Williamson test 2	$lshallow_water=.TRUE.$
				'Will_3': Williamson test 3	$lshallow_water=.TRUE.$
				'Will 5': Williamson test 5	lshallow water=.TRUE.
				'Will 6': Williamson test 6	lshallow water=.TRUE.
				'GW': gravity wave (nlev=20 only!)	lshallow water=.FALSE.
				'LDF': local diabatic forcing test without physics	lshallow_water=.FALSE.
					and iforcing=4
				'LDF-Moist': local diabatic forcing test with	lshallow_water=.FALSE.,
				physics initalised with zonal wind field	and iforcing=5
				'HS': Held-Suarez test	lshallow_water=.FALSE.
				'JWs': Jablonowski-Will. steady state	$lshallow_water=.FALSE.$
				'JWw': Jablonowski-Will. wave test	$lshallow_water=.FALSE.$
				'JWw-Moist': Jablonowski-Will. wave test	$lshallow_water=.FALSE.$
				including moisture	
				'APE': aqua planet experiment	lshallow_water=.FALSE.
				'MRW': mountain induced Rossby wave	lshallow_water=.FALSE.
				'MRW2': modified mountain induced Rossby	lshallow_water=.FALSE.
				wave	

Parameter	Type	Default	Unit	Description	Scope
				'PA': pure advection 'SV': stationary vortex	lshallow_water=.FALSE. lshallow_water=.FALSE., ntracer = 2
				'DF1': deformational flow test 1 'DF2': deformational flow test 2 'DF3': deformational flow test 3 'DF4': deformational flow test 4	
tracer_inidist_list	I(:)	1		'RH': Rossby-Haurwitz wave test For a subset of testcases pre-defined initial tracer distributions are available. This namelist parameter specifies the initial distribution for each tracer. In the following the testcases and the pre-defined numbers are given: 'PA': 4,5,6,7,8 'JABW':1,2,3,4 'DF': 5,6,7,8,9	lshallow_water=.FALSE. ha_testcase_nml='PA', 'JABW','DF'
rotate_axis_deg	R	0.0	deg	For more details on the initial distributions, please have a look into the code. Earth's rotation axis pitch angle	ctest_name= 'Will_2', 'Will_3', 'JWs', 'JWw', 'PA', 'DF1234'
gw brunt vais	R	0.01	1/s	Brunt Vaisala frequency	ctest name= 'GW'
gw u0	R	0.0	m m/s	zonal wind parameter	ctest name= 'GW'
gw_lon_deg	R	180.0	deg	longitude of initial perturbation	ctest_name= 'GW'
gw lat deg	R	0.0	\deg	latitude of initial perturbation	ctest name= 'GW'
jw_uptb	R	1.0	m/s (?)	amplitude of the wave pertubation	ctest name= 'JWw'
mountctr lon deg	R	90.0	deg	longitude of mountain peak	ctest name= 'MRW(2)'
mountctr lat deg	R	30.0	deg	latitude of mountain peak	ctest name= 'MRW(2)'
mountctr height	R	2000.0	m	mountain height	ctest name= 'MRW(2)'
mountctr half width	R	1500000.0	m	mountain half width	ctest name= 'MRW(2)'
$-$ mount_u $\overline{0}$	R	20.0	m/s	wind speed for MRW cases	ctest name= 'MRW(2)'
rh wavenum	I	4	,	wave number	ctest name= 'RH'
rh_init_shift_deg	R	0.0	deg	pattern shift	ctest_name= 'RH'
ihs_init_type	I	1		Choice of initial condition for the Held-Suarez test. 1: the zonal state defined in the JWs test case; other integers: isothermal state (T=300 K, ps=1000 hPa, u=v=0.)	ctest_name= 'HS'
lhs_vn_ptb	L	.TRUE.		Add random noise to the initial wind field in the Held-Suarez test.	ctest_name= 'HS'
hs_vn_ptb_scale	R	1.	m/s	Magnitude of the random noise added to the initial wind field in the Held-Suarez test.	ctest_name= 'HS'
lrh_linear_pres	L	.FALSE.		Initialize the relative humidity using a linear function of pressure.	ctest_name= 'JWw-Moist','APE', 'LDF-Moist'

Parameter	Type	Default	Unit	Description	Scope
rh_at_1000hpa	R	0.75		relative humidity	ctest_name=
				0,1	'JWw-Moist','APE',
				at 1000 hPa	'LDF-Moist'
linit_tracer_fv	L	.TRUE.		Finite volume initialization for tracer fields	ctest_name='PA'
ape_sst_case	C	'sst1'		SST distribution selection	ctest_name='APE'
				'sst1': Control experiment	
				'sst2': Peaked experiment	
				'sst3': Flat experiment	
				'sst4': Control-5N experiment	
				'sst_qobs': Qobs SST distribution exp	
				'sst_ice': Control SST distribution with -1.8 C	
				above 64 N/S .	
ildf_init_type	I	0		Choice of initial condition for the Local diabatic	ctest_name= 'LDF'
				forcing test. 1: the zonal state defined in the	
				JWs test case; other: isothermal state (T=300	
				K, ps=1000 hPa, u=v=0.)	
ldf_symm	L	.TRUE.		Shape of local diabatic forcing:	ctest_name=
				.TRUE.: local diabatic forcing symmetric about	'LDF','LDF-Moist'
				the equator (at 0 N)	
				.FALSE.: local diabatic forcing asym. about the	
				equator (at 30 N)	

Defined and used in: src/testcases/mo_ha_testcases.f90

4.2. nh_testcase_nml (Scope: Itestcase=.TRUE. and iequations=3 in run_nml)

Parameter	Type	Default	Unit	Description	Scope
nh_test_name	С	'jabw'		testcase selection	
				'zero': no orography	
				'bell': bell shaped mountain at 0E,0N	
				'schaer': hilly mountain at 0E,0N	
				'jabw': Initializes the full Jablonowski	
				Williamson test case.	
				'jabw s': Initializes the Jablonowski	
				Williamson steady state test case.	
				'jabw m': Initializes the Jablonowski	
				Williamson test case with a mountain instead of	
				the wind perturbation (specify mount height).	
				'mrw nh': Initializes the full	
				Mountain-induced Rossby wave test case.	
				'mrw2 nh': Initializes the modified	
				mountain-induced Rossby wave test case.	

Parameter	Туре	Default	Unit	Description	Scope
				'mwbr_const': Initializes the mountain wave	
				with two layers test case. The lower layer is	
				isothermal and the upper layer has constant	
				brunt vaisala frequency. The interface has	
				constant pressure.	
				'PA': Initializes the pure advection test case.	
				'HS nh': Initializes the Held-Suarez test case.	
				At the moment with an isothermal atmosphere	
				at rest (T=300K, ps=1000hPa, u=v=0,	
				topography=0.0).	
				'HS jw': Initializes the Held-Suarez test case	
				with Jablonowski Williamson initial conditions	
				and zero topography.	
				'APE nwp, APE echam, APE nh,	
				APEc nh, ': Initializes the APE experiments.	
				With the jabw test case, including moisture.	
				'wk82': Initializes the Weisman Klemp test case	1 limited area = .TRUE.
				'g_lim_area': Initializes a series of general	
				limited area test cases: itype_atmos_ana	
				determines the atmospheric profile,	
				itype anaprof uv determines the wind profile	
				and itype topo ana determines the topography	
				'dcmip bw 11': Initializes (moist) baroclinic	
				instability/wave (DCMIP2016)	
				'dcmip pa 12': Initializes Hadley-like	
				meridional circulation pure advection test case.	
				'dcmip rest 200': atmosphere at rest test	lcoriolis = .FALSE.
				(Schaer-type mountain)	
				'dcmip mw 2x': nonhydrostatic mountain	lcoriolis = .FALSE.
				waves triggered by Schaer-type mountain	
				'dcmip gw 31': nonhydrostatic gravity waves	
				triggered by a localized perturbation (nonlinear)	
				'dcmip gw 32': nonhydrostatic gravity waves	1 limited area =.TRUE.
				triggered by a localized perturbation (linear)	$\overline{\text{and lcoriolis}} = .\text{FALSE}.$
				'dcmip tc 51': tropical cyclone test case with	lcoriolis = .TRUE.
				'simple physics' parameterizations (not yet	
				implemented)	
				'dcmip tc 52': tropical cyclone test case with	lcoriolis = .TRUE.
				with full physics in Aqua-planet mode	
				'CBL': convective boundary layer simulations	is plane torus= .TRUE.
				for LES package on torus (doubly periodic) grid	
is toy chem	ho L	.FALSE.		Terminator toy chemistry activated when	
	-			.TRUE.	

Parameter	Type	Default	Unit	Description	Scope
tracer_inidist_list	I(:)	1		For a subset of testcases pre-defined initial tracer distributions are available. This namelist	nh_test_name='PA', 'JABW','DF'
				parameter specifies the initial distribution for	JABW , DF
				each tracer. In the following the testcases and	
				the pre-defined numbers are given:	
				'PA': 4,5,6,7,8	
				'JABW':1,2,3,4	
				'DF': 5,6,7,8,9	
				For more details on the initial distributions,	
				please have a look into the code.	
dcmip_bw%	·	·		DCMIP2016 baroclinic wave test	'dcmip_bw_11'
deep	I	0		deep atmosphere	
				(1 = yes or 0 = no)	
moist	I	0		include moisture, i.e. $qv \neq 0$	
				(1 = yes or 0 = no)	
pertt	I	0		type of initial perturbation	
				(0 = exponential, 1 = stream function)	
toy_chem%				terminator toy chemistry	is_toy_chem=.TRUE.
dt_chem	R	300	S	chemistry tendency update interval	
dt_cpl	R	300	s	chemistry-transport coupling interval	
id_cl	I -	1		Tracer container slice index for species CL	
id_cl2	1	2		Tracer container slice index for species CL2	
jw_up	R	1.0	m/s	amplitude of the u-perturbation in jabw test case	nh_test_name='jabw'
u0_mrw	R	20.0	m/s	wind speed for mrw(2) and mwbr_const cases	nh_test_name= 'mrw(2)_nh' and 'mwbr_const'
mount_height_mrw	R	2000.0	m	maximum mount height in $mrw(2)$ and	nh_test_name= 'mrw(2)_nh'
		1200000		mwbr_const	and 'mwbr_const'
mount_half_width	R	1500000.0	m	half width of mountain in mrw(2), mwbr_const and bell	nh_test_name= 'mrw(2)_nh', 'mwbr_const' and 'bell'
mount_lonctr_mrw_deg	R	90.	deg	lon of mountain center in $mrw(2)$ and	nh_test_name= 'mrw(2)_nh'
				mwbr_const	and 'mwbr_const'
mount_latctr_mrw_deg	R	30.	deg	lat of mountain center in mrw(2) and mwbr_const	nh_test_name= 'mrw(2)_nh' and 'mwbr_const'
temp_i_mwbr_const	R	288.0	K	temp at isothermal lower layer for mwbr_const case	nh_test_name= 'mwbr_const'
p_int_mwbr_const	R	70000.	Pa	pres at the interface of the two layers for mwbr const case	nh_test_name= 'mwbr_const'
bruntvais_u_mwbr_const	R	0.025	1/s	constant brunt vaissala frequency at upper layer for mwbr const case	nh_test_name= 'mwbr_const'
mount height	R	100.0	m	peak height of mountain	nh test name= 'bell'
layer_thickness	R	-999.0	m	thickness of vertical layers	If $layer_{thickness} < 0$, the
					vertical level distribution is
					read in from externally given HYB_PARAMS_XX.

Parameter	Type	Default	Unit	Description	Scope
n_flat_level	I	2		level number for which the layer is still flat and	$layer_thickness > 0$
				not terrain-following	
nh_u0	R	0.0	m/s	initial constant zonal wind speed	$nh_test_name = 'bell'$
nh_t0	R	300.0	K	initial temperature at lowest level	nh_test_name = 'bell'
nh_brunt_vais	R	0.01	1/s	initial Brunt-Vaisala frequency	nh_test_name = 'bell'
torus domain length	R	100000.0	m	length of slice domain	nh test name = 'bell',
					lplane=.TRUE.
rotate axis deg	R	0.0	deg	Earth's rotation axis pitch angle	nh test name= 'PA'
lhs nh vn ptb	\mid L	.TRUE.		Add random noise to the initial wind field in the	nh test name= 'HS nh'
				Held-Suarez test.	
lhs fric heat	\mid L	.FALSE.		add frictional heating from Rayleigh friction in	nh test name= 'HS nh'
	"			the Held-Suarez test.	
hs_nh_vn_ptb_scale	R	1.	m/s	Magnitude of the random noise added to the	nh test name= 'HS nh'
m_m_vii_bin_scare	16	1.	111/5	initial wind field in the Held-Suarez test.	m_ccsc_name= ms_m
rh at 1000hpa	\mid R	0.7	1	relative humidity at 1000 hPa	nh tost namo- 'iahw'
m_at_1000mpa	l n	0.7	1	relative numerty at 1000 nra	nh_test_name= 'jabw',
	D	20 2	1- 0- /1	an asific humidity in the to	nh_test_name= 'mrw'
qv_max	R	20.e-3	kg/kg	specific humidity in the tropics	nh_test_name= 'jabw',
		, ,,,		CCCD 1: 4 · 1 · 4 · 1 · 4 · 1	nh_test_name='mrw'
ape_sst_case	C	'sst1'		SST distribution selection	nh_test_name='APE_nwp',
				'sst1': Control experiment	'APE_echam'
				'sst2': Peaked experiment	
				'sst3': Flat experiment	
				'sst4': Control-5N experiment	
				'sst_qobs': Qobs SST distribution exp.	
				'sst_const': constant SST	
ape_sst_val	R	29.0	degC	aqua planet SST for ape_sst_case='sst_const'	nh_test_name= 'APE_nwp', 'APE_echam'
linit tracer fv	L	.TRUE.		Finite volume initialization for tracer fields	pure advection tests, only
lcoupled rho	L	.FALSE.		Integrate density equation 'offline'	pure advection tests, only
qv_max_wk	R	0.014	$\mathrm{Kg/kg}$	maximum specific humidity near	nh test name='wk82'
• – –			3, 3	the surface, range 0.012 - 0.016	
				used to vary the buoyancy	
u infty wk	R	20.	m/s	zonal wind at infinity height	nh_test_name='wk82'
		-0.	111/5	range 0 45.	
				used to vary the wind shear	
bub_amp	R	2.	K	maximum amplitud of the thermal perturbation	nh test name='wk82'
bubctr lat	R	0.	deg	latitude of the center of the thermal perturbation	nh_test_name='wk82'
bubctr lon	R	90.	deg	longitude of the center of the thermal	nh test name='wk82'
_			ueg	perturbation	
bubctr_z	R	1400.	m	height of the center of the thermal perturbation	nh_test_name='wk82'
bub_hor_width	R	10000.	m	horizontal radius of the thermal perturbation	$nh_test_name='wk82'$
bub_ver_width	R	1400.	m	vertical radius of the thermal perturbation	nh_test_name='wk82'
itype_atmo_ana	I	1		kind of atmospheric profile:	nh_test_name=
				1 piecewise N constant layers	'g_lim_area'
	1			2 piecewise polytropic layers	

Parameter	Type	Default	Unit	Description	Scope
type_anaprof_uv	I	1		kind of wind profile:	$nh_test_name =$
				1 piecewise linear wind layers	'g_lim_area'
				2 constant zonal wind	
				3 constant meridional wind	
itype_topo_ana	I	1		kind of orography:	nh test name=
				1 schaer test case mountain	'g_lim_area'
				2 gaussian 2d mountain	= =
				3 gaussian 3d mountain	
				any other no orography	
nlayers nconst	Ţ	1		Number of the desired layers with a constant	nh test name=
mayers_neons	1	1		Brunt-Vaisala-frequency	'g_lim_area' and
				Diano-vaisara-nequency	itype atmo ana=1
n hasa naonst	D	100000.	Pa	programs at the bage of the first M constant laws	· - — —
p_base_nconst	R	100000.	га	pressure at the base of the first N constant layer	nh_test_name=
					'g_lim_area' and
11 4 0 1	TD.	000	TZ.		itype_atmo_ana=1
$theta0_base_nconst$	R	288.	K	potential temperature at the base of the first N	nh_test_name=
				constant layer	'g_lim_area' and
_					itype_atmo_ana=1
h_nconst	R(nlayers	0., 1500., 12000.	m	height of the base of each of the N constant	nh_test_name=
	_nconst)			layers	'g_lim_area' and
					itype_atmo_ana=1
N_nconst	R(nlayers	0.01	1/s	Brunt-Vaisala-frequency at each of the N	$nh_test_name =$
	_nconst)			constant layers	'g_lim_area' and
				•	itype atmo ana=1
rh nconst	R(nlayers	0.5	%	relative humidity at the base of each N constant	nh test name=
_	_nconst)			layers	'g_lim_area' and
					itype atmo ana=1
rhgr nconst	R(nlayers	0.	%	relative humidity gradient at each of the N	nh test name=
-11-01-11-01-11-01-11-01-11-01-11-01-11-01-11-01-11-01-11-01-11-01-11-01-11-01-11-01-11-01-11-01-11-01-11-01-	nconst)		/0	constant layers	'g_lim_area' and
				Combunit Tayors	itype atmo ana=1
nlavora noly	т	2		Number of the desired layers with constant	
nlayers_poly	1			The state of the s	nh_test_name=
				gradient temperature	'g_lim_area' and
1 1	TD.	100000	D		itype_atmo_ana=2
p_base_poly	R	100000.	Pa	pressure at the base of the first polytropic layer	nh_test_name=
					'g_lim_area' and
					itype_atmo_ana=2
h_poly	R(nlayers	0., 12000.	m	height of the base of each of the polytropic layers	nh_test_name=
	_poly)				'g_lim_area' and
					$itype_atmo_ana=2$
t_poly	R(nlayers	288., 213.	K	temperature at the base of each of the polytropic	$nh_test_name =$
	_poly)			layers	'g_lim_area' and
					itype atmo ana=2
rh_poly	R(nlayers	0.8, 0.2	%	relative humidity at the base of each of the	nh test name=
•	_poly)	,		polytropic layers	'g_lim_area' and
	_F = 1, /			r · v · · · · · · · · · · · · · · · · ·	itype atmo ana=2
	I	I	1		

Parameter	Type	Default	Unit	Description	Scope
rhgr_poly	R(nlayers	5.e-5, 0.	%	relative humidity gradient at each of the	nh_test_name=
	_poly)			polytropic layers	'g_lim_area' and
					itype_atmo_ana=2
nlayers_linwind	I	2		Number of the desired layers with constant U	nh_test_name=
				gradient	'g_lim_area' and
1 1: 1	D/ 1	0 0500			itype_anaprof_uv=1
h_linwind	R(nlayers	0., 2500.	m	height of the base of each of the linear wind	nh_test_name=
	-linwind)			layers	'g_lim_area' and
limmind	D/releases	5, 10.	**** /a	zonal wind at the base of each of the linear wind	itype_anaprof_uv=1
u_linwind	R(nlayers	5, 10.	m/s		nh_test_name= 'g lim area' and
	-linwind)			layers	itype anaprof uv=1
ugr_linwind	R(nlayers	0., 0.	1/s	zonal wind gradient at each of the linear wind	nh test name=
ugi _iiiiwiiid	linwind)	0., 0.	1/8		'g lim area' and
	- IIIIwiiid)			layers	itype anaprof uv=1
vel const	R	20.	m/s	constant zonal/meridional wind	nh_test_name=
. 51001150		-0.	111/5	(itype_anaprof_uv=2,3)	'g lim area' and
				(, Fo_mmpror_a, - -,0)	itype anaprof uv=2,3
mount lonc deg	R	90.	deg	longitud of the center of the mountain	nh_test_name=
			3.58		'g_lim_area'
mount_latc_deg	R	0.	deg	latitud of the center of the mountain	nh test name=
1					'g lim area'
schaer_h0	R	250.	m	h0 parameter for the schaer mountain	nh_test_name=
-					'g lim area' and
					itype topo ana=1
schaer_a	R	5000.	m	-a- parameter for the schaer mountain,	$nh_test_name =$
				also half width in the north and south side of the	'g_lim_area' and
				finite ridge to round the sharp edges	itype_topo_ana=1,2
schaer_lambda	R	4000.	m	lambda parameter for the schaer mountain	$nh_test_name =$
					'g_lim_area' and
					itype_topo_ana=1
lshear_dcmip	L	FALSE		run dcmip_mw_2x with/without vertical wind	nh_test_name=
				shear	'dcmip_mw_2x'
				FALSE: dcmip_mw_21: non-sheared	
1 16 : 141 - 0.1		10000		TRUE: dcmip_mw_22: sheared	
halfwidth_2d	R	10000.	m	half lenght of the finite ridge in the north-south	nh_test_name=
				direction	'g_lim_area' and
m haight	D	1000	***	height of the mountain	itype_topo_ana=1,2
m_height	R	1000.	m	height of the mountain	nh_test_name=
					'g_lim_area' and
m width w	D	5000.	***	half width of the gaussian magnetain in the	itype_topo_ana=2,3
m_width_x	R	5000.	m	half width of the gaussian mountain in the east-west direction	nh_test_name= 'g_lim_area' and
				half width in the north-south direction in the	itype_topo_ana=2,3
				rounding of the finite ridge (gaussian 2d)	hype_topo_ana=2,5
	I	l		rounding of the fillite fluge (gaussian_2u)	l l

Parameter	Type	Default	Unit	Description	Scope
m_width_y	R	5000.	m	half width of the gaussian mountain in the	nh_test_name=
				north-south direction	'g_lim_area' and
					itype_topo_ana=2,3
gw_u0	R	0.	m/s	maximum amplitude of the zonal wind	$nh_test_name =$
					'dcmip_gw_3X'
gw_clat	R	90.	deg	Lat of perturbation center	nh_test_name=
					'dcmip_gw_3X'
gw_delta_temp	R	0.01	K	maximum temperature perturbation	nh_test_name=
					'dcmip_gw_32'
u_cbl(2)	R	0:0	m/s and	to prescribe initial zonal velocity profile for	nh_test_name=CBL
			1/s	convective boundary layer simulations where	
				u_cbl(1) sets the constant and u_cbl(2) sets the	
				vertical gradient	
v_cbl(2)	R	0:0	m/s and	to prescribe initial meridional velocity profile for	nh_test_name=CBL
			1/s	convective boundary layer simulations where	
				$v_{cbl}(1)$ sets the constant and $v_{cbl}(2)$ sets the	
				vertical gradient	
$th_cbl(2)$	R	290:0.006	K and	to prescribe initial potential temperature profile	nh_test_name=CBL
			K/m	for convective boundary layer simulations where	
				$th_cbl(1)$ sets the constant and $th_cbl(2)$ sets	
				the gradient	

Defined and used in: src/testcases/mo_nh_testcases.f90

5. External data

5.1. extpar_nml (Scope: itopo=1 in run_nml)

Parameter	Type	Default	Unit	Description	Scope
itopo	I	0		0: analytical topography/ext. data	
				1: topography/ext. data read from file	
itype_vegetation_cycle	I	1		1: annual cycle of LAI solely based on NDVI	
				climatology	
				2: additional use of monthly T2M climatology to	
				get more realistic values in extratropics (requires	
				external parameter data contining this field)	
				3: as 2 with additional coupling of vegetation	
				parameters to T2M bias in transitional seasons	
n iter smooth topo	I(n_dom)	0		iterations of topography smoother	itopo = 1
fac_smooth_topo	R	0.015625		pre-factor of topography smoother	$n_{ter}smooth_{topo} > 0$
hgtdiff_max_smooth_topo	R	0.	m	RMS height difference to neighbor grid points at	$n_{ter}smooth_{topo} > 0$
				which the smoothing pre-factor	
				fac_smooth_topo reaches its maximum value	
				(linear proportionality for weaker slopes)	

Parameter	Type	Default	Unit	Description	Scope
heightdiff_threshold	R(n_dom)	3000.	m	height difference between neighboring grid points	
				above which additional local nabla2 diffusion is applied	
lrevert_sea_height	L	.FALSE.		If .TRUE., sea point heights will be reverted to original (raw data) heights after topography smoothing was applied.	$\verb n_iter_smooth_topo > 0$
l_emiss	L	.TRUE.		read and use external surface emissivity map	itopo = 1
extpar_filename	C			Filename of external parameter input file,	
				default: " <path>extpar_<gridfile>". May</gridfile></path>	
				contain the keyword <path> which will be</path>	
				substituted by model_base_dir.	
extpar_varnames_map_ file	C	, ,		Filename of external parameter dictionary, This	
				is a text file with two columns separated by	
				whitespace, where left column: NetCDF name,	
				right column: GRIB2 short name. It is required,	
				if external parameter are read from a file in	
				GRIB2 format.	

Defined and used in: src/namelists/mo_extpar_nml.f90

6. External packages

7. Information on vertical level distribution

If no vertical sleve coordinate is chosen (ivetype / =2), the hydrostatic and nonhydrostatic models need hybrid vertical level information to generate the terrain following coordinates. The hybrid level specification is stored in <icon home>/hyb_params/HYB_PARAMS_<nlev>. The hydrostatic model assumes to get pressure based coordinates, the nonhydrostatic model expects height based coordinates. For further information see <icon home>/hyb_params/README.

8. Compile flag for mixed precision

To speed up code parts strongly limited by memory bandwidth (primarily the dynamical core and the tracer advection), an option exists to use single precision for variables that are presumed to be insensitive to computational accuracy. This affects most local arrays in the dynamical core routines (solve_nonhydro and velocity_advection), some local arrays in the tracer transport routines, the metrics coefficients, arrays used for storing tendencies or differenced fields (gradients, divergence etc.), reference atmosphere fields, and interpolation coefficients. Prognostic variables and intermediate variables affecting the accuracy of mass conservation are still treated in double precision. To activate the mixed-precision option, the cpp flags '-D__MIXED_PRECISION' and '-D__MIXED_PRECISION_2' need to be specified in the configuration settings used for generating the Makefile. The latter flag is used for physics tendencies. Note that interpolation to a latitude-longitude grid is not supported for single-precision variables; if you desire to output physics tendency fields on a regular grid for diagnostic purposes, do not set '-D__MIXED_PRECISION_2'.

A. Arithmetic expression evaluation

The mo_expression module evaluates basic arithmetic expressions specified by character-strings. It is possible to include mathematical functions, operators, and constants. An application of this module is the evaluation of arithmetic expressions povided as namelist parameters.

Besides, Fortran variables can be linked to the expression and used in the evaluation. The implementation supports scalar input variables as well as 2D and 3D fields. From a users' point of view, the basic usage of this module is described in Section A.1 below. Technically, infix expressions are processed based on a Finite State Machine (FSM) and Dijkstra's shunting yard algorithm. A more detailed described of the Fortran interface is given in Section A.3.

A.1. Examples for arithmetic expressions

Basic examples:

- "sqrt(2.0)"
- "sin(45*pi/180.) * 10 + 5"
- "if(1. > 2, 99, -1.*pi)"
- "min(1,2)"

Variables are used with a bracket notation:

• "sqrt([u]^2 + [v]^2)"

Note that the use of variables requires that these are enabled ("linked") by the Fortran routine that calls the mo_expression module.

A.2. Expression syntax

A.2.1. List of functions

name	#args	description
log(), exp()	1	natural logarithm and its inverse function.
sin(), cos()	1	trigonometric functions
sqrt()	1	square root
min(), max()	2	minimum and maximum of two values
if(value, then, else)	3	conditional expression (value > 0.)

A.2.2. List of operators

name	evaluates to	
a + b, a - b, a * b, a / b	(a+b), (a-b), (a*b), (a/b)	
a ^ b	a^b	
a > b	$\begin{cases} 1, & \text{if } a > b, \\ 0, & \text{otherwise.} \end{cases}$	
a < b	$\begin{cases} 1, & \text{if } a < b, \\ 0, & \text{otherwise.} \end{cases}$	

A.2.3. List of available constants

name of constant	assigned value	description
pi	4 atan(1)	mathematical constant equal to a circle's cir-
		cumference divided by its diameter
r	$6.371229 \cdot 10^6$	Earth's radius ¹

A.3. Usage with Fortran

The minimal Fortran interface is as follows:

- 1. The TYPE expression which is initialized with the character-string that specifies the arithmetic expression.
- 2. The type-bound procedure evaluate(), which returns the result (scalar or array-shaped) as a POINTER.
- 3. The type-bound procedure link() connecting a variable to a name in the character-string expression.

A.3.1. Fortran examples

The following examples illustrate the arithmetic expression parser. The calls to DEALLOCATE the data structures have been ommitted for the sake of brevity:

1. Scalar arithmetic expression:

```
formula = expression("sin(45*pi/180.) * 10 + 5")
CALL formula%evaluate(val)
... use "val" for some purpose ...
```

2. Masking of a 2D array as an example for the link procedure:

```
formula = expression("if([z_sfc] > 2., [z_sfc], 0.)")
CALL formula%link("z_sfc", z_sfc)
CALL formula%evaluate(val_2D)
... use "val_2D(:,:)" for some purpose ...
```

A.3.2. Error handling

Invalid arithmetic expressions yield "empty" expression objects. When these are evaluated, a NULL() pointer is returned. A successful expression evaluation can be tested with the err_no variable:

```
IF (formula%err_no == ERR_NONE) THEN
    ...
END IF
```

In case of error, the err_no variable also provides the reason for the aborted evaluation process.

A.4. Remarks

- Variable names are treated case-sensitive!
- For 3D array input it is implicitly assumed that 2D fields are embedded in 3D fields as "3D(:,level,:) = 2D(:,:)".

B. Changes incompatible with former versions of the model code

Change: var_names_map_file, out_varnames_map_file

 Date of Change:
 2013-04-25

 Revision:
 12016

ullet Renamed var names map file o output nml dict.

- $\bullet \ \operatorname{Renamed} \ \mathbf{out_varnames_map_file} \to \mathbf{netcdf_dict}.$
- The dictionary in netcdf_dict is now reversed, s.t. the same map file as in output_nml_dict can be used to translate variable names to the ICON internal names and back.

Change: output nml: namespace

 Date of Change:
 2013-04-26

 Revision:
 12051

• Removed obsolete namelist variable namespace from output nml.

Change: gribout nml: generatingCenter, generatingSubcenter

 Date of Change:
 2013-04-26

 Revision:
 12051

- Introduced new namelist variables generatingCenter and generatingSubcenter.
- If not set explicitly, center and subcenter information is copied from the input grid file

Change: radiation_nml: albedo_type

 Date of Change:
 2013-05-03

 Revision:
 12118

- Introduced new namelist variable albedo type
- If set to 2, the surface albedo will be based on the MODIS data set.

¹This number seems to be based on Hayford's 1910 estimate of the Earth. It is used in ICON as well as MPAS and was almost certainly taken from the Jablonowski and Williamson test case (QJRMS, 2006).

Change: initicon_nml: dwdinc_filename

 Date of Change:
 2013-05-24

 Revision:
 12266

• Renamed dwdinc_filename to dwdana_filename

Change: initicon nml: l ana sfc

 Date of Change:
 2013-06-25

 Revision:
 12582

- \bullet Introduced new namelist flag l ana sfc
- If true, soil/surface analysis fields are read from the analysis fiel dwdfg_filename. If false, surface analysis fields are not read. Soil and surface are initialized with the first guess instead.

Change: new nwp phy tend list: output names consistent with variable names

 Date of Change:
 2013-06-25

 Revision:
 12590

- \bullet temp tend radlw \rightarrow ddt temp radlw
- $\bullet \ temp_tend_turb \to ddt_temp_turb$
- $\bullet \ \operatorname{temp_tend_drag} \to \operatorname{ddt_temp_drag}$

Change: prepicon_nml, remap_nml, input_field_nml

 Date of Change:
 2013-06-25

 Revision:
 12597

- Removed the sources for the "prepicon" binary!
- The "prepicon" functionality (and most of its code) has become part of the ICON tools.

Change: initicon_nml
Date of Change: 2013-08-19
Revision: 13311

• The number of vertical input levels is now read from file. The namelist parameter **nlev** in has become obsolete in r12700 and has been removed.

 $egin{array}{lll} {\it Change:} & {\it parallel_nml} \\ {\it Date of Change:} & {\it 2013-10-14} \\ {\it Revision:} & {\it 14160} \\ \hline \end{array}$

• The namelist parameter exch_msgsize has been removed together with the option iorder_sendrecv=4.

 $egin{array}{ll} {\it Change:} & {\it parallel_nml} \\ {\it Date of Change:} & {\it 2013-08-14} \\ {\it Revision:} & {\it 14164} \\ \hline \end{array}$

• The namelist parameter use_sp_output has been replaced by an equivalent switch use_dp_mpi2io (with an inverse meaning, i.e. we have use_dp_mpi2io = .NOT. use_sp_output).

 $egin{array}{lll} {\it Change:} & {\it parallel_nml} \\ {\it Date of Change:} & {\it 2013-08-15} \\ {\it Revision:} & {\it 14175} \\ \hline \end{array}$

• The above-mentioned namelist parameter use_dp_mpi2io got the default .FALSE. By this, the output data are sent now in single precision to the output processes.

Change: initicon_nml: l_ana_sfc

 Date of Change:
 2013-10-21

 Revision:
 14280

• The above-mentioned namelist parameter l_ana_sfc has been replaced by lread_ana. The default is set to .TRUE., meaning that analysis fields are required and read on default. With lread_ana=.FALSE. ICON is able to start from first guess fields only.

Change: output_nml: lwrite_ready, ready_directory

 Date of Change:
 2013-10-25

 Revision:
 14391

- The namelist parameters lwrite_ready and ready_directory have been replaced by a single namelist parameter ready_file, where ready_file /= 'default' enables writing ready files.
- Different output_nml's may be joined together to form a single ready file event they share the same ready_file.

Change: output_nml: output_bounds

 Date of Change:
 2013-10-25

 Revision:
 14391

• The namelist parameter **output bounds** specifies a start, end, and increment of output invervals. It does no longer allow multiple triples.

Change: output nml: steps per file

 Date of Change:
 2013-10-30

 Revision:
 14422

• The default value of the namelist parameter steps per file has been changed to -1.

 Change:
 run_nml

 Date of Change:
 2013-11-13

 Revision:
 14759

- The dump/restore functionality for domain decompositions and interpolation coefficients has been removed from the model code. This means, that the parameters
 - ldump_states,
 - lrestore_states,
 - ldump_dd,
 - lread_dd,
 - nproc_dd,
 - dd_filename,
 - dump_filename,
 - l_one_file_per_patch

have been removed together with the corresponding functionality from the ICON model code.

Change: output_nml: filename_format

 Date of Change:
 2013-12-02

 Revision:
 15068

• The string token <ddhhmmss> is now substituted by the relative day-hour-minute-second string, whereas the absolute date-time stamp can be inserted using <datetime>.

Change: output_nml: ready_file

 Date of Change:
 2013-12-03

 Revision:
 15081

• The ready file name has been changed and may now contain string tokens <path>, <datetime>, <ddhhmmss> which are substituted as described for the namelist parameter filename_format.

Change: interpl nml: rbf vec scale ll

 Date of Change:
 2013-12-06

 Revision:
 15156

- The real-valued namelist parameter rbf_vec_scale_ll has been removed.
- Now, there exists a new integer-valued namelist parameter, rbf_scale_mode_11 which specifies the mode, how the RBF shape parameter is determined for lon-lat interpolation.

 Change:
 io_nml

 Date of Change:
 2013-12-06

 Revision:
 15161

- Removed remaining vlist-related namelist parameter. This means that the parameters
 - out filetype
 - out expname
 - dt data
 - dt file
 - lwrite_dblprec, lwrite_decomposition, lwrite_vorticity, lwrite_divergence, lwrite_pres, lwrite_tracer, lwrite_tend_phy, lwrite_radiation, lwrite_precip, lwrite_cloud, lwrite_tke, lwrite_surface, lwrite_initial, lwrite_oce_timestepping

are no longer available.

• Changed namelist defaults for nesting: grf_intmethod_e, 1_mass_consvcorr, 1_density_nudging.

 $egin{array}{lll} {\it Change:} & & & & & & & & & \\ {\it Date of Change:} & & & & & & & & \\ {\it Revision:} & & & & & & & \\ & & & & & & & & \\ & & & & & & & & \\ & & & & & & & & \\ & & & & & & & \\ & & & & & & & & \\ & & & & & & & \\ & & & & & & & \\ & & & & & & & \\ & & & & & & & \\ & & & & & & & \\ & & & & & & & \\ & & & & & & & \\ & & & & & & & \\ & & & & & & & \\ & & & & & & & \\ & & & & & & & \\ & & & & & & & \\ & & & & & & & \\ & & & & & & & \\ & & & & & & \\ & & & & & & & \\ & & & & & \\ & & & & & & \\ & & & & & \\ & & & & & & \\ & & & & & \\ & & & & & \\ & & & & & \\ & & & & & \\ & & & & & \\ & & & & & \\ & & & & & \\ & & & & & \\ & & & & & \\ & & & & \\ & & & & \\ & & & & \\ & & & & \\ & & & & \\ & & & & \\ & & & & \\ & & & & \\ & & & & \\ & & & & \\ & & & & \\ & & & & \\ & & & \\ & & & & \\ & & & \\ & & & & \\ & & & \\ & & & & \\ & & \\ & & & \\ & & & \\ & & & \\ & & \\ & & & \\ & & \\ & &$

• Changed namelist default for rbf_scale_mode_11: The RBF scale factor for lat-lon interpolation is now determined automatically by default.

Change: echam_phy_nml
Date of Change: 2014-02-27

Revision: 16313

• Replace the logical switch lcover by the integer switch icover that is used in ECHAM-6.2. Values are transferred as follows: FALSE. = 1 (=default), TRUE. = 2.

 $\begin{array}{ll} {\it Change:} & {\it turbdiff_nml} \\ {\it Date of Change:} & {\it 2014-03-12} \\ {\it Revision:} & {\it 16527} \end{array}$

• Change constant minimum vertical diffusion coefficients to variable ones proportional to $1/\sqrt{Ri}$ for inwp_turb = 10; at the same time the defaults for tkhmin and tkmmin are increased from $0.2\,\mathrm{m}^2/\mathrm{s}$ to $0.75\,\mathrm{m}^2/\mathrm{s}$.

 Change:
 nwp_phy_nml

 Date of Change:
 2014-03-13

 Revision:
 16560

• Removed namelist parameter dt_ccov, since practically it had no effect. For the quasi-operational NWP-setup, the calling frequency of the cloud cover scheme is the same as that of the convection scheme. I.e. both are synchronized.

 Change:
 nwp_phy_nml

 Date of Change:
 2014-03-24

 Revision:
 16668

• Changed namelist default for **itype z0**: use land cover related roughness only (itype_z0=2).

Change: nonhydrostatic_nml

 Date of Change:
 2014-05-16

 Revision:
 17293

• Removed switch for vertical TKE advection in the dynamical core (lvadv_tke). TKE advection has been moved into the transport scheme and can be activated with iadv_tke=1 in the transport_nml.

Change: nonhydrostatic nml

 Date of Change:
 2014-05-27

 Revision:
 17492

• Removed namelist parameter model_restart_info_filename in namelist master_model_nml.

 $egin{array}{lll} {\it Change:} & {\it transport_nml} \\ {\it Date of Change:} & {\it 2014-06-05} \\ {\it Revision:} & {\it 17654} \\ \hline \end{array}$

• Changed namelist default for itype_hlimit from monotonous limiter (3) to positive definite limiter (4).

 Change:
 nh_pzlev_nml

 Date of Change:
 2014-08-28

 Revision:
 18795

• Removed namelist nh_pzlev_nml. Instead, each output namelist specifies its separate list of p_levels, h_levels, and i_levels.

Change: nonhydrostatic nml

 Date of Change:
 2014-10-27

 Revision:
 19670

• Removed namelist parameter l_nest_rcf in namelist nonhydrostatic_nml.

Change: nonhydrostatic nml

 Date of Change:
 2014-11-24

 Revision:
 20073

• Removed namelist parameter iadv_rcf in namelist nonhydrostatic_nml. The number of dynamics substeps per advective step are now specified via ndyn_substeps. The meaning of run_nml:dtime has changed and denotes the advective time step.

 Change:
 io_nml

 Date of Change:
 2015-03-25

 Revision:
 21501

• Namelist parameter lzaxis_reference is deprecated and has no effect anymore. However, users are not forced to modify their scripts instantaneously: lzaxis_reference=.FALSE. is still a valid namelist setting, but it has no effect and a warning will be issued. lzaxis_reference finally removed in r24606.

Change: limarea_nml
Date of Change: 2016-02-08
Revision: 26390

• Namelist parameter dt_latbc has been removed. Its value is now identical to the namelist parameter dtime_latbc.

 $egin{array}{lll} {\it Change:} & & & & & & & & & \\ {\it Date of Change:} & & & & & & & & \\ {\it Revision:} & & & & & & & \\ {\it 2016-02-11} & & & & & & \\ {\it Revision:} & & & & & & \\ {\it 26423} & & & & & \\ \hline \end{array}$

• Namelist parameter l_intp_c2l is deprecated and has no effect anymore.

 $\begin{array}{ll} \textit{Change:} & & \text{lnd_nml} \\ \textit{Date of Change:} & & \textbf{2016-07-21} \\ \textit{Revision:} & & \textbf{28536} \end{array}$

• The numbering of the various options for sstice_mode has changed. Former option 2 became 3, former option 3 became 4, and former option 4 became 5. This was necessary, because a new option was introduced (option 2).

Change: initicon_nml
Date of Change: 2016-07-22
Revision: 28556

• Namelist parameter latbc_varnames_map_file has been moved to the namelist limarea_nml.

 $\begin{array}{ll} \textit{Change:} & \text{transport_nml} \\ \textit{Date of Change:} & \textbf{2016-09-22} \\ \textit{Revision:} & \textbf{29339} \end{array}$

• Namelist parameter niter_fct has been removed, since the functionality of iterative flux correction is no longer available.

Change: initicon_nml
Date of Change: 2016-10-07
Revision: 29484

• Namelist parameter l_sst_in has been removed. In case of init_mode=2 (IFSINIT), sea points are now initialized with SST, if provided in the input file. Otherwise sea points are initialized with the skin temperature. The possibility to use the skin temperature despite having the SST available has been dropped.

Change: initicon_nml
Date of Change: 2016-12-14

Revision: 62288ed77b2975182204a2ec6fa210a3fb1ad8a7

• Namelist parameters ana_varlist, ana_varlist_n2 have been renamed to check_ana(jg)%list, with jg indicating the patch ID.

 $egin{array}{lll} {\it Change:} & & {\it initicon_nml} \\ {\it Date of Change:} & & {\it 2017-01-27} \\ {\it Revision:} & & {\it ae1be66f} \\ \end{array}$

• The default value of the namelist parameter num_prefetch_proc has been changed to 1, i.e. asynchronous read-in of lateral boundary data is now enabled.

 Change:
 interpol_nml

 Date of Change:
 2017-01-31

 Revision:
 e1c56104

• With the introduction of the namelist parameter lreduced_nestbdry_stencil in the namelist interpol_nml the nest boundary points are no longer removed from lat-lon interpolation stencil by default.

 $egin{array}{lll} {\it Change:} & & {\it limarea_nml} \\ {\it Date of Change:} & & 2017\text{-}03\text{-}14} \\ {\it Revision:} & & 631b731627 \\ \hline \end{array}$

• The namelist parameter nlev_latbc is now deprecated. Information about the vertical level number is taken directly from the input file.

Change: echam_phy_nml / mpi_phy_nml

Date of Change: 2017-04-19

Revision: icon-aes:icon-aes-mag 9ecee54f69108716308029d8d7aa0296c343a3c2

• The namelist echam_phy_nml is replaced by the namelist mpi_phy_nml, which extends the control to multiple domains and introduces time control in terms of start and end date/time [sd_prc,ed_prc] and time interval dt_prc for individual atmospheric processes prc.

Change: mpi phy nml / echam phy nml and mpi sso nml / echam sso nml

Date of Change: 2017-11-22

 ${\it Revision:} \qquad \qquad {\rm icon-aes:icon-aes-cfgnml} \ f84219511329281d441d81923fe97ce1d7ecf007$

• The namelists, configuration variables and related modules are renamed from ...mpi_phy... to ...echam_phy... because programmers felt that the acronym "mpi" for "Max Planck Institute" in relation to physics cannot be distinguished from "mpi" for "Message Passing Interface" as used in the parallelization.

Change: gw hines nml / echam gwd nml

Date of Change: 2017-11-24

Revision: icon-aes:icon-aes-cfgnml 699346b5d318d53be215e0b8e8b5ba8631d44c48

• The namelists gw hines nml is replaced by the namelist echam gwd nml, which extends the control to multiple domains.

Change: vdiff nml / echam_vdf_nml

Date of Change: 2017-11-27

• The namelists vdiff_nml is replaced by the namelist echam_vdf_nml, which additionally includes tuning parameters for the total turbulent energy scheme, and extends the control to multiple domains.

Change: echam_conv_nml / echam_cnv_nml

Date of Change: 2017-11-29

Revision: icon-aes-cfgnml 099c40f88dbaae6c7cc79ea878e5862847ef7e27

• The namelists echam conv nml is replaced by the namelist echam cnv nml, which extends the control to multiple domains.

Change: echam_cloud_nml / echam_cld_nml

Date of Change: 2017-12-04

Revision: icon-aes:icon-aes-cfgnml afacc102a87b03f78ff47ad0b7af8f348bacef6f

• The namelists echam_cloud_nml is replaced by the namelist echam_cld_nml, which extends the control to multiple domains.

Change: psrad_orbit_nml / radiation_nml / echam_rad_nml

Date of Change: 2017-12-12

Revision: icon-aes-cfgnml 8da087238b81183c337a3b1ae81d2b2e3dafdba8

• For controlling the input of ECHAM physics to the PSrad scheme, the namelists psrad_orbit_nml and radiation_nml are replaced by the namelist echam_rad_nml, which extends the control to multiple domains. For controlling the input of NWP physics to the RRTMG radiation, the radiation_nml namelist remains valid. The psrad orbit nml namelist, which is not used for RRTMG radiation, is deleted.