Table of Contents

Fencing	t/Stonith	
Virtu	ıalBox	
VMV	Vare	

Fencing/Stonith

Configuring fencing depends on the final deployment. The fencing operation relies on a script installed on the cluster node. Each cluster technology supports several kind of fencing mechanisms, but you can create your own if necessary.

Before configuring the fencing mechanism, it is a good practice to do a research about the available fencing script, to decide which fits better on a particular deployment and make sure it works before configuring it on the cluster.

The virtual lab is configured through *Vagrant*, and this application uses *VirtualBox* to create and manage the the VMs. *Vagrant* and *VirtualBox* are running on *Mac OS X*. For this particular deployment, using *VirtualBox* as a fence mechanism makes sense, as this will always be running in order to keep the VMs running.

This is similar to a *VMWare vSphere* environment where *vCenter* manages the VMs of the cluster nodes. For *VMWare*, *RedHat* provides a fencing mechanism called fence_vmrare_soap, which uses the *SOAP* Interface of *vCenter*.

Unfortunately, for VirtualBox there is no fencing agent, which means it should be created.

VirtualBox

RHEL/CentOS 6

There is no fencing device for *VirtualBox*, so I've created one in *Python* using *RedHat's Fencing API* (see Appending A). The script must be placed on /usr/sbin, and must have 0755 for its permissions.

The following command can list all the VMs with their *IDs* (VBoxManage is executed on the host machine, in my case *Mac OS X*):

```
$ /Applications/VirtualBox.app/Contents/MacOS/VBoxManage list vms
"opennms-cluster-onmssrv01" {5c467fe9-2611-4e5f-99f6-d1c6aa17527e}
"opennms-cluster-onmssrv02" {a379c5c0-2ce0-482a-be49-7237aa67f662}
"opennms-cluster-pgdbsrv01" {5ebfd17b-1325-4cd7-b2ee-ac3347e38306}
"opennms-cluster-pgdbsrv02" {b74dbaff-46ae-402b-bd50-5cebdfb81cfa}
"opennms-cluster-nfssrv01" {8379a446-d3a4-44a8-954c-408f0c236a20}
```

After creating the /usr/sbin/fence_vbox (own by root with 0755 for its permissions), you should be able to see the following:

```
[root@onmssrv01 ~]# /usr/sbin/fence_vbox -h
Usage:
fence_vbox [options]
Options:
   -o, --action=<action>
                                  Action: status, reboot (default), off or on
   -a, --ip=<ip>
                                   IP address or hostname of fencing device
  -l, --username=<name>
                                  Login name
  -p, --password=<password>
                                  Login password or passphrase
  -S, --password-script=<script> Script to run to retrieve password
                                  Use ssh connection
   -x, --ssh
   -n, --plug=<id>
                                  Physical plug number on device or
                                         name of virtual machine
   -k, --identity-file=<filename> Identity file (private key) for ssh
   -4, --inet4-only
                                   Forces agent to use IPv4 addresses only
   -6, --inet6-only
                                  Forces agent to use IPv6 addresses only
   -c, --command-prompt=prompt> Force command prompt
   -v, --verbose
                                  Verbose mode
   -D, --debug-file=<debugfile>
                                  Debugging to output file
   -V, --version
                                  Output version information and exit
  -h, --help
                                   Display this help and exit
  --power-timeout <seconds>
--shell-timeout <seconds>
--login-timeout <seconds>
                                  Test X seconds for status change after ON/OFF
                                  Wait X seconds for cmd prompt after issuing command
                                  Wait X seconds for cmd prompt after login
  --power-wait <seconds>
                                  Wait X seconds after issuing ON/OFF
                                  Wait X seconds before fencing is started
   --delay <seconds>
   --retry-on <attempts>
                                  Count of attempts to retry power on
```

Here is a sample execution:

```
[root@onmssrv01 ~]# /usr/sbin/fence_vbox -a 192.168.205.1 -l vboxuser -p vboxpasswd -n opennms-cluster-onmssrv01 -o status
Status: ON
```

On the above example, the *VirtualBox* application is running on 192.168.205.1, and the user called *vboxuser* (with password, *vboxpasswd*) has privileges to run the VBoxManage command on *MacOS X*, and it will retrieve the status of the VM called *opennms-cluster-onmssrv01*.

You can use either the name of the *VM* or its *UUID*:

```
[root@onmssrv01 ~]# /usr/sbin/fence_vbox -a 192.168.205.1 -l vboxuser -p vboxpasswd -n '5c467fe9-2611-4e5f-99f6-d1c6aa17527e' -o status
Status: ON
```

After copying the file to all the cluster nodes and verify they work, configure the fencing mechanism in the cluster.

Add the fence device (using virtualbox_dev as the device's name):

```
[root@onmssrv01 ~]# ccs --addfencedev virtualbox_dev agent=fence_vbox ipaddr="192.168.205.1" login="onms_user" passwd="onms_passwd"
```

Add a method to every cluster node (using virtualbox_m as the method's name):

```
[root@onmssrv01 ~]# ccs --addmethod virtualbox_m onmssrv01.local
Method virtualbox_m added to onmssrv01.local.
[root@onmssrv01 ~]# ccs --addmethod virtualbox_m onmssrv02.local
Method virtualbox_m added to onmssrv02.local.
```

Add the fence instance to each cluster node:

```
[root@onmssrv01 ~]# ccs --addfenceinst virtualbox_dev onmssrv01.local virtualbox_m port="opennms-cluster-onmssrv01"
[root@onmssrv01 ~]# ccs --addfenceinst virtualbox_dev onmssrv02.local virtualbox_m port="opennms-cluster-onmssrv02"
```

As an alternative, you can use the *UUIDs* in you want, instead of the *VM* names:

```
[root@onmssrv01 ~]# ccs --addfenceinst virtualbox_dev onmssrv01.local virtualbox_m port="5c467fe9-2611-4e5f-99f6-d1c6aa17527e"
[root@onmssrv01 ~]# ccs --addfenceinst virtualbox_dev onmssrv02.local virtualbox_m port="a379c5c0-2ce0-482a-be49-7237aa67f662"
```

The advantage of using the *UUID* is that the *VM* name can be changed, while the *UUID* should be fixed. Remember to use the command shown at the beginning of the section to obtain the *VM* names or *UUIDs*.

Propagate the cluster configuration and activate it:

```
[root@onmssrv01 ~]# ccs --sync --activate
```

To test the fencing, execute the following command (assuming that the onms_svc service is active on onmssrv02):

```
[root@onmssrv01 ~]# fence_node -vv onmssrv02.local fence onmssrv02.local dev 0.0 agent fence_vbox result: success agent args: port=a379c5c0-2ce0-482a-be49-7237aa67f662 nodename=onmssrv02.local agent=fence_vbox ipaddr=10.0.1.9 login=agalue passwd=9224153 fence onmssrv02.local success
```

RHEL/CentOS 7

Similar to *RHEL/CentOS 6*, there is no fencing device for *VirtualBox*, so I've created one in *Python* using *RedHat's Fencing API* (See Appending A). The script must be placed on /usr/sbin, and must have 0755 for its permissions.

The script <code>fence_vbox</code> is slightly different than the one used on <code>RHEL/CentOS 6</code> because the <code>API</code> was changed, so keep in mind they are not interchangeable. Make sure you use the correct one (see Appending B).

After copying the file to all the cluster nodes at /usr/sbin, and verify they work, configure the fencing mechanism in the cluster.

The following command can be used to get the list of parameters of a given fencing script:

```
[root@onmssrv11 ~]# pcs stonith list | grep vbox
fence_vbox - Fence agent for VirtualBox over SSH
[root@onmssrv11 ~]# pcs stonith describe fence vbox
Stonith options for: fence_vbox
  ipport: TCP/UDP port to use for connection with device
  ipaddr (required): IP Address or Hostname
 port (required): Physical plug number, name of virtual machine or UUID
 secure: SSH connection
 cmd prompt: Force Python regex for command prompt
  inet6 only: Forces agent to use IPv6 addresses only
  identity file: Identity file for ssh
  inet4 only: Forces agent to use IPv4 addresses only
 passwd_script: Script to retrieve password
 passwd: Login password or passphrase
 ssh_options: SSH options to use
 action (required): Fencing Action
 login (required): Login Name
 verbose: Verbose mode
 debug: Write debug information to given file
 version: Display version information and exit
 help: Display help and exit
 separator: Separator for CSV created by operation list
 power wait: Wait X seconds after issuing ON/OFF
 login_timeout: Wait X seconds for cmd prompt after login
 power_timeout: Test X seconds for status change after ON/OFF
 delay: Wait X seconds before fencing is started
 shell_timeout: Wait X seconds for cmd prompt after issuing command
 retry_on: Count of attempts to retry power on
 stonith-timeout: How long to wait for the STONITH action to complete per a stonith device.
 priority: The priority of the stonith resource. Devices are tried in order of highest priority to
 pcmk_host_map: A mapping of host names to ports numbers for devices that do not support host names.
 pcmk_host_list: A list of machines controlled by this device (Optional unless pcmk_host_check=static-
  pcmk_host_check: How to determine which machines are controlled by the device.
```

As you can see the parameters are similar but not exactly the same.

For example:

```
[root@onmssrv01 ~]# /usr/sbin/fence_vbox -a 192.168.205.1 -l onms_user -p onms_passwd -o list | grep onms opennms-cluster-onmssrv01,5c467fe9-2611-4e5f-99f6-d1c6aa17527e opennms-cluster-onmssrv02,a379c5c0-2ce0-482a-be49-7237aa67f662
```

The first thing to do is re-enable stonith:

```
[root@onmssrv01 ~]# pcs property set stonith-enabled=true
```

Then, create a stonith entry for each node:

```
[root@onmssrv01 ~]# pcs stonith create vbox_1 fence_vbox ipaddr=192.168.205.1 \
login=onms_user passwd=onms_passwd \
pcmk_host_map="onmssrv01:opennms-cluster-onmssrv01" \
pcmk_host_list="onmssrv01"

[root@onmssrv01 ~]# pcs stonith create vbox_2 fence_vbox ipaddr=192.168.205.1 \
login=onms_user passwd=onms_passwd \
pcmk_host_map="onmssrv02:opennms-cluster-onmssrv02" \
pcmk_host_list="onmssrv02"
```

The key parameters here are pcmk_host_map and pcmk_host_list.

- pcmk_host_list, contains the list of cluster nodes that are going to be fenced with the fence device.
- pcmk_host_map, contains the map list of each cluster node that is going to be fenced with the fence device.

As mentioned before, the *VM* names on *VirtualBox* might not be the same as the names used for the nodes (and keep in mind that the name of the cluster nodes could be the FQDN or the short name, depending on how you've added them to the cluster). So, the value for this attribute has the following format:

```
pcmk_host_map="{cluster_node_name_X}:{vm_name_in_virtualbox_X}"
```

Now, it is important to tell the cluster where the stonith resources must be allocated. The vbox_1 is defined to fence onmssrv01, so it cannot be running on the same node for obvious reasons. Because of this, we need to define a location constraint for each snotty resource.

```
[root@onmssrv01 ~]# pcs constraint location add fence_onmssrv01_loc vbox_1 onmssrv01 -INFINITY [root@onmssrv01 ~]# pcs constraint location add fence_onmssrv02_loc vbox_2 onmssrv02 -INFINITY fence_onmssrv01_loc means, start vbox_1 anywhere but onmssrv01. fence_onmssrv02_loc means, start vbox_2 anywhere but onmssrv02.
```

You can check the configured settings with the following command:

```
[root@onmssrv02 ~]# pcs stonith show --full
Resource: vbox_1 (class=stonith type=fence_vbox)
Attributes: ipaddr=192.168.205.1 login=onms_user passwd=onms_passwd pcmk_host_map=onmssrv01:opennms-
cluster-onmssrv01 pcmk_host_list=onmssrv01
Operations: monitor interval=60s (vbox_1-monitor-interval-60s)
Resource: vbox_2 (class=stonith type=fence_vbox)
Attributes: ipaddr=192.168.205.1 login=onms_user passwd=onms_passwd pcmk_host_map=onmssrv02:opennms-
cluster-onmssrv02 pcmk_host_list=onmssrv02
Operations: monitor interval=60s (vbox_2-monitor-interval-60s)
```

Use the following command to verify that each stonith resource is associated with the proper cluster node:

```
[root@onmssrv01 ~]# stonith_admin -l onmssrv01
vbox_1
1 devices found
[root@onmssrv01 ~]# stonith_admin -l onmssrv02
vbox_2
1 devices found
```

If you see a different output, check the stonith configuration.

Now, to validate the constraints:

```
[root@onmssrv01 ~]# pcs constraint show --full
Location Constraints:
   Resource: onms_app
      Enabled on: onmssrv01 (score:INFINITY) (role: Started) (id:cli-prefer-onms_app)
   Resource: vbox_1
      Disabled on: onmssrv01 (score:-INFINITY) (id:fence_onmssrv01_loc)
   Resource: vbox_2
      Disabled on: onmssrv02 (score:-INFINITY) (id:fence_onmssrv02_loc)
Ordering Constraints:
Colocation Constraints:
```

The first is related with the resource group, and the last two are associated with the fencing resources.

The cluster status shows the following:

```
[root@onmssrv01 ~]# pcs status
Cluster name: cluster_onms
Last updated: Wed Jul 29 20:06:57 2015
Last change: Wed Jul 29 20:05:56 2015
Stack: corosync
Current DC: onmssrv01 (1) - partition with quorum
Version: 1.1.12-a14efad
2 Nodes configured
8 Resources configured
Online: [ onmssrv01 onmssrv02 ]
Full list of resources:
 Resource Group: onms_app
     virtual_ip(ocf::heartbeat:IPaddr2):Started onmssrv01
     onms_etc(ocf::heartbeat:Filesystem):Started onmssrv01
     onms_var(ocf::heartbeat:Filesystem):Started onmssrv01
     pgpool_etc(ocf::heartbeat:Filesystem):Started onmssrv01
     pgpool_bin(systemd:pgpool):Started onmssrv01
     onms_bin(systemd:opennms):Started onmssrv01
 vbox_1(stonith:fence_vbox):Started onmssrv02
 vbox 2(stonith:fence vbox):Started onmssrv01
PCSD Status:
  onmssrv01: Online
  onmssrv02: Online
Daemon Status:
  corosync: active/enabled
  pacemaker: active/enabled
  pcsd: active/enabled
```

Pacemaker doesn't have a fence_node command to test fencing like *rgmanager* on *RHEL/CentOS 6*. For this reason, testing fence in this case is different.

At this point you should be able to test fencing with stonith_admin -F; or simulate a node problem with killall -9 corosync, on the active cluster node.

```
[root@onmssrv02 ~]# stonith admin -B onmssrv01
```

After running the above command, onmssrv01 will be rebooted and all the resources will be moved to onmssrv02.

Once you start *onmssrv01* again (through *vCenter*), you can see it will join the cluster.

VMWare

As mentioned before, RedHat provides a fencing script for VMWare called fencing_vmware_soap. In order to use it, the SOAP Interface must be enabled on vCenter for a user designated for fencing. This user must be created with the following permissions on vCenter:

```
System.Anonymous
System.View
VirtualMachine.Interact.PowerOff
VirtualMachine.Interact.PowerOn
```

Once the user is configured, you can test the fencing script to be sure it works. The first thing to do is retrieving the list of VMs using fencing_vmware_soap. This will confirm that the credentials are correct, and will give us all the information required to configure fencing on the cluster.

```
[root@onmssrv01 ~]# /usr/sbin/fence_vmware_soap -a vcentersrv01.local -l onms_user -p onms_passwd -z -o list | grep onms onmssrv01,42332447-59ef-4d71-a200-6f3c61b549a9 onmssrv02,423317fe-8ee0-e442-7529-c1f9e3eede38
```

As you can see, you should provide the IP or FQDN of the vCenter server (-a), the user credentials with the required permissions to manipulate VMs as mentioned before (-1, -p), the command (-o), and either the name (-n) or the UUID (-U) of the VM you want to manipulate. Also, it is common that SSL is enabled (-z).

Looking at the output of the list command, the VM's name are displayed at the left side, and their UUIDs appear at the left side. Keep in mind that not necessarily the FQDN of the server is the name of the VM in vCenter. For this reason, it is important to use the above command, or look at the vCenter UI to pick the correct names. Also, it is extremely important to avoid changing the VM name after configuring the fencing if you are planing to use them for fencing instead of the UUIDs.

In order to retrieve the status, you could use either of them, for example:

```
[root@onmssrv01 ~]# /usr/sbin/fence_vmware_soap -a vcentersrv01.local -l onms_user -p onms_passwd -z -o status -n "onmssrv02"
Status: ON

[root@onmssrv01 ~]# /usr/sbin/fence_vmware_soap -a vcentersrv01.local -l onms_user -p onms_passwd -z -o status -U "423317fe-8ee0-e442-7529-c1f9e3eede38"
Status: ON
```

If you want to test further you can request a power-off by using -o off on any of above commands.

Once the script works without issues, you can configure the fencing mechanism on the cluster.

RHEL/CentOS 6

The following command can be used to identify the available parameters of a supported fencing script:

```
[root@onmssrv01 ~]# ccs --lsfenceopts fence_vmware_soap
fence_vmware_soap - Fence agent for VMWare over SOAP API
 Required Options:
 Optional Options:
   option: No description available
    action: Fencing Action
    ipaddr: IP Address or Hostname
    login: Login Name
    passwd: Login password or passphrase
    passwd_script: Script to retrieve password
   ssl: SSL connection
    port: Physical plug number or name of virtual machine
   uuid: The UUID of the virtual machine to fence.
    ipport: TCP port to use for connection with device
    verbose: Verbose mode
    debug: Write debug information to given file
    version: Display version information and exit
   help: Display help and exit
    separator: Separator for CSV created by operation list
    power_timeout: Test X seconds for status change after ON/OFF
    shell_timeout: Wait X seconds for cmd prompt after issuing command
    login_timeout: Wait X seconds for cmd prompt after login
    power_wait: Wait X seconds after issuing ON/OFF
    delay: Wait X seconds before fencing is started
    retry_on: Count of attempts to retry power on
```

The mapping between the parameter names and their equivalent switches are the following:

```
-a: ipaddr
-l: login
-p: passwd
-o: action
-z: ssl
-n: port
-U: uuid
```

Add the fence device (using vmware_dev for the device's name):

```
[root@onmssrv01 ~]# ccs --addfencedev vmware_dev agent=fence_vmware_soap ipaddr= vcentersrv01.local login="onms_user" passwd="onms_passwd"
```

Add a method to every cluster node (using vmware_m for the method's name):

```
[root@onmssrv01 ~]# ccs --addmethod vmware_m onmssrv01.local
Method vmware_m added to onmssrv01.local.
[root@onmssrv01 ~]# ccs --addmethod vmware_m onmssrv02.local
Method vmware_m added to onmssrv02.local.
```

Add the fence instance to each cluster node:

```
[root@onmssrv01 ~]# ccs --addfenceinst vmware_dev onmssrv01.local vmware_m ssl="on" port="onmssrv01" [root@onmssrv01 ~]# ccs --addfenceinst vmware_dev onmssrv02.local vmware_m ssl="on" port="onmssrv02"
```

As an alternative, you can use the *UUIDs* in you want, instead of the *VM* names:

```
[root@onmssrv01 ~]# ccs --addfenceinst vmware onmssrv01.local vmware ssl="on" uuid="423317fe-8ee0-e442-7529-c1f9e3eede38"
[root@onmssrv01 ~]# ccs --addfenceinst vmware onmssrv02.local vmware ssl="on" uuid="42332447-59ef-4d71-a200-6f3c61b549a9"
```

The advantage of using the *UUID* is that the VM name can be changed at any time by the administrators, while the *UUID* should be fixed.

Remember to use the command shown at the beginning of the section to obtain the VM names or UUIDs.

Propagate the cluster configuration and activate it:

```
[root@onmssrv01 ~]# ccs --sync --activate
```

1. Test Fencing

There are several ways to test it:

- Block the network access of the active *VM* through *vCenter*.
- Create an iptables rule to block all the IN/OUT traffic on the machine.
- Use the fence_node command to trigger the fencing on a given node using the information from cluster.conf.

I'm going to use the third option:

```
[root@onmssrv02 ~]# fence_node -vv onmssrv01.local fence onmssrv01.local dev 0.0 agent fence_vmware_soap result: success agent args: port=onmssrv01 ssl=on nodename=centos1 agent=fence_vmware_soap ipaddr= vcentersrv01.local login=onms_user passwd=onms_passwd
```

I tested both configuration options: using the VM names, and then using the UUIDs. Both were working properly.

RHEL/CentOS 7

The following command can be used to get the list of parameters of a given fencing script:

```
[root@onmssrv01 ~]# pcs stonith list | grep vmware
fence_vmware_soap - Fence agent for VMWare over SOAP API
[root@onmssrv01 ~]# pcs stonith describe fence vmware soap
Stonith options for: fence_vmware_soap
  ipport: TCP/UDP port to use for connection with device
 notls: Disable TLS negotiation, force SSL 3.0
 ssl_secure: SSL connection with verifying fence device's certificate
 port (required): Physical plug number, name of virtual machine or UUID
  inet6 only: Forces agent to use IPv6 addresses only
  ipaddr (required): IP Address or Hostname
  inet4 only: Forces agent to use IPv4 addresses only
  passwd script: Script to retrieve password
 passwd: Login password or passphrase
 ssl: SSL connection
  ssl_insecure: SSL connection without verifying fence device's certificate
 action (required): Fencing Action
 login (required): Login Name
 verbose: Verbose mode
 debug: Write debug information to given file
 version: Display version information and exit
 help: Display help and exit
 separator: Separator for CSV created by operation list
 power_wait: Wait X seconds after issuing ON/OFF
 login_timeout: Wait X seconds for cmd prompt after login
  power_timeout: Test X seconds for status change after ON/OFF
 delay: Wait X seconds before fencing is started
 shell_timeout: Wait X seconds for cmd prompt after issuing command
 retry_on: Count of attempts to retry power on
 stonith-timeout: How long to wait for the STONITH action to complete per a stonith device.
 priority: The priority of the stonith resource. Devices are tried in order of highest priority to
 pcmk_host_map: A mapping of host names to ports numbers for devices that do not support host names.
 pcmk_host_list: A list of machines controlled by this device (Optional unless pcmk_host_check=static-
  pcmk_host_check: How to determine which machines are controlled by the device.
```

As you can see the parameters are similar but not exactly the same.

Actually the *VMWare* fencing script is more strict on *RHEL/CentOS* 7 so it might complain about the *SSL Certificate* if it cannot be verified. If this is the case, you should see the following message when running the script:

```
Server side certificate verification failed
```

If you see the above message, add --ssl-insecure to the command and it should work; for example:

Now, the first thing to do is re-enable stonith:

```
[root@onmssrv01 ~]# pcs property set stonith-enabled=true
```

Then, create a stonith entry for each node:

```
[root@onmssrv01 ~]# pcs stonith create vmware_1 fence_vmware_soap \
ipaddr=vcentersrv01.local login=onms_user passwd=onms_passwd \
ssl=1 ssl_insecure=1 \
pcmk_host_map="onmssrv01:onmssrv01" \
pcmk_host_list="onmssrv01"

[root@onmssrv01 ~]# pcs stonith create vmware_2 fence_vmware_soap \
ipaddr=vcentersrv01.local login=onms_user passwd=onms_passwd \
ssl=1 ssl_insecure=1 \
pcmk_host_map="onmssrv02:onmssrv02" \
pcmk_host_list="onmssrv02"
```

NOTE

If you don't have problems with the *SSL Certificate*, you can remove the ssl_insecure parameter from the above commands.

The key parameters here are pcmk_host_map and pcmk_host_list.

- pcmk_host_list, contains the list of cluster nodes that are going to be fenced with the fence device.
- pcmk_host_map, contains the map list of each cluster node that is going to be fenced with the fence device.

As mentioned before, the *VM* names on *vCenter* might not be the same as the names used for the nodes (and keep in mind that the name of the cluster nodes could be the *FQDN* or the short name, depending on how you've added them to the cluster). So, the value for this attribute has the following format:

```
pcmk_host_map="{cluster_node_name_X}:{vm_name_on_vcenter_X}"
```

Now, it is important to tell the cluster where the stonith resources must be allocated. The vbox_1 is defined to fence onmssrv01, so it cannot be running on the same node for obvious reasons. because of this, we need to define a location constraint for each snotty resource"

```
[root@onmssrv01 ~]# pcs constraint location add fence_onmssrv01_loc vmware_1 onmssrv01 -INFINITY [root@onmssrv01 ~]# pcs constraint location add fence_onmssrv02_loc vmware_2 onmssrv02 -INFINITY fence_onmssrv01_loc means, start vmware_1 anywhere but onmssrv01. fence_onmssrv02_loc means, start vmware_2 anywhere but onmssrv02.
```

You can check the configured settings with the following command:

```
[root@onmssrv02 ~]# pcs stonith show full
Resource: vmware_1 (class=stonith type=fence_vmware_soap)
Attributes: ipaddr=vcentersrv01.local login=onms_user passwd=onms_passwd ssl=1 ssl_insecure=1
pcmk_host_map=onmssrv01:onmssrv01 pcmk_host_list=onmssrv01
Operations: monitor interval=60s (vmware_1-monitor-interval-60s)
Resource: vmware_2 (class=stonith type=fence_vmware_soap)
Attributes: ipaddr=vcentersrv01.local login=onms_user passwd=onms_passwd ssl=1 ssl_insecure=1
pcmk_host_map=onmssrv02:onmssrv02 pcmk_host_list=onmssrv02
Operations: monitor interval=60s (vmware_2-monitor-interval-60s)
```

Use the following command to verify that each stonith resource is associated with the proper cluster node:

```
[root@onmssrv01 ~]# stonith_admin -l onmssrv01
vmware_1
1 devices found
[root@onmssrv01 ~]# stonith_admin -l onmssrv02
vmware_2
1 devices found
```

If you see a different output, check the stonith configuration.

Now, to validate the constraints:

```
[root@onmssrv01 ~]# pcs constraint show --full
Location Constraints:
   Resource: onms_app
      Enabled on: onmssrv01 (score:INFINITY) (role: Started) (id:cli-prefer-onms_app)
   Resource: vmware_1
      Disabled on: onmssrv01 (score:-INFINITY) (id:fence_onmssrv01_loc)
   Resource: vmware_2
      Disabled on: onmssrv02 (score:-INFINITY) (id:fence_onmssrv02_loc)
Ordering Constraints:
Colocation Constraints:
```

The first is related with the resource group, and the last two are associated with the fencing resources.

The cluster status shows the following:

```
[root@onmssrv01 ~]# pcs status
Cluster name: cluster_onms
Last updated: Fri Jul 24 19:40:51 2015
Last change: Fri Jul 24 19:29:12 2015
Stack: corosync
Current DC: onmssrv02 (2) - partition with quorum
Version: 1.1.12-a14efad
2 Nodes configured
8 Resources configured
Online: [ onmssrv01 onmssrv02 ]
Full list of resources:
 Resource Group: onms_app
     virtual_ip(ocf::heartbeat:IPaddr2):Started onmssrv01
     onms_etc(ocf::heartbeat:Filesystem):Started onmssrv01
     onms_var(ocf::heartbeat:Filesystem):Started onmssrv01
     pgpool_etc(ocf::heartbeat:Filesystem):Started onmssrv01
     pgpool_bin(systemd:pgpool):Started onmssrv01
     onms_bin(systemd:opennms):Started onmssrv01
 vmware_1(stonith:fence_vbox):Started onmssrv02
 vmware_2(stonith:fence_vbox):Started onmssrv01
PCSD Status:
  onmssrv01: Online
  onmssrv02: Online
Daemon Status:
  corosync: active/enabled
  pacemaker: active/enabled
  pcsd: active/enabled
```

Pacemaker doesn't have a fence_node command to test fencing like *rgmanager* on *RHEL/CentOS 6*. For this reason, testing fence in this case is different.

At this point you should be able to test fencing with stonith_admin -F; or simulate a node problem with killall -9 corosync, on the active cluster node.

```
[root@onmssrv02 ~]# stonith_admin -B onmssrv01
```

After running the above command, onmssrv01 will be rebooted and all the resources will be moved to onmssrv02.

Once you start onmssrv01 again (through *vCenter*), you can see it will join the cluster.