

RouteFlow

Wholesale Distribution Management System

v1.0.0

April 2026

Internal Use — Not for Distribution

PART 1 — SYSTEM OVERVIEW	4
1.1 What RouteFlow Does	4
1.2 Who Uses RouteFlow	4
1.3 System Architecture	4
1.4 Accessing RouteFlow	4
PART 2 — GETTING STARTED	4
2.1 Logging In	5
2.2 Password Reset	5
2.3 Your Dashboard	5
2.4 Navigation	5
PART 3 — OPERATOR GUIDE	6
3.1 Customer Management	6
3.2 Supplier Management	6
3.3 Inventory Management	6
3.4 Order Management	7
3.5 Route Management	8
3.6 Invoicing	8
3.7 Customer Credit Balance System	9
3.8 Expense Management	10
3.9 User and Account Administration	10
3.10 Notifications and Alerts	10
PART 4 — DRIVER GUIDE	11
4.1 Your Route View	11
4.2 Completing a Delivery	11
4.3 Recording a Failed Delivery	11
4.4 Viewing a Customer's Balance	11
4.5 Submitting an Expense	11
PART 5 — CUSTOMER PORTAL GUIDE	12
5.1 Logging Into Your Account	12
5.2 Viewing Your Orders	12
5.3 Your Account Statement	12
5.4 Your Invoices	12
5.5 Updating Your Contact Information	12
5.6 Getting Help	13
PART 6 — SYSTEM REFERENCE	13
6.1 Roles and Permissions	13
6.2 Order Status Definitions	14
6.3 Ledger Entry Types	15
6.4 Finance Reports Reference	15

6.5 Notification Reference	16
6.6 Keyboard Shortcuts	16
6.7 Error Messages Reference.....	16
PART 7 — TROUBLESHOOTING.....	16
7.1 I cannot log in	17
7.2 My session keeps expiring	17
7.3 An order will not submit	17
7.4 A customer's credit balance looks wrong	17
7.5 A route is not showing in the driver app	17
7.6 An invoice total does not match what I expected	17
7.7 A file upload failed	17
7.8 The map is not loading	17
PART 8 — APPENDIX.....	17
A. Glossary	18
B. Version History	18
C. Data Retention and Privacy	18
D. Contact and Support	19
PART 9 — PLATFORM ADMINISTRATOR GUIDE	19
9.1 What Is a Tenant?	19
9.2 Logging In as Platform Administrator	19
9.3 Platform Admin Dashboard	19
9.4 Tenant Management	19
9.5 Creating a New Tenant.....	20
9.6 Tenant Detail Page.....	20
9.7 Impersonation	21
9.8 Subscription and Billing	21
9.9 Audit Logs.....	21
9.10 Tenant Settings (Tenant Admin)	22

PART 1 — SYSTEM OVERVIEW

1.1 What RouteFlow Does

RouteFlow is an end-to-end wholesale distribution management system. It handles the complete order-to-cash cycle: product catalog management, customer orders, route planning and execution, delivery confirmation, invoicing, payment collection, and financial reporting. From the moment a product is stocked to the moment a customer's invoice is paid, RouteFlow tracks and records every step.

1.2 Who Uses RouteFlow

RouteFlow serves three primary roles within each business:

OPERATOR / TENANT_ADMIN: The business owner or office manager. Full access to all features — managing customers, products, inventory, orders, routes, invoices, finance reports, and account settings.

DRIVER: Field staff who execute deliveries. Access via the mobile app. Views assigned routes and stops, marks deliveries complete, records failed deliveries, submits expenses, and collects payments on delivery.

CUSTOMER: The end buyer accessing their own account portal. Can view their orders, invoices, credit balance, and account statement. Cannot place new orders directly through the portal.

1.3 System Architecture

RouteFlow is a cloud-hosted web application deployed on Railway. Data is stored in a PostgreSQL database. Authentication uses JWT tokens (access + refresh). Address geocoding uses the OpenStreetMap Photon API. Outbound email is sent via SMTP (configurable per tenant). Mobile push notifications use Firebase Cloud Messaging (FCM). The driver mobile app is built with React Native (Expo) and works on iOS and Android.

[SCREENSHOT: 1.3-railway-dashboard.png]

1.4 Accessing RouteFlow

- Web app: Open Chrome or Edge and navigate to your RouteFlow URL (provided by your administrator)
- Optimal display: 1440px width or wider for the operator interface
- Driver app: Install the RouteFlow Driver app from the App Store or Google Play; log in with your company code and credentials
- Mobile web: Supported on Safari (iOS) and Chrome (Android) at 390px width

PART 2 — GETTING STARTED

2.1 Logging In

Navigate to your RouteFlow URL. Enter your username and password. Press Enter on the username field to move to the password field, or press Enter on the password field to submit. Click Sign In. If your organization has Google OAuth configured, a "Sign in with Google" button will also appear.

[SCREENSHOT: 2.1-login-page.png]

2.2 Password Reset

Passwords are managed by your account administrator. If you forget your password, contact your administrator — they can issue a temporary password from Settings → Team. On your next login, the system will require you to set a new password before you can proceed. If your organization has Google OAuth enabled, you can log in with your Google account without a password.

[SCREENSHOT: 2.2-force-password-change.png]

2.3 Your Dashboard

After logging in, you are taken to your role-specific dashboard:

Operator Dashboard: KPI cards showing orders by status, revenue totals, overdue invoices, and low-stock products. Below the cards: an active routes table and a recent orders table.

Driver Dashboard (mobile): Your assigned routes for today, with stop count and scheduled time for each.

Customer Dashboard: A quick summary of your recent orders and current account balance.

[SCREENSHOT: 2.3-operator-dashboard.png]

[SCREENSHOT: 2.3-driver-dashboard-mobile.png]

[SCREENSHOT: 2.3-customer-dashboard.png]

2.4 Navigation

Operator/Admin: A collapsible sidebar on the left shows all modules: Dashboard, Customers, Orders, Returns, Routes, Drivers, Products, Inventory, Suppliers, Invoices, Estimates, Credit Notes, Finance, Analytics, Settings. Collapse to icon-only mode using the arrow button.

Customer: Left sidebar shows Dashboard, Orders, Returns, Invoices, Settings only.

Driver (mobile): Bottom tab bar shows Dashboard, My Routes, Settings.

The notification bell (top right, web) shows an unread count. Click to see recent notifications. Your user avatar (top right) opens a dropdown with profile and logout options.

[SCREENSHOT: 2.4-operator-navigation.png]

PART 3 — OPERATOR GUIDE

3.1 Customer Management

Customer list: Search by business name, contact name, email, or phone. Filter by status (Active / Inactive). The list shows receivable balances and available credit for each customer.

Create / edit customer: Fill in business name, contact name, email, phone, billing address (with autocomplete suggestions), customer type, tax ID, payment terms, credit limit, and optional tags.

Customer detail tabs:

- Profile — contact and address information
- Orders — all orders for this customer
- Addresses — delivery addresses
- Standing Orders — recurring order templates
- Invoices — all invoices for this customer
- Billing — ledger, advance payments, and statement
- Special Prices — customer-specific product pricing
- Comments — internal notes

Deactivating a customer: Toggle the status switch. Inactive customers cannot be selected for new orders or routes.

Bulk actions: Import customers via CSV (Zoho format supported), export to CSV, and merge duplicate records.

[SCREENSHOT: 3.1-customer-list.png]

[SCREENSHOT: 3.1-new-customer-form.png]

[SCREENSHOT: 3.1-customer-detail.png]

3.2 Supplier Management

Create a supplier with company name, contact person, phone, mobile, email, lead time (days), address, and notes. Link suppliers to products via purchase orders. Deactivate a supplier when no longer in use — this preserves historical purchase order data.

[SCREENSHOT: 3.2-supplier-list.png]

3.3 Inventory Management

Products: View in table or grid mode. Search by SKU, barcode, or product name. Filter by stock status (In Stock, Low Stock, Out of Stock).

New product form: Name, SKU, barcode, category, unit of measure, description, product images, list price, cost price, reorder point, and reorder quantity.

Manual stock adjustment: Select a product, choose the adjustment type (Stock In, Stock Return, Damage, or Adjustment), enter quantity and notes. The adjustment is logged with user and timestamp.

Low stock alert: When stock quantity falls to or below the reorder point, the product is flagged. A low-stock widget appears on the operator dashboard.

Purchase Orders: Track supplier orders with status: Draft → Sent → Partial → Received → Closed.

CSV Bulk Import — Column Format:

Column	Type	Required	Example
NAME	Text	Yes	Sourdough Loaf 800g
SKU	Text	Yes	BRD-001
BARCODE	Text	No	1234567890001
CATEGORY	Text	No	Bread
UNIT	Text	No	each
PRICE	Number	Yes	4.50
COST	Number	No	2.00
STOCK	Integer	No	50
REORDER_POINT	Integer	No	10

Deactivate vs. delete: Deactivating a product preserves all historical order and invoice data. Deleting is permanent and only allowed for products in draft status.

[SCREENSHOT: 3.3-inventory-list.png]

[SCREENSHOT: 3.3-new-product-form.png]

[SCREENSHOT: 3.3-stock-adjustment.png]

3.4 Order Management

Create an order: Select a customer, then add line items by searching products (or scanning a barcode). Customer-specific pricing is applied automatically. Add notes if needed.

Line items: Edit quantity inline. Add or remove items. Totals update in real time.

Status lifecycle: PENDING → CONFIRMED → OUT_FOR_DELIVERY → DELIVERED. Any non-delivered order can be CANCELLED.

Editing rules: Orders can be edited while PENDING or CONFIRMED. Once OUT_FOR_DELIVERY or DELIVERED, the order is read-only.

Cancellation: Cancelling an order does not automatically restock inventory — create a manual stock adjustment if needed.

Audit trail: Every status change is logged with the acting user and timestamp.

[SCREENSHOT: 3.4-order-create.png]

[SCREENSHOT: 3.4-order-detail.png]

[SCREENSHOT: 3.4-order-list.png]

3.5 Route Management

Create a route: Enter a route name, optionally assign a default driver, and add customer stops by searching. Stops can be reordered by drag and drop. Each stop shows a geocoded map pin.

Duplicate stops: The system prevents the same customer from appearing more than once on a single route.

Assign and dispatch: Use the dispatcher modal to select a driver, set a scheduled date, and dispatch. The route run status moves from SCHEDULED to IN_PROGRESS when the driver begins.

Route run statuses: SCHEDULED → IN_PROGRESS → COMPLETED. Can also be CANCELLED.

Route optimization: Auto-reorder stops for delivery efficiency using the Optimize Route button.

Real-time progress: Each stop shows its status: PENDING, IN_PROGRESS, COMPLETED, or SKIPPED.

Packing list: Download a PDF listing all items to be delivered at each stop.

[SCREENSHOT: 3.5-route-builder.png]

[SCREENSHOT: 3.5-route-map.png]

[SCREENSHOT: 3.5-driver-assignment.png]

3.6 Invoicing

Generate from order: After delivery, open the order, go to the Invoice tab, and click Create Invoice. Line items are auto-populated from the delivered order.

Invoice lifecycle: DRAFT → SENT → VIEWED → PARTIAL / PAID / OVERDUE. Voidable unless PAID.

Sending an invoice: Email (via your SMTP settings), download PDF, or share via WhatsApp link.

Recording a payment:

- Amount
- Method: Cash, Check, ACH, Credit Card, Other, Credit Note, or Advance (customer credit balance)
- Reference number

- Date
- Bank charges (if applicable)

Partial payments: When a payment does not cover the full amount, the invoice status becomes PARTIAL and the remaining balance is shown.

Credit notes: Create from an invoice or as a standalone credit. Status: DRAFT → ISSUED → APPLIED. Can be applied to a specific invoice or left as account credit.

Void invoice: Available while the invoice is unpaid. Use for billing errors. Voiding does not affect inventory.

AR aging: The Finance dashboard shows a stacked bar chart of receivables aged into Current, 1–15 days, 16–30 days, 31–45 days, and 45+ days.

[SCREENSHOT: 3.6-invoice-generate.png]

[SCREENSHOT: 3.6-invoice-detail.png]

[SCREENSHOT: 3.6-finance-dashboard.png]

3.7 Customer Credit Balance System

What the credit balance represents: A customer's credit balance is money held by your business on their behalf. It reduces future invoice amounts when applied. Credit balances can come from advance payments (customer pays before an invoice exists), overpayments (payment exceeds the invoice total), or credit notes applied to the account rather than a specific invoice.

Recording an advance payment — worked example:

1. Customer Harbor Cafe drops off a check for \$500 before any invoice is issued.
2. Open Customers → Harbor Cafe → Billing tab → Record Advance Payment.
3. Fill in: Amount = \$500, Method = Check, Reference = Chk #1042, Date = today.
4. The system records an ADVANCE ledger entry. Harbor Cafe's credit balance is now \$500.

Applying credit to an invoice — worked example:

5. Create Invoice INV-0089 for Harbor Cafe, total = \$320.
6. On the Record Payment screen, select Method = Advance.
7. Enter Amount = \$320 (or less for partial application).
8. The system deducts \$320 from the \$500 credit balance.
9. Invoice becomes PAID. Harbor Cafe's remaining credit = \$180.

Viewing the customer ledger: Customer detail → Billing tab → Statement section. Shows every ledger entry with type, date, amount, and running balance.

Issuing a credit note: Finance → Credit Notes → New → select customer, enter amount and reason → Issue → Apply to Invoice (or leave as account credit).

Manual adjustments: Use only to correct data entry errors. A reason is required. All adjustments are logged in the audit trail.

Dormant credit review: Customers with credit balances unused for 90 or more days should be reviewed periodically. There is no automated expiry, but the aging report can help identify these accounts.

[SCREENSHOT: 3.7-credit-balance-panel.png]

[SCREENSHOT: 3.7-customer-ledger.png]

[SCREENSHOT: 3.7-advance-payment-form.png]

3.8 Expense Management

Record an expense: Date, category, vendor or supplier, amount, description, and optional receipt upload (photo or PDF).

AI receipt extraction: Upload a receipt image and click Extract Items — the system auto-fills the amount, date, and vendor name.

Expense categories: Configurable per tenant — common defaults include Rent, Utilities, Supplies, Salaries, Marketing, Insurance, and Other.

Reports: Expense Details, Expenses by Category, and Expenses by Customer are available from the Finance → Reports section.

[SCREENSHOT: 3.8-expense-list.png]

[SCREENSHOT: 3.8-expense-detail.png]

3.9 User and Account Administration

Team management: Settings → Team. View all users, create a new user (username, email, role, temporary password), edit user details, and toggle user status.

Roles: OPERATOR has full access. DRIVER has field-access only (mobile). CUSTOMER has read-only portal access.

Deactivating a user: Toggle their status to Inactive. The user cannot log in until reactivated.

Password reset: Click Reset Password on the user row. The user will be forced to change their password on next login.

Sessions: No concurrent session limit. Logging out on one device clears that device's refresh token only.

[SCREENSHOT: 3.9-user-management.png]

3.10 Notifications and Alerts

Invoice sent email: Triggered when the operator clicks Send on an invoice. The recipient is the customer email address on file.

Payment reminder email: Triggered manually from the invoice detail page. Does not automatically change the invoice status.

Push notifications (mobile): Firebase Cloud Messaging. Drivers receive push notifications when their route is updated.

Low stock alert: Appears on the operator dashboard when a product's stock falls to or below its reorder point.

In-app notification bell: Shows unread count. Click to see all recent notifications.

PART 4 — DRIVER GUIDE

4.1 Your Route View

Log in to the driver app. Your dashboard shows all routes assigned to you for today. Each route card shows the route name, number of stops, and scheduled time. Tap a route to see the stop list, which shows customer name, delivery address, and order summary for each stop. Work through stops from top to bottom.

[SCREENSHOT: 4.1-driver-route-list-mobile.png]

[SCREENSHOT: 4.1-driver-stop-detail-mobile.png]

4.2 Completing a Delivery

At the customer location, tap the stop. Review the items to deliver. Tap Mark Delivered. A confirmation dialog appears — confirm to proceed. The stop turns green and the route progress updates automatically.

[SCREENSHOT: 4.2-delivery-confirmation-mobile.png]

4.3 Recording a Failed Delivery

At the stop, tap Cannot Deliver or Skip Stop. Select a reason: Customer Not Present, Refused Delivery, Address Not Found, or Other. Add a note if needed, then tap Submit. The stop is marked SKIPPED and the dispatcher is notified automatically.

[SCREENSHOT: 4.3-failed-delivery-mobile.png]

4.4 Viewing a Customer's Balance

The stop detail screen shows the customer's current outstanding balance. You can view this information but you cannot issue credit notes, record payments, or edit the balance from the mobile app. If the customer asks about their credit, direct them to contact the office.

4.5 Submitting an Expense

Tap Settings → Expenses (or use the Expense shortcut on the dashboard). Fill in Date, Category, and Amount (all required). To attach a receipt, tap the camera icon and take a photo or choose from your gallery. Tap Submit. The expense is sent to the operator for review. You cannot approve your own expenses.

[SCREENSHOT: 4.5-expense-form-mobile.png]

PART 5 — CUSTOMER PORTAL GUIDE

5.1 Logging Into Your Account

Go to the RouteFlow web address your supplier gave you. Enter your username and password. Press Enter or click Sign In.

[SCREENSHOT: 5.1-customer-login.png]

5.2 Viewing Your Orders

After logging in, click Orders in the left menu. You will see a list of all your orders, newest first. Each order shows the order number, date, items, total, and status. Status meanings: Pending means your order is being prepared. Confirmed means it has been approved. Out for Delivery means it is on the way. Delivered means the delivery is complete. Cancelled means the order was cancelled.

[SCREENSHOT: 5.2-customer-order-list.png]

5.3 Your Account Statement

Go to Settings → Statement, or click the account summary on your dashboard. The statement shows all charges and payments on your account in date order. A positive credit balance means money is available to offset your next invoice.

[SCREENSHOT: 5.3-customer-statement.png]

5.4 Your Invoices

Click Invoices in the left menu. To download an invoice, click the invoice number, then click Download PDF. If an invoice shows a credit applied line, that means a credit note or advance payment was used to reduce the amount you owe.

[SCREENSHOT: 5.4-customer-invoice.png]

5.5 Updating Your Contact Information

Click Settings in the left menu. Update your phone number, email address, or delivery address. Click Save Changes.

[SCREENSHOT: 5.5-customer-profile.png]

5.6 Getting Help

For questions about your account, invoices, or orders: contact your supplier's office directly. For delivery issues: contact your delivery driver or the office. [Contact information placeholder — fill in before publishing]

PART 6 — SYSTEM REFERENCE

6.1 Roles and Permissions

Five roles exist in RouteFlow. SUPER_ADMIN is a platform-level role for RouteFlow staff only. TENANT_ADMIN is the business owner with the same access as OPERATOR plus user management. OPERATOR, DRIVER, and CUSTOMER are the everyday business roles.

Roles and Permissions Matrix:

Action	SUPER_ADMIN	TENANT_ADMIN	OPERATOR	DRIVER	CUSTOMER
View all customers	Yes (all tenants)	Yes	Yes	Yes (read)	No
Create / edit customer	Yes	Yes	Yes	No	No
View all orders	Yes	Yes	Yes	Yes (assigned)	Yes (own)
Create order	Yes	Yes	Yes	Yes	No
Update order status	Yes	Yes	Yes	Yes (limited)	Yes (cancel own)
View routes	Yes	Yes	Yes	Yes (assigned)	No
Create / edit routes	Yes	Yes	Yes	No	No
Mark stop delivered	Yes	Yes	Yes	Yes	No
Create invoice	Yes	Yes	Yes	No	No
View invoices	Yes	Yes	Yes	No	Yes (own)
Record payment	Yes	Yes	Yes	No	No
Issue credit note	Yes	Yes	Yes	No	No

Action	SUPER_ADMIN	TENANT_ADMIN	OPERATOR	DRIVER	CUSTOMER
View credit notes	Yes	Yes	Yes	No	Yes (own)
View products	Yes	Yes	Yes	Yes	No
Edit products	Yes	Yes	Yes	No	No
Adjust stock	Yes	Yes	Yes	Yes	No
View finance reports	Yes	Yes	Yes	No	No
Manage expenses	Yes	Yes	Yes	Yes (own)	No
Manage users (tenant)	No	Yes	Yes	No	No
View own profile	Yes	Yes	Yes	Yes	Yes
Create / manage tenants	Yes	No	No	No	No
View all tenant data	Yes	No	No	No	No
Impersonate tenants	Yes	No	No	No	No
View platform audit logs	Yes	No	No	No	No
Change tenant plan/billing	Yes	No	No	No	No

6.2 Order Status Definitions

Status	Meaning	Who Can Set	Actions Available
PENDING	Order received, awaiting confirmation	System on create	Confirm, Cancel, Edit items
CONFIRMED	Approved for fulfillment	OPERATOR	Dispatch, Cancel, Edit items
OUT_FOR_DELIVERY	On an active route run	OPERATOR / DRIVER	Mark delivered, initiate return
DELIVERED	Delivery confirmed	OPERATOR / DRIVER	Create invoice, create return
CANCELLED	Voided	OPERATOR, CUSTOMER (own pending orders)	Reopen (OPERATOR only)

6.3 Ledger Entry Types

Type	Created By	Effect on Balance	Who Can Create
INVOICE	Invoice creation	Increases amount owed	OPERATOR
PAYMENT	Payment recorded	Decreases amount owed	OPERATOR
ADVANCE	Advance payment recorded	Creates credit balance	OPERATOR
CREDIT_NOTE	Credit note applied	Reduces amount owed	OPERATOR
CREDIT_APPLIED	Credit applied to invoice	Reduces both credit balance and invoice	OPERATOR

6.4 Finance Reports Reference

RouteFlow includes 19 built-in finance reports accessible from Finance → Reports:

Report	Description
Sales by Customer	Total revenue grouped by customer for the selected period
Sales by Item	Total revenue grouped by product
Sales by Driver	Total revenue grouped by driver
AR Aging Summary	Receivables bucketed by days outstanding
AR Aging Details	Individual invoice breakdown by age bucket
Invoice Details	Line-item detail for all invoices
Bad Debts	Written-off invoices and amounts
Customer Balance Summary	Current balance owed by each customer
Estimate Details	All estimates with status and value
Receivable Summary	Total outstanding receivables snapshot
Payments Received	All payments by date and method
Time to Get Paid	Average days from invoice to payment by customer
Refund History	All credit notes and refunds issued
Expense Details	All expenses with category and vendor
Expenses by Category	Expense totals grouped by category
Expenses by Customer	Expenses attributed to specific customers
Profit and Loss	Revenue minus cost of goods and expenses
Cash Flow	Cash in and out over time

Report	Description
Transactions Ledger	Full double-entry ledger of all financial events

6.5 Notification Reference

Trigger	Recipient	Channel	Content
Invoice sent	Customer	Email	Invoice PDF, total, and due date
Payment reminder	Customer	Email	Outstanding balance reminder
Route updated	Driver	Push (mobile)	Route status or stop change notification
Low stock	Operator	In-app	Product name and current stock level

6.6 Keyboard Shortcuts

Key	Action
Enter (username field)	Move focus to password field
Enter (password field)	Submit login form

6.7 Error Messages Reference

Message	Meaning	What to Do
Invalid credentials	Username or password is incorrect	Check username; reset password if needed
Account suspended	Your account has been deactivated	Contact your administrator
Cannot cancel a delivered order	Order is past cancellation	Contact the operator
Advance payment amount exceeds available balance	Customer has less credit than the amount being applied	Check the customer's current credit balance
Cannot void a paid invoice	Invoice already has payments recorded	Void the payments first, then void the invoice
Session expired	Your login session timed out	Log in again — your work is saved
Slug already taken	Another tenant is using this slug	Choose a different slug
Reserved slug	The chosen slug is not allowed	Choose a different slug (see reserved list in Section 9.5)

PART 7 — TROUBLESHOOTING

7.1 I cannot log in

Check that you are entering your username, not your email address. Check that Caps Lock is off. If this is your first login, the system may be requiring you to change your password. Contact your administrator if your account may have been deactivated.

7.2 My session keeps expiring

Sessions expire after a period of inactivity — this is a security feature. Log in again. Your data is not lost.

7.3 An order will not submit

Ensure a customer is selected. Ensure at least one item has been added. Check that each item has a quantity greater than zero. Look for validation errors highlighted in red on required fields.

7.4 A customer's credit balance looks wrong

Open the customer record → Billing tab → Statement. Review each ledger entry in order. Check whether a credit note was voided or a payment was reversed. Contact support if an entry appears to be incorrect.

7.5 A route is not showing in the driver app

Confirm the route run has been dispatched — its status should be SCHEDULED or IN_PROGRESS. Confirm the correct driver is assigned to that run. Have the driver log out and log back in to refresh their route list.

7.6 An invoice total does not match what I expected

Verify the tax rate in Settings → Business Profile. Check whether a customer-specific price is applied (Customers → [name] → Special Prices tab). Check for any discount applied to a line item.

7.7 A file upload failed

Supported file types: PNG, JPG, PDF. Maximum file size: 10 MB. Ensure a stable internet connection and try again.

7.8 The map is not loading

Map data comes from OpenStreetMap via the Photon geocoding API. Check your internet connection. If addresses are not resolving, ensure the address includes street, city, state, and ZIP code.

PART 8 — APPENDIX

A. Glossary

Term	Definition
Route	A delivery sequence assigning a driver to a list of customer stops.
Stop	One customer delivery location on a route.
Route Run	A specific scheduled execution of a route, with an assigned driver and date.
Invoice	A formal bill sent to a customer for goods delivered.
Credit Note	A document that reduces a customer's outstanding balance.
Advance Payment	A pre-payment from a customer that creates a credit balance.
Credit Balance	Money the business holds on a customer's behalf, available to offset future invoices.
Statement	A chronological record of all charges and payments for a customer account.
Ledger Entry	A single line in the financial record (payment, invoice, credit, etc.).
Standing Order	A recurring order template that generates orders automatically on a set schedule.
Dispatch	The act of assigning a driver to a route run and setting it to active.
FIFO	First In First Out — the stock depletion method used for inventory costing.
DSO	Days Sales Outstanding — the average number of days between issuing an invoice and receiving payment.
AR	Accounts Receivable — money owed to the business by customers.
PO	Purchase Order — a formal request to a supplier for goods.
Tenant	A single isolated business instance within the RouteFlow platform, identified by a unique slug.
Slug	A short URL-safe identifier for a tenant (e.g., acme-foods).
Impersonation	A platform administrator accessing a tenant's account in read-only mode for support purposes.
Audit Log	A system-generated record of every significant action, who performed it, and when.
Trial	A time-limited free access period for new tenants before they must activate a subscription.

B. Version History

Version	Date	Summary
v1.0.0	April 2026	Initial production release — orders, routes, invoicing, inventory, bookkeeping, customer portal, driver app, multi-tenant platform

C. Data Retention and Privacy

RouteFlow stores customer names, addresses, order history, invoice data, and payment records. All data is scoped to your business account and is not shared with other RouteFlow customers. Data is retained for the life of your account. Contact your administrator or RouteFlow support to request data deletion.

D. Contact and Support

[Placeholder — insert support email, phone, and hours before publishing]

PART 9 — PLATFORM ADMINISTRATOR GUIDE

This section is intended for RouteFlow staff and designated super-administrators who manage the SaaS platform. Individual business customers do not have access to these features.

9.1 What Is a Tenant?

RouteFlow is a multi-tenant system. Each tenant is one isolated business instance with its own users, customers, orders, drivers, routes, and financial data. Tenants cannot see each other's data. A tenant is identified by a slug — a short, URL-safe name (e.g., acme-foods) used as the tenant's access key.

9.2 Logging In as Platform Administrator

Navigate to /admin/login — this is a separate login page from the regular business login. Enter your SUPER_ADMIN username and password. The system rejects non-SUPER_ADMIN credentials on this page. On success, you are taken to the Platform Admin Dashboard.

9.3 Platform Admin Dashboard

The dashboard shows summary cards for: Total tenants, Active tenants, Trial tenants, Suspended tenants, and a plan breakdown (how many tenants are on STARTER, PROFESSIONAL, and ENTERPRISE). A Recent Tenants table shows the last five tenants created.

9.4 Tenant Management

Tenant list view: Search by slug or business name. Filter by status: TRIAL, ACTIVE, SUSPENDED, or CANCELLED. Columns show: Slug, Business Name, Status, Plan, User Count, and Created Date. Each row has actions: View, Suspend or Reactivate, and Impersonate.

Tenant statuses:

Status	Meaning
TRIAL	New tenant with limited-time access. Expires in 14 days (self-registered) or 7 days (admin-provisioned)
ACTIVE	Paid subscription in good standing
SUSPENDED	Access blocked — expired trial, payment failure, or manual suspension. Data preserved

Status	Meaning
CANCELLED	Account soft-deleted. Data preserved but inaccessible

9.5 Creating a New Tenant

Navigate to Tenants → Create Tenant.

Create tenant fields:

Field	Rules
Slug	Required. 3–30 characters. Lowercase letters, numbers, and hyphens only. Must be unique
Business Name	Required. 2–100 characters
Admin Email	Required. Where credentials and billing links are sent
Admin Username	Required. 3–50 characters. The TENANT_ADMIN login username
Admin Password	Required. Minimum 8 characters. Tenant admin must change on first login
Plan	Required. STARTER, PROFESSIONAL, or ENTERPRISE

Reserved slugs — the following cannot be used: api, www, admin, app, static, assets, mail, support, platform, login, signup, register, billing, dashboard.

On creation, a welcome email is sent to the admin email address with login credentials. If Stripe is configured, a payment link is also included.

[SCREENSHOT: 9.5-create-tenant-form.png]

9.6 Tenant Detail Page

Opening a tenant shows the info panel (ID, slug, business name, plan, created date, trial end date with countdown), usage stats (Users, Customers, Orders, Drivers, Routes), actions panel, and recent audit logs (last 20 platform actions for this tenant).

Tenant detail actions:

Action	What It Does
Suspend	Blocks all logins for the tenant. Data is preserved
Reactivate	Restores access to a SUSPENDED tenant
Change Plan	Switches the tenant between STARTER, PROFESSIONAL, and ENTERPRISE
Impersonate	Grants 15-minute read-only access to the tenant's account
Extend Trial	Adds days to the trial period (enter 1–365 days)

Action	What It Does
Reset Admin Password	Generates a temporary password. Tenant admin must change it on next login
Delete Tenant	Soft-deletes the tenant (status = CANCELLED). Data is preserved but inaccessible

[SCREENSHOT: 9.6-tenant-detail-page.png]

9.7 Impersonation

Impersonation lets a platform administrator view a tenant's account as if they were the TENANT_ADMIN. This is used for support and diagnostics. Click Impersonate on the tenant detail page. You are redirected to that tenant's dashboard. An impersonation banner is displayed at the top of every page during the session. Impersonation is read-only: all create, edit, and delete actions are blocked by the system. The session expires automatically after 15 minutes. To exit early, click Exit Impersonation in the banner, or log out.

[SCREENSHOT: 9.7-impersonation-banner.png]

9.8 Subscription and Billing

RouteFlow integrates with Stripe for subscription billing. When configured: Tenants on TRIAL are prompted to add a payment method before the trial expires. Plans are billed monthly or annually based on Stripe product configuration. If a payment fails, a 3-day grace period applies before automatic suspension. Platform admin can generate a Stripe Checkout link or Billing Portal link from the tenant detail page.

Subscription plans:

Plan	Stripe Price Source
STARTER	STRIPE_PRICE_STARTER environment variable
PROFESSIONAL	STRIPE_PRICE_PROFESSIONAL environment variable
ENTERPRISE	STRIPE_PRICE_ENTERPRISE environment variable

Add-ons: Optional premium features (AI receipt scanning, advanced route optimization, API access) can be enabled or disabled per tenant from the tenant detail page.

9.9 Audit Logs

Platform audit logs record every significant action across all tenants. Navigate to Audit Logs from the admin sidebar. Filter by tenant ID to see actions for a specific business.

Audit log columns:

Column	Description
Tenant	The business the action was performed in
User	The user who performed the action
Action	What was done (e.g., CREATE, UPDATE, DELETE)
Entity Type	The type of record affected (e.g., Invoice, Customer)
Entity ID	The ID of the specific record
Timestamp	Date and time of the action
IP Address	The IP address of the user at time of action

Logs are paginated at 50 per page. Tenant admins can view audit logs scoped to their own tenant only — they cannot see other tenants' logs.

[SCREENSHOT: 9.9-audit-logs.png]

9.10 Tenant Settings (Tenant Admin)

A TENANT_ADMIN can configure the following from their Settings menu:

Branding (Settings → Business Profile): Business name, logo upload (PNG, JPG, or SVG, max 5 MB), and primary brand color.

Email / SMTP (Settings → Email): SMTP host, port, encryption (TLS or SSL), sender name, sender email, username, and password. Use Test Email to verify the configuration before saving. The password is stored encrypted and is never shown after saving.

Google OAuth (Settings → Integrations): Client ID, Client Secret, Callback URL, and an Enable/Disable toggle. When enabled, customers and drivers can log in using their Google account. The client secret is stored encrypted and is never shown after saving.