Type Conversion in C++





Type Conversion

The conversion of a variable from one data type to another is called Type Conversion. Type conversion in C++ is most commonly used to perform mathematical and logical operations on two variables with different data types.

Type Conversion

Types


Type conversion is the method of converting one data type to another.

There are two types of Type Conversions in C++:

- ✓ Implicit Type Conversion
- ✓ Explicit Type Conversion

The Implicit Type Conversion is where the type conversion is done automatically by the compiler. It does not require any effort from the programmer. The C++ compiler has a set of predefined rules. The compiler automatically converts one data type to another based on these rules. Therefore, implicit type conversion is also known as automatic type conversion.

Higher Data Type



Lower Data Type

By - Mohammad Imran

Example - 1

```
#include <iostream>
using namespace std;
int main()
     int iVar;
     float fVar = 20.5;
     iVar = fVar;
     cout << "iVar = " << iVar << endl;
     cout << "fVar = " << fVar << endl;</pre>
     return 0;
```

OUTPUT

```
iVar = 20
fVar = 20.5
```

```
#include <iostream>
using namespace std;
class Conversion
  int integer;
  char character;
  public:
  Conversion()
     integer = 50;
     character = 'a';
```

```
void intChar()
  integer = integer + character;
  cout << "50 + 'a' = " << integer
  << endl;
void intFloat()
  float f = integer + 1.5;
  cout << "f + 1.5 = " << f << endl;
```

Example - 2

```
int main()
{
    Conversion cn;
    cn.intChar();
    cn.intFloat();
    return 0;
}
```

OUTPUT

$$50 + 'a' = 147$$

f + 1.5 = 148.5

Explicit Type Conversions are those conversions that are done by the programmer manually. In other words, explicit conversion allows the programmer to typecast (change) the data type of a variable to another type. Hence, it is also called typecasting.

Explicit type conversion in C++ can be done in two ways:

- ✓ Conversion using the Assignment Operator
- ✓ Conversion using the Cast Operator

Explicit Type Conversion Conversion by Assignment Operator

Explicit typecasting in C++ is done using the assignment operator is also referred to as a forced casting.

It can be done in two ways:

- ✓ C-Style Type Casting
- ✓ Function Style Type Casting

C-Style Type Casting

Example - 3

```
#include <iostream>
using namespace std;
int main()
  char char var = 'a';
  int int var;
  int var = (int) char var;
  cout << "char var: " << char var << endl;</pre>
  cout << "int var: " << int var << endl;</pre>
  return 0;
```

OUTPUT

```
char_var = a
Int_var = 97
```

```
#include <iostream>
using namespace std;
int main()
     int int var = 17;
     float float var;
     float var = float(int var) / 2;
     cout << "float var: " << float var << endl;</pre>
     return 0;
```

<u>OUTPUT</u>

float_var: 8.5

To perform this conversion, the idea is to use the constructor to perform type conversion during the object creation. Below is the example to convert **int** to **user-defined** data type:

```
#include <bits/stdc++.h>
using namespace std;
class Time
  int hour;
  int mins;
  public:
  Time()
     hour = 0;
     mins = 0;
```

```
Time (int t)
  hour = t / 60;
  mins = t % 60;
void Display()
   cout << hour << " Hrs" << endl;</pre>
   cout << mins << " Mins" << endl;</pre>
```

Example - 5

```
int main()
{
    Time T1;
    int dur = 95;
    T1 = dur;
    T1.Display();
    return 0;
}
```

OUTPUT

1 hrs
35 mins

Example - 5

Explanation of main()

Object Creation:

Time T1

Creates an object **T1** of type **Time** using the default constructor.

At this point, T1 has hour = 0 and mins = 0

Integer Assignment:

```
int dur = 95; T1 = dur;
```

dur is an integer with a value of 95. This line attempts to assign an integer value to T1.

By - Mohammad Imran

Example - 5

Key Points

The assignment $\mathtt{T1} = \mathtt{dur}$; is not directly supported by the class as it doesn't have an assignment operator that takes an \mathtt{int} . This causes the code to fail to compile unless the compiler can implicitly convert int to \mathtt{Time} .

If the compiler provides implicit conversion (which is non-standard and compiler-specific), it would use the constructor Time(int t) to convert dur into a Time object and then assign it to T1.

By - Mohammad Imran

In this conversion, the **from** type is a class object and the **to** type is primitive data type. The normal form of an overloaded casting operator function, also known as a conversion function. Below is the syntax for the same:

```
#include <bits/stdc++.h>
using namespace std;
class Time
  int hrs, mins;
  public:
  Time(int, int);
  operator int();
  ~Time()
     cout << "Destructor" << endl;</pre>
```

```
Time::Time(int a, int b)
  hrs = a;
  mins = b;
Time::operator int()
  cout << "Class To Basic" << endl;</pre>
  return (hrs * 60 + mins);
```

```
void TypeConversion(int hour, int mins)
  int duration;
  Time t(hour, mins);
  duration = t;
  cout << "Total Minutes: " << duration << endl;</pre>
  cout << "2nd method operator overloading " << endl;</pre>
  duration = t.operator int();
  cout << "Total Minutes are " << duration << endl;</pre>
  return;
```

Example - 6

```
int main()
{
   int hour, mins;
   hour = 2;
   mins = 20;
   TypeConversion(hour, mins);
   return 0;
}
```

OUTPUT

```
Class To Basic
Total Minutes: 140
2nd method operator overloading
Class To Basic
Total Minutes are 140
Destructor
```

Type Conversion

Using Cast Operator

A Cast operator is an **unary operator** which forces one data type to be converted into another data type. C++ supports 4 types of casting:

- √ Static Cast
- ✓ Dynamic Cast
- ✓ Const Cast
- ✓ Reinterpret Cast

Cast Operator

Static Cast

The Static Cast is the simplest among all four types of Casting in C++. The static cast can perform all the conversions that are done implicitly such as int to float or pointer to void.

It can perform upcast (conversion from a derived class to a base class) operations and downcast (conversion from a base class to a derived class) operations.

Syntax:

static cast <datatype> (expression)

```
#include <iostream>
using namespace std;
int main()
  double num = 3.7 * 5.5;
  cout << "Before static cast " << endl;</pre>
  cout << "num = " << num << endl;
  int cast var;
  cast var = static cast <int> (num);
  cout << "After static cast" << endl;</pre>
  cout << "cast var = " << cast var;</pre>
  return 0;
```

OUTPUT

```
Before static_cast
num = 20.35
After static_cast
cast_var = 20
```

1. static_cast for primitive data type pointers:

```
#include <iostream>
using namespace std;
int main()
  int a = 10;
  char c = 'a';
  int* q = (int*)&c;
  int* p = static cast<int*>(&c); //Error
  return 0;
```

<u>OUTPUT</u>

Error
Undefined Behavior

Static Cast Behavior in Different Scenario

Explanation of the Code:

Casting the Address of 'c' to 'int*': int *q = (int*) &c

- √ (int*)&c performs a C-style cast, converting the address of the char variable c to an int*.
- ✓ This line essentially tells the compiler to treat the address of the char variable as if it points to an int.
- ✓ This cast can be unsafe because char and int have different sizes and alignment requirements. char is usually 1 byte, while int is typically 4 bytes. This can lead to alignment issues or incorrect data access.

By - Mohammad Imran

Static Cast Behavior in Different Scenario

Explanation of the Code:

Static Cast of Address of 'c' to 'int*': int *p = static_cast<int*>&c

- ✓ static_cast<int*>(&c) attempts to use static_cast to convert the address of c to int*.
- ✓ Unlike a C-style cast, static_cast in C++ is designed to perform more type-safe conversions, but it still cannot change the fundamental nature of the data being pointed to.
- ✓ In this case, static_cast<int*>(&c) is effectively equivalent to the C-style cast and will result in the same issues.

By - Mohammad Imran

Static Cast Behavior in Different Scenario

2. Converting an Object using a User-Defined Conversion Operator

static_cast is able to call the conversion operator of the class if it is defined. Let's take another example of converting an object to and from a class.

2. Converting an Object using a User-Defined Conversion Operator

```
#include <iostream>
#include <string>
using namespace std;
class Integer
  int x;
  public:
  Integer(int x in = 0): x{ x_in }
     cout << "Constructor Called" << endl;</pre>
```

2. Converting an Object using a User-Defined Conversion Operator

```
// user defined conversion operator to string type
operator string()
{
   cout << "Conversion Operator Called" << endl;
   return to_string(x);
}
</pre>
```

int main()

// Driver code

2. Converting an Object using a User-Defined Conversion Operator

```
Integer obj(3);
string str = obj;
obj = 20;

// using static_cast for typecasting
string str2 = static_cast<string>(obj);
obj = static_cast<integer>(30);
return 0;
```

<u>OUTPUT</u>

```
Constructor Called
Conversion Operator Called
Constructor Called
Conversion Operator Called
Constructor Called
```

User-defined Conversion Operator:

- ✓ operator string() defines a conversion operator that allows an integer object to be implicitly converted to a string.
- ✓ This method prints "Conversion Operator Called" and converts the integer x to a string using to_string(x).

Creating an integer Object:

integer obj(3); -

- \checkmark Constructs an integer object with x initialized to 3.
- ✓ Outputs: "Constructor Called".

Implicit Conversion to 'string':

```
string str = obj; -
```

- ✓ The obj is implicitly converted to a string using the conversion operator.
- ✓ Outputs: "Conversion Operator Called".
- ✓ The str variable is assigned the value "3".

Assignment with 'int':

$$obj = 20;$$

✓ This line is valid but doesn't involve a user-defined conversion operator.

It assigns 20 to x.

By - Mohammad Imran

Explicit Conversion to 'static_cast':

string str2 = static_cast<string>(obj); -

- ✓ This explicitly uses **static_cast** to convert obj to string by invoking the user-defined conversion operator.
- ✓ Outputs: "Conversion Operator Called".
- ✓ str2 is assigned the value "20" (since obj was modified to 20).

Explicit Conversion to integer using 'static_cast':

obj = static_cast<integer>(30); -

- ✓ This creates a temporary integer object with x initialized to 30 using
 the constructor and assigns it to obj.
- ✓ Outputs: "Constructor Called".

Static Cast Behavior in Different Scenario

3. Static Cast for Inheritance

static_cast can provide both upcasting and down casting in case of inheritance. The following example demonstrates the use of static_cast in the case of upcasting.

```
#include <iostream>
using namespace std;
class Base
  public:
   Base()
      cout << "Base Constructor Called" << endl;</pre>
   virtual ~Base() // Virtual destructor for proper cleanup
      cout << "Base Destructor Called" << endl;</pre>
   void baseFunction()
      cout << "Function in Base Class" << endl;</pre>
```

```
class Derived : public Base
  public:
  Derived()
      cout << "Derived Constructor Called" << endl;</pre>
  ~Derived()
      cout << "Derived Destructor Called" << endl;</pre>
  void derivedFunction()
      cout << "Function in Derived Class" << endl;</pre>
```

Static Cast

Behavior in Different Scenario

Example - 10

```
// Driver code
int main()
  Derived d1;
  // Implicit cast allowed
  Base* b1 = (Base*)(&d1);
  b1->baseFunction();
  // upcasting using static cast
  Base* b2 = static cast<Base*>(&d1);
  return 0;
```

OUTPUT

Base Constructor Called
Derived Constructor Called
Function in Base Class
Derived Destructor Called
Base Destructor Called

Static Cast

Behavior in Different Scenario

Example - 10

Explanation: Difference between

```
Base* b1 = (Base*)(&d1);
Base* b2 = static_cast<Base*>(&d1);
```

The two statements Base* b1 = (Base*)(&d1); and Base* b2 = static_cast<Base*>(&d1); both perform casting from a Derived pointer to a Base pointer, but they differ in several important aspects regarding type safety, compiler checks, and general usage.

Explanation

1. C-Style Cast:

Base*
$$b1 = (Base*)(&d1);$$

- **Description:** This is a C-style cast. It directly converts the address of d1 to a Base*.
- Behavior
 - ✓ **Type Safety:** The C-style cast is a more general cast that can perform various types of conversions, including static, reinterpret, and const casts. It does not provide compile-time checks to ensure the safety of the conversion.
 - ✓ **Error Handling:** If the cast is not safe or results in undefined behavior, the compiler will not catch it. The responsibility for ensuring the cast is correct lies with the programmer.
 - ✓ **Usage:** C-style casts are less preferred in C++ due to their lack of specificity and safety. They can lead to ambiguous or unsafe conversions.

1. Static Cast:

• **Description:** This is a static cast, which is a more explicit and type-safe cast introduced in C++.

Behavior

- ✓ **Type Safety:** The static performs compile-time checks to ensure that the cast is safe. For upcasting (casting from a derived class to a base class), it is generally safe and allowed, but it still performs checks to ensure that the conversion is logically correct.
- ✓ **Error Handling:** If static cast encounters a type mismatch or an incorrect conversion, it will generate a compile-time error. This helps in catching potential issues earlier in the development process.

Static Cast Behavior in Different Scenario

```
#include <iostream>
using namespace std;
class Base
class Derived: private Base //privately access
};
int main()
   Derived d1;
   Base* b1 = (Base*)(&d1);
   Base* b2 = static cast<Base*>(&d1); // static cast not allowed
   return 0;
```

Static Cast Behavior in Different Scenario

4. Cast 'to and from' Void Pointer

static_cast operator allows casting from any pointer type to void pointer and vice versa.

```
#include <iostream>
using namespace std;
int main()
  int i = 10;
  void* v = static cast<void*>(&i);
  int* ip = static cast<int*>(v);
  cout << *ip;</pre>
  return 0;
```

OUTPUT

10

Cast Operator Dynamic Cast

A cast is an operator that converts data from one type to another type. In C++, dynamic casting is mainly used for safe downcasting at run time. To work on **dynamic_cast** there must be one virtual function in the base class. A **dynamic_cast** works only polymorphic base class because it uses this information to decide safe downcasting.

Syntax: dynamic_cast <datatype> (expression)

Cast Operator Dynamic Cast

Downcasting: Casting a base class pointer (or reference) to a derived class pointer (or reference) is known as downcasting. In figure 1 casting from the Base class pointer/reference to the "derived class 1" pointer/reference showing downcasting (Base -> Derived class).

Upcasting: Casting a derived class pointer (or reference) to a base class pointer (or reference) is known as upcasting. In figure 1 Casting from Derived class 2 pointer/reference to the "Base class" pointer/reference showing Upcasting (Derived class 2 -> Base Class).

As we mention above for dynamic casting there must be one Virtual function.

```
class Base
  public:
  virtual void print()
     cout << "Base print" << endl;</pre>
class Derived: public Base
 public:
  void print()
     cout << "Derived print" << endl;</pre>
```

Cast Operator Dynamic Cast Example - 13

```
int main()
  Base* b = new Derived;
  Derived* d = dynamic cast <Derived*>(b);
  if (d != NULL)
     cout << "dynamic cast done" << endl;</pre>
  else
     cout << "dynamic cast not done" << endl;</pre>
  return 0;
```

OUTPUT

[Error] cannot dynamic_cast 'bp' (of type 'class Base*') to type 'class Derived2*' (source type is not polymorphic)

Understanding the Error

This error arises because dynamic_cast requires the source type to be polymorphic. In C++, a class is considered polymorphic if it has at least one virtual function.

Cast Operator

Const Cast

The Const Cast is used to change an object's constant value or to remove the constant nature of any object. Const cast is generally used in programs with one or more objects with some constant value(s) that need to be changed at some point in the program.

For a const cast operation to be successful, the pointer and the source being cast should be of the same data type.

Syntax: const_cast <datatype> (expression)

```
#include <iostream>
                                                 OUTPUT
using namespace std;
                                    The old value of ptr1 is: 10
                                    The new value of ptr1 is: 3
int main()
  const int var1 = 10;
  const int* ptr1 = &var1;
  cout << "The old value of ptr1 is: " << *ptr1 << end1;</pre>
  int* ptr2 = \langle int* \rangle (ptr1);
  *ptr2 = 3;
  cout << "The new value of ptr1 is: " << *ptr1 << end1;</pre>
  return 0;
```

Cast Operator

Reinterpret Cast

The Reinterpret Cast is used to convert one pointer type to another, regardless of whether the classes are related. It does not check whether the pointer type and data pointed out by the pointer are the same. That is why reinterpreting cast should not be used unless required.

Reinterpret cast is mainly used to work with bits. It does not return any value. It directly changes the pointer type. If reinterpret cast is used on boolean values, the boolean values are converted to integers - 0 for false and 1 for true.

Syntax: reinterpret_cast <datatype> (expression)

```
#include <iostream>
                                               OUTPUT
using namespace std;
                                   The old value of ptr1 is: 10
                                   The new value of ptr1 is: 3
int main()
  int* ptr = new int(98);
  char* ch = reinterpret cast <char*> (ptr);
  cout << "The value of *ptr is: " << *ptr << endl;</pre>
  cout << "The value of ptr is: " << ptr << endl;</pre>
  cout << "The value of *ch is: " << *ch << endl;
  cout << "The value of ch is: " << ch << endl;</pre>
  return 0;
```

Coding Questions

Question - 1

Write a C++ program to overload unary pre-increment operator (++) to increment by default 2 when used with object.

Sample Output

$$X = 10$$

$$X = 12$$

Question - 1

Write a C++ program to overload binary minus (-) operator using reference and friend function.

Click here to see code

By - Mohammad Imran

QUIZ

Quiz - 1

```
#include <iostream>
                                                   ANSWER
using namespace std;
                                         Value of pi is: 3.14159
int main()
                                          Value of intPi is: 3
  double pi = 3.14159;
  int intPi = static cast<int>(pi);
  cout << "Value of pi is: " << pi << endl;</pre>
  cout << "Value of intPi is: " << intPi << endl;</pre>
  return 0;
```

Quiz - 2

```
#include <iostream>
using namespace std;
int main()
  int num = 65;
  char* ptr = reinterpret cast<char*>(&num);
  cout << "Integer value is: " << num << endl;</pre>
  cout << "Character is: " << *ptr << endl;</pre>
  return 0;
```

ANSWER

Integer value is: 65 Character is: A

Quiz - 3

```
#include <iostream>
using namespace std;
void printValue(const int* ptr)
  int* modifiablePtr = const cast<int*>(ptr);
  *modifiablePtr = 100;
  cout << "Value of x: " << *ptr << endl;</pre>
int main()
  int x = 10;
  printValue(&x);
  cout << "Modified x: " << x << endl;</pre>
  return 0;
```

ANSWER

Value of x: 100

Modified x: 100