



Metal Barrel Tutorial


Important concepts covered: select loops, extrude loops, scale, bevel




Let's start by deleting the default cube (DEL or X) and adding a new cylinder to the scene (SHIFT+A → MESH → Cylinder):




Next, change the number of vertices to 16. You can do this by clicking on the little window that has appeared on the bottom left corner of the screen:




Now enter edit mode and move the cylinder up (G+Z) by 1:




Change to face selection mode, select the top face of the cylinder and move it along the Z axis (G+Z) by 1.7:



Now add a loop cut using 2 cuts (to do this, you can press CTRL + R and type '2' or scroll the middle mouse button to increase the number of cuts until it has 2 cuts, then to confirm double click the left mouse button):




With these loops selected, press CTRL + B in order to bevel them and type 0.03:




Now add another edge loop on the top part of the barrel (CTRL+R), click once and then type -0.9 to slide it to the top:




Now repeat the process but now for the bottom part of the barrel: add another edge loop on the bottom part of the barrel, click once and then type 0.9 to slide it to the bottom:




Now change to face selection mode and select all the thin face loops created (in order to select a loop, you can hold ALT and then left click on top of a face of the loop that you want. to select multiple loops, you can hold SHIFT + ALT and then left click):




Now, press ALT + E and select “Extrude Along Normals” and then type 0.05:







Now change to edge selection mode and select all the edge loops of the details created (in order to select multiple edge loops, you can hold ALT and then left click on top of an edge of the first loop that you want to select. Then, you can hold SHIFT + ALT and then keep left clicking until you have all the loops that you want selected):




Now hit CTRL + B to bevel then type 0.02 and increase to 2 segments. To do this, you can use the scroll of the mouse to increase/decrease the number of segments:




Now change back to face selection mode and select the top face of the barrel:




Inset it (I) by 0.05 and then extrude it (E) by -0.13:




Then, scale it down (S) by 0.8:




Next, inset the face (I) by 0.6 and move it along the X axis (G+X) by -0.4:




Then extrude it (E) by 0.15:




Then inset it (I) by 0.03 and then extrude it (E) by -0.1:





Now to add a final detail, add 2 edge loops (CTRL+R, 2) on this cylinder:




Change to face selection mode, select the middle face loop, press ALT + E, select "Extrude Along Normals" and type 0.02:




Now change back to object mode, right click on the viewport and select "Shade Smooth":




As you can see the mesh looks weird. In order to fix is, go to “Object Data Properties” → “Normals” and check “Auto Smooth”:






Now add a bevel modifier to the selected object and set the Amount to 0.002, the Segments to 2 and check “Harden Normals” under “Shading” tab:



Finally, add a Subdivision Surface modifier:



Now the barrel looks round and polished:

