Problem

In <u>part one</u> we built and configured the <u>WDS</u> Server. Now you need to prepare the reference Windows 8 machine so that you can 'capture' its image.

Solution


Before you start, make sure that the machine you are imaging has **PLENTY** of room on one of its local drive(s), because it copies the image locally, before it sends it to <u>WDS</u>.

Place Your Reference Windows 8 Machine in Audit Mode

To put all the software on your reference machine and configure it how you like, the machine needs to be in 'Audit Mode' before you start. There are **TWO** ways to put the machine into audit mode. **Note**: While a machine is in audit mode, it will log on automatically as the Administrator, and every time the machine boots sysprep will launch (in anticipation of you needing it).


Option 1: A Newly Built Machine

1. When you have first built the Windows 8 machine, you will see the screen below, Press **CTRL+SHIFT+F3**, the machine will automatically reboot and enter audit mode.




Option 2: You Are Already in Windows


2. You can also put a Windows 8 machine into audit mode by running the sysprep executable with the /audit switch.




3. Once in Audit mode, install all the program and configure all the settings you want in your master image. When you are happy run the sysprep program, (Or simply reboot, as sysprep launches at every boot when you are in audit mode).



4. Tick the 'Generalize' option, select either shutdown or reboot, (If you choose reboot **make sure** the machine is ready to <u>pXe</u> boot from the network, and the boot order has the <u>NIC</u> **BEFORE** the hard drive, or sysprep will start and rebuild the machine before it's imaged).



5. Sysprep will run, and shutdown or reboot as requested.



6. When the machine boots press F12 to boot from the \underline{WDS} server.



7. **Note**: Now you can see why (in <u>part one</u>) we called the boot image 'Capture an Image' and the capture 'Capture an Image'. Select the capture option.




8. <u>WindowsPE</u> will run at the welcome screen > Next, **Note**: If the process fails at this point, usually it's because the network card driver for this machine **IS NOT** in the boot image. <u>Adding Drivers to Images on Windows Deployment Services</u>




9. Select the volume that you want to image, (**Note**: It will **NOT** be C: that's reserved, usually it's D:) > Give the image a name, this is the name you will see in the <u>WDS</u> console, and when you are imaging the target machines > Enter a comment/description > Next.

Windows Deployment	Services Image Capture Wizard	
	petenetlive	9
contain operating systems that ha	r this image. Note that you will only see volumes that when prepared with Sysprep.	ò
Volume to capture:		
D:\	~	
Image name:		
Windows8_v1		
Image description:		
1.0		
	D ₂	
	< Back Next > Cancel	


10. Browse.



11. Navigate to a local drive, and give the image a name with a .wim extension > Save.




12. Tick the box to upload the image > Supply IP/Name of the WDS server > Connect.




13. Supply credentials to log onto the \underline{WDS} server > OK.




14. Once authenticated you can select the image group we setup in <u>part one</u> > Next.




15. The image will be created on the reference machine.



16. Then it will be uploaded to the <u>WDS</u> Server.



17. When complete click Finish. At this point the reference machine will reboot and rebuild itself.



18. Back in the Windows Deployment Services management console yo will see the image you have just uploaded in your image group. **Note**: Sometimes it can take a while to appear, be patient!

